Performance Analytics



Setup, Installation and Administration Guide

VERSION 9.6.0 (47)

DATE 04/2023

© 2023 cubus AG Copyrighted material. All rights reserved. Restricted use only.

Microsoft, Excel, Windows and Windows Server are trademarks or registered trademarks of Microsoft Corporation.

All other names of companies, products and/or services are trademarks of their respective owners. Essbase is a registered trademark of Oracle.

IBM, TM1, and Cognos are trademarks or registered trademarks of International Business Machines Corp.

Subject to change without notice.

All rights reserved. No part of this document may be reproduced, translated or transmitted in any form or by any means, electronic, optical or mechanical, including photocopy, recording, or any information storage system, for any purpose other than the purchaser's personal use, without the prior written consent of cubus AG.

cubus AG assumes no responsibility for typographical errors or inaccuracies in this documentation or for the use, reliability, interoperability, merchantability, or fitness for a particular purpose of the software product and/or programs described herein. This manual is subject to periodic updates. cubus AG reserves the right to modify, augment, or improve this document as well as the products and/or programs described herein.

Contents

Part I	Introduction	1
1	Audience	1
2	Forward-looking statements	1
3	Accessibility features	
4	Samples disclaimer	
Part II		3
1	Performance AL Server	3
2	Performance AL Explorer	
3	Performance AL Desktop Explorer	
4	Performance AL Client	
4		
	Performance AL Desktop	
6	Performance AL Anywhere Client	
7	Repository	
8	Providers	
9	Data sources	
10	Slave servers	5
Part III	Preparing to install	6
1	Supported environments	6
2	Supported languages	6
3	System requirements	6
	Performance AL Server requirements	7
	Additional requirements	
	Performance AL Explorer requirements	
	Performance AL Desktop Explorer requirements	
	Performance AL Client requirements	
	Performance AL Desktop requirements	
	Performance AL Anywhere requirements	
	Upgrade requirements	
4	Configuring data sources	
	Configuring Oracle Essbase data sources	
-	Configuring Microsoft Analysis Services data sources	
5	Preparing the operating system	
	Preparing Microsoft Windows Server Preparing Microsoft Windows 10	
C		
6	Preparing Microsoft Azure	
7	Preparing Keycloak	18
Part IV	Installing Performance Analytics	21

1	Installing Performance AL	21
	Selecting the mail server	21
	Installing Performance AL with default settings	21
	Installing Performance AL with custom settings	22
	Selecting the install components	22
	Specifying the catalog providers	23
	Specifying the security providers	24
	Completing the custom installation	26
2	Installing Performance Analytics using silent install	26
3	Installing Performance Analytics Desktop Explorer	26
4	Installing Performance Analytics Client	
5	Installing Performance Analytics Desktop	
6	Installing Performance AL Client from a link on an HTML page	
Ū	Description of the example page	
	Installing the Performance AL Client after editing the HTML page	
	Checking the security settings of the internet browser	
	Changing the language setting for Performance AL Client	
7	Configuring Performance AL Server	
,	Specifying a Performance AL Server	
	Configuring the data source	
	Configure IBM Cognos TM1	
	Configure Microsoft Analysis Services or SQL Analysis Services	
	Configure Oracle Essbase	
	Run the Performance AL Web Service on another Server than the Performance AL Server	
8	Installing maps	36
	Adding maps for use by the Performance AL	
	Understanding layers and shapes	
	Understand the mapping file	37
	Library	37
	Layer	38
	Mapping	39
9	Installing images for use in Performance Analytics	41
10	Uninstalling Performance AL components	
	To uninstall Performance AL	
	To uninstall Performance AL Desktop	
	To uninstall Performance AL Desktop Explorer	
	To uninstall Performance AL Client	
11	Configuring access for authentification portals	42
Part V	Configure the service and the configuration file	44
1	Change the Account that runs the Performance AL service	лл
Т	Giving the account the rights to replace a process level token	
	Giving the account the rights to act as part of the operating system	
	Giving the account the rights to impersonate a client after authentication	
	Giving the account the rights to log on as a service	
	Giving the account the rights for Local Administrator	
2	Log on locally	
Z		40

3	Editing the configuration file	46
	Configuration file elements	
	<configsections></configsections>	
	<catalogprovider></catalogprovider>	
	<securityproviders></securityproviders>	
	<logproviders></logproviders>	
	<appsettings></appsettings>	
	<datasourcesettings></datasourcesettings>	
	<system.net></system.net>	53
	Configuring the catalog provider	53
	Configuring the SQL Server catalog provider	53
	Configuring the Oracle catalog provider	54
	Configuring the security provider	55
	Configuring the IBM Cognos 8 Security Provider	55
	Configuring the TM1 Security Provider	57
	Configuring the Windows Integrated Security Provider	59
	Configuring the Forms Security Provider	60
	Configuring the Anonymous Security Provider	
	Configuring the Essbase Security Provider	
	Configuring the OAuth2 Security Provider	
	Configuring the OIDC Security Provider	
	Configuring the Log Providers	69
	Log categories	
	Log components	
	Log providers	
	Configuring the Event Log Provider	
	Configuring the XML Log Provider	
	Configuring the Mail Log Provider	
	Configuring the SQL Server Log Provider	
	Configuring the Oracle Log Provider	
	Configuring the Shared Backend Log Provider	
	Configuring the mail-server	
Part VI	Performance AL Server API	78
1	URL API	
2	URL API syntax	
	Generic option parameters	
	Action: render	
	Action: updatepreload	
	Action: image	
	Action: customitem	
	Action: listitems	
	Action: listnamedusers	
	Action: listconcurrencycounters	
	URL API - encoded characters	
3	Error messages	
Part VII	Performance AL Explorer	96

Part VII Performance AL Explorer

1	Starting Performance Analytics	
2	The interface of Performance AL Explorer	
3	Managing Performance AL Server	
	Changing the environmental properties of Performance AL Server	
	Changing the properties of the Performance AL repository	
	Changing the server settings for a Performance AL Server	
	Viewing the version information for a Performance AL Server	
	Removing a Performance AL Server	
4	Managing folders and items	
	Folders that are added during the installation of Performance AL	100
	Managing items	100
	Creating an item	101
	Creating a shortcut item	102
	Opening items	102
	Specifying a data source item	
	Specifying a database item	
	Changing the properties of an item	
	Creating user-defined properties	
	Changing the MIME type of a custom item	
	Connecting a view item to a database item	
_	Associating a view item with a canvas	
5	View item	
6	Shortcut item	107
	Property inheritance	108
7	Database wizard	108
	Using the Database Wizard	108
8	Process distribution	109
	How it works	109
	Default behavior	
	Group Cubes from this Data Source	
	Group Cubes by Application	
	Each Cube separately	
	Inheritance	
	Using Slave Servers	
	Enabling process distribution on Performance AL Server	
	Configuring process distribution for a data source item	
	Configuring process distribution on a database item	
~	Adding a slave server to Performance AL Server	
9	Accounts	
	Viewing Accounts	
10		
	Item security	
_	System security	
11	Sessions	
12	Item permissions and roles	121
	Available permissions	121
	Permissions implications	122

1	Starting Performance AL Desktop Explorer	140
VIII	Performance AL Desktop Explorer	140
22	Desktop Application	138
21	Comments	137
	CXO Software Integration	
	Limitations	
	User Management	
	Connection User	
	User Token	
	Portal Integration Portal Web Page	
20	Integration	
20	Viewing concurrent users	
	Viewing named users	
19	Monitoring	
10		
18	Search paths	
10		
	Setting a filter on the Log entries Activity Log	
	Showing and browsing the Log entries	
17	Server Log	
<u> </u>	Terminating Active Sessions	
	Viewing Active Sessions	
16	Active Sessions	
	Viewing the system policy Evaluation User	
	Changing properties of the Evaluation User item role	
	Evaluation User item roles	
	Changing properties of the Evaluation User system role	
	Evaluation User system roles	
	Initial situation	
15	Evaluation roles and policies	127
	Adding System Policies	127
	Logon User	
14	System Policies	126
	Editing system roles	
	Adding System Roles	
	System roles	
	Setting system permissions	
	Available permissions	
13	System permissions and roles	124
	Adding Item Policies	
	Item Policies	
	Opening an item role	
	Adding an item role	
	Item roles	
	Setting permissions for an item	100

Part

2	Changing the language of Performance AL Desktop Explorer	140
3	Adding a Performance AL Server	141
4	Removing a Performance AL Server	141
5	Items	141
6	Default settings after installation	142
7	Adding items	
8	Managing items	
9	Opening items	
9	Security warning when opening a view	
	Opening an item	
10	The folder item in Performance Analytics Desktop Explorer	
10	Creating a folder item	
	Changing the properties of a folder item	
	Creating a data source item	
	Specifying the details of a data source item	146
	Changing the properties of a data source item	147
11	Database item in Performance Analytics Desktop Explorer	147
	Creating a database item	147
	Specifying the details of a database item	148
	Changing the properties of a database item	148
12	View item in Performance Analytics Desktop Explorer	148
	Creating a view item	
	Opening a view after creation of a view item	
	Changing the properties of a view item	
13	Canvas item in Performance Analytics Desktop Explorer	
	Creating a canvas item	
	Opening a canvas after creation of a canvas item	
	Associating a view item with a canvas with Performance AL Desktop Explorer	
	Changing the properties of a canvas item	
14	Image item in Performance Analytics Desktop Explorer	
	Creating an image item Changing the properties of an image item	
15		
15	Custom item in Performance Analytics Desktop Explorer Creating a custom item	
	Opening a custom item	
	Changing the MIME type of a custom item	
	Changing the properties of a custom item	
16	Shortcut item in Performance Analytics Desktop Explorer	
10	Creating a shortcut item	
	Property inheritance	
17	Database wizard in Performance Analytics Desktop Explorer	
18	Item system properties and view system properties	
19	Properties	
13	User-defined properties	
	Creating user-defined properties	

20	Managing Performance AL Server with Performance AL Desktop	150
	Explorer	
21	Viewing the version information	
22	Accounts	
	Viewing Accounts	
	Deleting Accounts	. 159
23	Security	160
	Item security	. 160
	System security	. 160
24	Sessions	161
25	Item permissions and roles	161
	Available permissions	. 161
	Permissions implications	. 162
	Setting permissions for an item	. 163
	Item roles	. 163
	Adding an item role	. 164
	Opening an item role	. 164
	Item Policies	. 164
	Adding Item Policies	. 164
26	System permissions and roles	165
	Available permissions	. 165
	Setting system permissions	. 166
	System roles	. 166
	Adding System Roles	. 166
	Editing system roles	. 167
27	System Policies	167
	Logon User	. 167
	Adding System Policies	. 167
28	Evaluation roles and policies	167
	Initial situation	. 168
	Evaluation User system roles	
	Changing properties of the Evaluation User system role	
	Evaluation User item roles	
	Changing properties of the Evaluation User item role	
	Viewing the system policy Evaluation User	. 169
29	Active Sessions	169
	Viewing Active Sessions	. 169
	Terminating Active Sessions	. 170
30	Server Log	170
	Showing and browsing the Log entries	. 170
	Setting a filter on the Log entries	. 171
31	Search paths	173
	Setting the search paths	. 173
32	Monitoring	173
	Viewing named users	
	Viewing concurrent users	
33	Comments	

Part IX	Performance AL Desktop	177
1	Performance AL Desktop URL parameters	177
Part X	Performance AL Anywhere	179
1	Configuring the web application	179
2	Configuring the REST server	179
	Configuration parameters	179
	Configuration for SSL	
3	Configuring the mobile device	
	Windows Integrated Authentication	
4	Functionality	
5	PowerBI Visual	182
Part XI	Appendix: dataSourceSettings	184
1	TM1	184
2	MSAS	184
3	Essbase	185
4	mdx	185
5	Data source type TM1	185
	Element <tm1></tm1>	
	Element <adminhosts></adminhosts>	186
	Element <authenticateusingwia></authenticateusingwia>	
	Element <authenticateusingwiaexceptions></authenticateusingwiaexceptions>	
	Element <server></server>	
	Element <allowwia></allowwia>	
	Element <allowoidc> Element <mdx></mdx></allowoidc>	
	Element <compliant></compliant>	
	Element <msextensions></msextensions>	
	Element <evcalculations></evcalculations>	
	Element <solveorderbase></solveorderbase>	
	Element <usepersonalizeddimension></usepersonalizeddimension>	190
6	Data source type MSAS	190
	Element <msas></msas>	190
	Element <ptstimeout></ptstimeout>	190
	Element <redirecturinative></redirecturinative>	
	Element <provider></provider>	
	Element <allowwia></allowwia>	
	Element <allowoidc></allowoidc>	
	Element <dimensionsfromotherperspectives> Element <mdx></mdx></dimensionsfromotherperspectives>	
	Element <ndx></ndx>	
	Element <msextensions></msextensions>	
	Element <evcalculations></evcalculations>	
	Element <solveorderbase></solveorderbase>	
	Element <amo></amo>	

	Element <dso></dso>	
	Element <servers></servers>	
	Element <server></server>	
	Element <active></active>	
	Element <ttl></ttl>	
	Element <autoreloadcache></autoreloadcache>	
	Element <reloadalloutlinesafterdimensionprocess></reloadalloutlinesafterdimensionprocess>	
	Element <reloadroleoutlinesafterrolechange></reloadroleoutlinesafterrolechange>	
7	Data source type Essbase	
	<essbase></essbase>	
	<unicode></unicode>	
	<nonunicodecodepage></nonunicodecodepage>	
8	0 //	
	<mdx></mdx>	
	<usesumformultiselect></usesumformultiselect>	203
Part XII	Appendix: Database Specific Configuration	205
1	Essbase Data Source Settings	205
2	Essbase Database Settings	206
3	TM1 Data Source Settings	206
4	TM1 Database Settings	207
5	MSAS Data Source Settings	
6	MSAS Database Settings	
Part XIII	Appendix: Preloading	212
Part XIV	Appendix: Impersonation	215
Part XV	Appendix: Essbase Drill Through	217
Part XVI	Appendix: Tools	218
1	EVCreateReport	218
2	UserManagement	221
	Creating Users	
	Deleting Users	
	Listing Users	
3	EncryptConsole	223
Part XVII	Appendix: Migration	224
1	Performance AL 9.0.2 to 9.1.0	
2		
Part XVIII	Notices	225
Part XIX	Trademarks	227
D 1 1/1/	Licenses	228

1	CURL	228
2	JsonCpp	228
3	LibXL	230
4	PDFsharp & MigraDoc	235
5	HTML Agility Pack	235
6	iTextSharp	236
7	SvgRenderer	252
8	 DotNetZip	253
9	Performance AL Anywhere Licenses	256
	МІТ	. 318
	ISC	. 318
	Zero-Clause BSD	. 318
	BSD 3	. 319
	BSD 2	. 319
	Apache 2.0	. 320
	X11 License	. 323
	WTFPL	. 323
	CC BY 4.0	. 323
	Unlicense	. 328
	CC0 1.0 Universal	. 329
	CC BY 3.0	. 331
	Academic Free License 2.1	. 335
	Zlib License	. 338
	MPL-2.0	. 338

1. Introduction

This document is intended for use with Performance Analytics. Performance Analytics provides you with a powerful tool to improve business results. Your systems administrator or supervisor will give you access to one or more sources of your data residing in the database of your organization.

Data is made available in views that are organized in a folder structure. Depending on the security set by your system administrator, it is possible to create new folders and views. You can keep folders and views to yourself or make these available to others. It is possible to create exception reports and customize these with colors to focus attention and trigger action. You can quickly generate calculations using timely, up-to-the-minute data, make charts, drill up or down to investigate your financial or operational information or drill through to your relational data. You can then save or discard these as you wish.

The Performance AL client is available as an ActiveX edition, a ClickOnce-based DesktopApp edition and as an HTML edition to display views. A view item shows the data stored in an OLAP database.

Audience

To use this guide, you should be familiar with:

- Basic Microsoft Windows administration skills
- The existing server environment and security infrastructure in your organization
- Reporting, analysis, and planning concepts
- Security issues

Forward-looking statements

This documentation describes the current functionality of the product. References to items that are not currently available may be included. No implication of any future availability should be inferred. Any such references are not a commitment, promise, or legal obligation to deliver any material, code, or functionality. The development, release, and timing of features or functionality remain at the sole discretion of cubus.

Accessibility features

This product does not currently support accessibility features that help users with a physical disability, such as restricted mobility or limited vision, to use this product.

Samples disclaimer

The Great Outdoors Company, GO Sales, any variation of the Great Outdoors name, and Planning Sample depict fictitious business operations with sample data used to develop sample applications for cubus and cubus customers. These fictitious records include sample data for sales transactions, product distribution, finance, and human resources. Any resemblance to actual names, addresses, contact numbers, or transaction values is coincidental. Other sample files may contain fictional data manually or machine generated, factual data compiled from academic or public sources, or data used with permission of the copyright holder, for use as sample data to develop sample applications. Product names referenced may be the trademarks of their respective owners. Unauthorized duplication is prohibited.

2. Components used by Performance Analytics

Performance Analytics has the following components:

- Performance AL Server
- Performance AL Explorer
- Performance AL Desktop Explorer (see note on future availability)
- Performance AL Client
- Performance AL Anywhere Client
- Performance AL Desktop
- Repository
- Databases used as providers
- OLAP data sources
- Slave servers

Each component, provider, and data source of Performance AL can be installed at different locations on the network. However to get the best performance from Performance AL for your system read the notes for each of the components. The performance of Performance AL also depends on the infrastructure of the network you use.

Performance AL Server

Performance Analytics Server is software that contains the interfaces to the catalog, log, and security providers, and the API interface protocols.

You can specify where each component is located on the system by either express or custom installation settings. The selection of an express or custom install is as follows:

- The express option installs all the software components onto the same system and sets all values to default settings. An express install will validate if SQL Server is installed on the same system as the Performance AL Server, if not the installation requests the location of the SQL Server database that you will use for the repository.
- The custom option allows you to install the separate software components onto different locations on the network.

Performance AL Explorer

Performance Analytics Explorer is the software from which you can manage Performance AL Server via your Internet browser. Performance AL Explorer can be deployed to client systems on a network by a simple URL link to the Performance AL Server. Performance AL Explorer can be launched from this link.

You can install Performance AL Explorer on the same system as the Performance AL Server, or on a different system. Either HTTP/HTTPS or TCP/IP can be used as the communication protocol. When installing Performance AL Explorer on the same system as Performance AL Server, it will by default use the TCP/IP protocol.

When installing Performance AL Explorer on a different system than the Performance AL

Server, the Performance AL Server has to be specified when the installation is complete.

Performance AL Desktop Explorer

Performance Analytics Desktop Explorer is the virtual directory software from which you can manage Performance AL Server(s) via Windows Explorer. Performance AL Desktop Explorer has more functionality for the management of views and items.

Performance AL Desktop Explorer has to be installed separately on each client system. Performance AL Desktop Explorer can also be used in organizations that do not allow Internet Information Systems to be used.

You can install Performance AL Desktop Explorer on the same system as the Performance AL Server, or on a different system. Either HTTP/HTTPS or TCP/IP can be used as the communication protocol.

When installing Performance AL Desktop Explorer on a different system than the Performance AL Server, the Performance AL Server has to be specified when the installation is complete. Refer to Specifying a Performance AL Server.

Performance AL Client

Performance Analytics Client is the software in which the user can perform ad-hoc analyses and is deployed as a client software program. The language of Performance AL Client depends of the culture and can be set either in the URL link for Performance AL Client, or as a language setting in Microsoft Internet Explorer. Either HTTP/HTTPS or TCP/ IP can be used as the communication protocol.

Performance AL Desktop

Performance AL Desktop is a ClickOnce deployable Windows Forms Application. The language of Performance AL Desktop depends on the culture and can be set either in the URL link for Performance AL Desktop or globally in the EVServer.exe.config. Either HTTP/ HTTPS or TCP/IP can be used as the communication protocol.

Performance AL Anywhere Client

Performance AL Anywhere Client is the software in which the user can perform ad-hoc analyses on devices without installing a browser add-on.

HTTP/HTTPS can be used as the communication protocol.

Repository

Performance Analytics Respository is a database that stores all the items and configuration used by Performance AL Server, including item and system security. The repository is controlled by the specified catalog provider. The best performance is obtained when the distance between Performance AL Server and the Repository is as short as possible. The performance also depends on the infrastructure of the network you use.

Providers

Providers are used to adapt the Performance AL Server installation to fit the needs of your company. A provider is software component (a dll) that provides necessary services

to Performance AL Server to extend functionality. There are three providers:

• Catalog provider

The catalog provider controls the storage of the repository. Performance AL Server can have only one catalog provider, in contrast to the security and log providers.

• Security provider

The security providers validate accounts against an existing security system. Performance AL Server does not have security accounts of its own but refers to accounts and uses the security provider to validate these accounts. The account name and credentials are validated with the security provider, that results in a valid or invalid authentication of the account. A valid authentication opens a session. Each security provider has its own system requirements and configuration.

• Log provider

The log providers used by Performance AL Server store log entries to an output destination depending on the Log Providers. When no log provider is configured for Performance AL Server, the Windows Event Log will be used to log errors of all log components and all log categories with the Log Level, Warning, Error, or Severe.

The providers are connected to Performance AL Server during the installation and configuration. The Performance AL Server must have a security and catalog provider.

Data sources

The data sources for Performance AL are the OLAP data bases that provide the raw data for Performance AL Server used for analysis. The data sources available are:

- Oracle Essbase
- Microsoft Analysis Services
- IBM Cognos TM1

Data sources do not have to be located on the same machine as Performance AL Server. Data sources can also be connected to Performance AL Server via a slave server. The use of a slave server is to enable process distribution on multiple systems.

Slave servers

A slave server can be installed and configured to a master server to provide additional server infrastructure for process distribution. You can configure one master server and multiple slave servers in your network.

Process distribution extends the memory required for processing data to enable parallel processing. Process distribution allows you to load cubes into separate processes that run parallel to the main process. By using process distribution, Performance AL can maximize the memory available for the cubes to be loaded.

If you enable process distribution, you can configure process distribution for data source and database items. Also you can use the Isolation Level to group specific cubes together and load them in separate processes.

3. Preparing to install

Before you install your cubus product, it is important to know all issues that can affect your installation strategy. Performance AL must be installed and configured correctly to integrate effectively with your existing network infrastructure.

Review the release notes before you install your product. The release notes contain latebreaking information about known issues as well as documentation updates and deprecation notices.

Before you install Performance AL, ensure that your computer and your software environment meet all applicable requirements.

Supported environments

To ensure your product works properly, apply all minimum required operating system patches and use only the versions of other software that are supported for a cubus product.

See the following section for further details.

Supported languages

Performance AL supports the following globalization and language settings:

User interface	Documentation
Chinese Traditional ⁽¹⁾	-
Danish	-
Dutch	-
English	English
French	-
German	German
Italian (1)	-
Japanese ⁽¹⁾	-
Korean ⁽¹⁾	-
Portuguese - Brazilian (1)	-
Spanish	-

⁽¹⁾ These languages are maintained based on customer specific requests and could not be up to date.

System requirements

Use the following tables to check the minimum hardware and software requirements to install and run Performance AL components.

Performance AL Server requirements

To install Performance AL Server the system should meet these requirements.

Performance AL Server Hardware Requirements	Specification
Disk space	Greater than 400 MB
Memory	Greater than 4 GB *1 *1 The memory requirements of Performance AL Server additionally depend on the number and size of cubes and also if the structure of the cubes is cached permanently or released again after usage.

I Planning Analytics Local 2.0 to 2.0.9.9 (IBM TM1 ver 11.0.00000.918 - 11.8.00800.5) (REST API only)
cle Essbase Version 11.1.2.4 and 11.2.0.0 cle Essbase OAC Version 105.3.0-117 (12.X) cle Essbase 19c Version 19.3.0.0 cle Essbase 21c Version 21.1.0.0-21.5.0.0
rosoft SQL Server Analysis Services 4, 2016, 2017, 2019, 2022
rosoft SQL Server Analysis Services Tabular Mode npatibility Level 1100, 1103, 1200, 1400
rosoft Azure Analysis Services 2019 mpatibility level 1200, 1400)
rosoft Windows Server 2, 2012 R2, 2016, 2019, 2022
rosoft Windows 7 Professional rosoft Windows 10
rosoft Windows 11
all Windows versions the latest service pack and current updates must be installed.
rosoft Internet Information Services (IIS)

	2019)
	See <u>Preparing the operating system</u> .
	Microsoft .NET Framework 4.8 or higher
Connection services	To connect to Oracle Essbase Server install Oracle Essbase Runtime Client.
The memory requirements depend on the number of users, usage, the size of the database models, the use	To connect to Microsoft SQL Server 2014 Analysis Services, install Connectivity Components of Microsoft SQL Server 2014.
of personalized databases and preload roles/users.	To connect to Microsoft SQL Server 2016 Analysis Services, install Connectivity Components of Microsoft SQL Server 2016.
	To connect to Microsoft SQL Server 2017 Analysis Services, install Connectivity Components of Microsoft SQL Server 2017.
	To connect to Microsoft SQL Server 2019 Analysis Services, install Connectivity Components of Microsoft SQL Server 2019.
	To connect to Microsoft SQL Server 2022 Analysis Services, install Connectivity Components of Microsoft SQL Server 2022.
	To connect to Oracle 11.2g or 12c, install Oracle Data Access Client (ODAC)/ODP.NET 64 bit version 12.1.x.
	To connect to IBM Cognos TM1 Server and IBM Planning Analytics Local 2.0 no local installation is needed.
Supported catalog providers Only one catalog provider	Microsoft SQL Server 2014, 2016, 2017, 2019, 2022
can be active at any one time.	Oracle 11.2g, 12c
Supported security providers More than one security	IBM Planning Analytics Local 2.0 to 2.0.9.9 (IBM TM1 Server 11.0.00000.918 - 11.8.00800.5) (REST API only)
provider can be active at the same time.	Windows Integrated Security
	Oracle Essbase Version 11.1.2.4 and 11.2.0.0 Oracle Essbase OAC Version 105.3.0-117 (12.X)

	Microsoft Azure (OAuth 2.0) Keycloak 18 or higher (OIDC)
Supported log providers	Microsoft SQL Server
More than one log	2014, 2016, 2017, 2019, 2022
provider can be active at	Oracle
the same time.	11.2g, 12c
OBI EE Integration	Oracle Business Intelligence Enterprise Edition
Optional	Version 11.1.1.7.141014
Report Subscription Mail Server Optional	Any SMTP Server

Untrusted Font Blocking

To ensure that the correct fonts for the code blue design are loaded <u>Untrusted Font</u> <u>Blocking</u> has to be disabled on the server that uses Performance Analytics. Please note that Microsoft <u>doesn't suggest</u> this setting anymore as the GDI Font Parsing is now done in an sandboxed process and not directly in kernel mode in recent Windows 10 versions after 1703.

Additional requirements

For Map support, Microsoft Internet Explorer version 11 should be installed on the machine running Performance AL Server.

Performance AL Explorer requirements

To install Performance AL Explorer the system should meet these requirements.

Performance AL Explorer Hardware Requirements	Specification
Disk space	Greater than 50 MB
Memory	Greater than 2 GB

Performance AL Explorer Software Requirements	Specification
Operating System. One is required. Only 64bit is supported.	Microsoft Windows Server 2012, 2016, 2019, 2022
	Microsoft Windows 7 Professional Microsoft Windows 10 Microsoft Windows 11

	For all Windows versions the latest service pack and all current updates must be installed.
Required software.	Microsoft Internet Information Services (IIS)IIS 8 (Windows 2012 Server)
	 IIS 10 (Windows 2016 Server, Windows Server 2019)
	Microsoft .NET Framework 4.8 Chrome Version 104 Apple Safari 16 Edge Version 101 (Chromium Edge) Mozilla Firefox is not supported.

Performance AL Desktop Explorer requirements

To install Performance AL Desktop Explorer the system should meet these requirements.

Performance AL Desktop Explorer Hardware Requirements	Specification
Disk space	Greater than 50 MB
Memory	Greater than 2 GB

Performance AL Desktop Explorer Software Requirements	Specification
Operating System. One is required.	Microsoft Windows Server 2012, 2016, 2019, 2022
	Microsoft Windows 7 Professional Microsoft Windows 10 Microsoft Windows 11
	For all Windows versions the latest service pack and all current updates must be installed.

Performance AL Client requirements

To install Performance AL Client your system should meet these requirements.

Performance AL Client	Specification
-----------------------	---------------

Hardware Requirements	
Disk space	Greater than 30 MB
Memory	Greater than 2 GB

Performance AL Client Software Requirements	Specification
Operating System. One is required. Only 64bit is supported.	Microsoft Windows Server 2012, 2016, 2019, 2022
	Microsoft Windows 7 Professional
	Microsoft Windows 10
	Microsoft Windows 11
	For all Windows versions the latest service pack and all current updates must be installed.
Required software.	Microsoft Internet Explorer 11
	Microsoft New Edge (Chromium) in Internet Explorer Mode.
	Note : Internet Explorer Protected Mode and Enterprise Mode can cause the client not to work properly and is therefore not supported.
Miscellaneous	Installation requires user rights to install and register ActiveX components in the browser and operating system.
	Port for communication between ActiveX and EVServer must be open when using TCP communication. Default ServerPortNumber is 7112.

Recommended Security Settings for Microsoft Internet Explorer to install the ActiveX client

If you have problems on downloading and installing the Performance Analytics Client software, please check if your Internet Explorer has the following settings.

In Internet Explorer open the Internet Options and navigate to the tab Security. Click the button Custom level... to validate if your account has the following settings active:

- ActiveX controls and plug-ins
 - Allow ActiveX Filtering > Enable
 - $\,\circ\,$ Allow previously unused ActiveX controls to run without prompt > Disable
 - Allow Scriptlets > Disable
 - \odot Automatic prompting for ActiveX controls > Disable
 - $\,\circ\,$ Binary and script behaviours > Enable

- $\,\circ\,$ Display video and animation on a webpage that does not use external media player > Disable
- \circ Download signed ActiveX controls > Prompt
- Download unsigned ActiveX controls > Disable
- \circ Initialize and script ActiveX controls not marked as safe for scripting > Disable
- $\,\circ\,$ Only allow approved domains to use ActiveX without prompt > Enable
- \circ Run ActiveX controls and plug-ins > Enable
- \circ Run antimalware software on ActiveX controls > Enable
- $\,\circ\,$ Only allow approved domains to use ActiveX without prompt > Enable
- Run ActiveX controls and plug-ins > Enable
- \circ Run antimalware software on ActiveX controls > Enable
- \circ Script ActiveX controls maked safe for scripting > Enable

Untrusted Font Blocking

To ensure that the correct fonts for the code blue design are loaded <u>Untrusted Font</u> <u>Blocking</u> has to be disabled on every client machine that uses Performance Analytics. Please note that Microsoft <u>doesn't suggest</u> this setting anymore as the GDI Font Parsing is now done in an sandboxed process and not directly in kernel mode in recent Windows 10 versions after 1703.

Performance AL Desktop requirements

To install Performance AL Desktop your system should meet these requirements.

Performance AL Desktop Hardware Requirements	Specification
Disk space	Greater than 50 MB
Memory	Greater than 2 GB

Performance AL Desktop Software Requirements	Specification
Operating System. One is required. Only 64bit is supported.	Microsoft Windows Server 2012, 2016, 2019, 2022
	Microsoft Windows 7 Professional
	Microsoft Windows 10
	Microsoft Windows 11
	For all Windows versions the latest service pack and all current updates must be installed.
Required software.	.Net Framework 4.8 For the initial installation the Microsoft Edge or Microsoft Internet Explorer browser is required.

	Google Chrome can also be used in combination with a valid ClickOnce add-in. After the initial deployment, no web browsers are required, the application updates itself automatically based on the installed server version.	
Miscellaneous	Port for communication between Performance AL Desktop and EVServer must be open when using TCP communication. Default ServerPortNumber is 7112.)	

Performance AL Anywhere requirements

To install Performance AL Anywhere the system should meet these requirements.

Performance AL Anywhere Hardware Requirements	Specification
Disk space	Greater than 50 MB
Memory	Greater than 2 GB

Performance AL Anywhere Software Requirements	Specification
Operating System. One is required.	Microsoft Windows Server 2012, 2016, 2019, 2022
	Microsoft Windows 10 Microsoft Windows 11 For all Windows versions the latest service pack and all current updates must be installed.
Required software.	 Microsoft Internet Information Services (IIS) IIS 8 (Windows 2012 Server) IIS 10 (Windows 2016 Server, Windows Server 2019) See Preparing the operating system. Microsoft .NET Framework 4.8 or higher

Performance AL	Specification
Anywhere Client	
Requirements	

Operating System	Android 7 Android 8 Android 9 Android 10
	iOS 11 iOS 12 iOS 13
	Windows 10 MacOS 10.15
Browser	Chrome Version 104 Firefox Version 104 Edge Version 101 (Chromium Edge) Safari 13-16

Upgrade requirements

When upgrading from the IBM Executive Viewer, the repository will be automatically migrated. Please note that this automatic upgrade is only supported for IBM Executive Viewer 9.2 to 10.1.

Configuring data sources

Each data source that is used must be configured to give access to Performance AL. These sections give the data source requirements.

Configuring Oracle Essbase data sources

For Performance AL to connect to Oracle Essbase the Essbase Runtime Client (64-bit) files need to be installed on the same system as the Performance AL Server. The version of the Runtime Client files must be the same as the version of Essbase you are using. Refer to the Oracle Essbase documentation to find the correct Runtime Client.

Oracle Analytics Cloud

If Performance AL is connecting to OAC datasources, the Windows system environment variable ESSOTLEDITSERVERMODE needs to be set to FALSE.

Configuring Microsoft Analysis Services data sources

For Performance AL to connect to Microsoft Analysis Services, the requirements are dependent on the version used.

To connect to Microsoft SQL Server Analysis Services, the following Analysis Services Client Libraries must be installed on the same system as Performance Analytics Server:

1. Microsoft Analysis Services OLE DB Provider (MSOLAP) (64-bit)

2. Microsoft Analysis Management Objects (AMO) (64-bit)

Use the setup of Microsoft SQL Server Analysis Services to install the client components. Refer to the Microsoft SQL Server Analysis Services documentation for more information. If you upgrade Microsoft SQL Server, you should also upgrade these components.

The following table lists the versions of the Analysis Services Client Libraries that are required for the versions of Microsoft SQL Server Analysis Services:

Microsoft SQL Server Analysis Services	Analysis Services Client Libraries
2014	12
2016	13
2017	15
2019	15
2022	16

Preparing the operating system

You need to prepare the operating systems before you install Performance AL.

Preparing Microsoft Windows Server

You have to enable the Web Server role and Microsoft .NET Framework for Windows Server.

Procedure

- 1. Open Server Manager.
- 2. Select Roles > Add Roles.
- 3. Select the Web Server role with the following Role Services:

- ▲ ✓ Web Server
 - ▲ 🔽 Common HTTP Features
 - Default Document
 - ✓ Directory Browsing
 - ✓ HTTP Errors
 - ✓ Static Content
 - ✓ HTTP Redirection
 - WebDAV Publishing
 - ▲ 🖌 Health and Diagnostics
 - HTTP Logging
 - Custom Logging
 - Logging Tools
 - ODBC Logging
 - Request Monitor
 - Tracing
 - Performance
 - ✓ Static Content Compression
 - Dynamic Content Compression
 - ▲ 🖌 Security
 - Request Filtering
 - Basic Authentication
 - Centralized SSL Certificate Support
 - Client Certificate Mapping Authentication
 - Digest Authentication
 - IIS Client Certificate Mapping Authentication
 - IP and Domain Restrictions
 - URL Authorization
 - ✓ Windows Authentication
 - ▲ ✔ Application Development
 - .NET Extensibility 3.5
 - ✓ .NET Extensibility 4.6
 - Application Initialization
 - ASP ASP.NET 3.5
 - ASP.NET 3.5
 - CGI
 - ✓ ISAPI Extensions
 - ✓ ISAPI Filters
 - Server Side Includes
 - WebSocket Protocol
- Management Tools
 - IIS Management Console
 - ▲ ✓ IIS 6 Management Compatibility
 - IIS 6 Metabase Compatibility
 - IIS 6 Management Console
 - ✓ IIS 6 Scripting Tools
 - IIS 6 WMI Compatibility

Note that the settings shown were made on a Windows Server 2016 machine. The differences in configuration between Windows Server 2012 (R2), Windows Server 2016, Windows Server 2019 and Windows Server 2022 are shown below.

2012 (R2) 2016 2019

.NET 4.5	Extensibility	.NET 4.6	Extensibility	.NET 4.7	Extensibility	.NET Extensibility 4.8
ASP.NET 4.5		ASP.NE	T 4.6	ASP.N	ET 4.7	ASP.NET 4.8

Preparing Microsoft Windows 10

You have to enable the Web Server role for Microsoft Windows 10/Windows 11.

Procedure

- 1. Open Control Panel > Programs.
- 2. Click Programs and Features > Turn Windows features on or off.
- 3. Enable the features:
 - Internet Information Services.
 - Internet Information Services World Wide Web Services Application Development Features ASP.NET.

Note: This will also include other options.

- Internet Information Services World Wide Web Services Security Windows Authentication.
- Internet Information Services Web Management Tools IIS 6 Management Compatibility IIS Metabase and IIS 6 configuration compatibility.

Preparing Microsoft Azure

When OAuth 2.0 should be used as authentication method Microsoft Azure needs to be configured. Performance Analytics needs to be registered in the Microsoft Azure environment as application.

Procedure

- 1. Open Home > Azure Active Directory > App registrations.
- 2. Click New registration.
- 3. Enter a Name and select the radio button Accounts in this organizational directory only (*yourOrganization* Single tenant).
- 4. Click **Register** on the bottom of the page.
- 5. After registration is finished the application page will be loaded
- 6. Redirect URIs are used to redirect back to Performance AL after the authentication. For Performance Analytics they need to be defined in Home > Azure Active Directory > App registrations > Performance Analytics application > Authentication: For Performance Analytics Explorer in section Web: <u>https://[EV_server_name]/</u> <u>EVExplorer/OAuth2ResponsePage.aspx</u> For Performance Analytics Anywhere in section Web: <u>https://[EV_server_name]/</u> EVAnywhere/oauthcallback.html

For Performance Analytics Desktop Clients in section **Mobile and Desktop Applications**: The current default value for native clients can be found in the Microsoft Azure documentation (https://login.microsoftonline.com/common/ oauth2/nativeclient).

7. In Home > Azure Active Directory > App registrations > Performance Analytics

application > API permissions click on the button Add a permission and select the tab APIs my organization uses.

- a. Select Azure Analysis Services and select the required permission (e.g. Model.ReadWrite.All).
- b. In order to use the Item/System Policies of Performance AL click on the button Add a permission and select the tab APIs my organization uses. Select Microsoft Graph and select the required permissions (GroupMember.Read.All, User.ReadBasic.All).
- In Home > Azure Active Directory > App registrations > Performance Analytics application > Certificates & secrets click on the button New client secret, enter description and select Expires period. Click Add. Then copy the created client secret to setup security provider.

Further configuration steps are described in

- MSAS Data Source Settings
- Specifying the security providers

Limitations

When using the New Edge Browser (Chromium) either the Anywhere client or the DesktopClient can be used with OAuth 2.0. This is actually a limitation of the New Edge Browser.

Preparing Keycloak

In order to use Keycloak with Performance Analytics it needs to be configured correctly.

In the first step a new application needs to be added to Keycloak.

Procedure

- 1. Open the Keycloak administration console and navigate to **Configure > Clients**.
- 2. Create a new client here.
- 3. Set the access type of the client to **confidential**. After saving the client you should now see a **Credentials** tab.
- 4. Set the **Client authenticator** to **Client Id and secret**. Generate a new client secret.
- 5. If MSAS Impersonation should be used a new Mapper called **database_user** needs to be defined. This Mapper is used to define the user should be impersonated when creating a connection to the MSAS database.

There are two options:

- a. Defining the Mapper as User Attribute. This means that the administrator has to define a **database_user** manually for each user created on the Keycloak server.
 - To do this define the following Mapper in the **Mappers** tab of the Performance Analytics application:

Setting	Value
Name	database_user
Mapper Type	User Attribute
User Attribute	database_user
Token Claim Name	database_user
Claim JSON Type	String

b. Defining the Mapper as User Property. This allows the administrator to map a existing property from the Keycloak server or an external provider (i.e. SAML) to be mapped to the **database_user** property.

To do this define the following Mapper in the **Mappers** tab of the Performance Analytics application:

Setting	Value
Name	database_user_userproperty
Mapper Type	User Property
Property	
Token Claim Name	database_user
Claim JSON Type	String

Set the value of the Setting **Property** to the name of the property you want to map to the **database_user** property.

- 6. Enable the following settings for the new Mapper:
 - Add to ID token
 - $\circ~$ Add to access token
 - \circ Add to userinfo
- If the Mapper database_user was defined as User Attribute every user that should be able to access Performance Analytics needs to have a database_user attribute defined:
 - a. Navigate to Users and edit an already existing user or create a new user.
 - b. Navigate to the **Attributes** tab and add a new attribute with key **database_user** and user name of the user that should be impersonated as value.
 - c. If a User should be able to change system or item policies he needs the to have the roles **view-clients** and **view-users** assigned from the **realm-management** client.
- 8. Add the following Redirect URIs for your Application:
 - a. https://[EV server name]/EVExplorer/OAuth2ResponsePage.aspx
 - b. https://[EV server name]/EVAnywhere/oauthcallback.html
 - c. http://localhost

9. In order to use subscriptions with Keycloak you need to set **Direct Access Grants** enabled to on in the settings tab of your client under **Configure > Clients**.

Note:

Keycloak is an open source software product to allow single sign-on. Once logged-in to Keycloak, users don't have to login again to access a different application. It is valid for web-applications in the same browser instance, but it is wrong for Performance AL Client. Due to technical implementation, the login dialog uses an another browser instance. It means user have to login in Performance AL Client again even if he is logged in to another application.

When using Keycloak with the Anywhere client, then popups needs to be enabled. You should disable any additional prompts (e.g. if you are asked if you want to store your credentials) - if these additional prompts pop up, it may be that case that the authentication response window is not closed automatically and needs to be closed manually.

4. Installing Performance Analytics

This chapter describes the steps necessary to install and configure Performance AL Server, Performance AL Explorer, and Performance AL Client.

The setup of Performance AL verifies that Microsoft Internet Information Services (IIS) is installed on your system. If IIS is not installed, the following applies:

- A message is shown at the start of the installation process stating that IIS is not installed.
- Performance AL Explorer and Web Service are not installed during the setup. Performance AL Explorer and the Web Service can be installed later during a custom installation.
- When you install Performance AL Explorer and Web Service, no virtual directories are created during the installation.

Note: When you use IIS 6 or higher the following message might be shown during the installation: *The Web Service Extension is prohibited, this extension will be used in the created virtual directories.* To make sure Performance AL works correctly, you have to allow this Web Service Extension manually. See <u>Preparing the operating system</u>.

Installing Performance AL

Selecting the mail server

If you want to use the Report Subscription feature you can configure a mail-server during the installation process.

Therefore you have to provide the following informations:

- SMTP Host Name
- SMTP Port
- Whether to use SSL connection
- Mail server authentication (if required by mail-server)
 - \circ User
 - o Password

Note: You can also keep the default values and skip this step in the installation process. To configure the mail-server after the installation process refer to chapter <u>Configuring the</u> <u>mail-server</u>.

Installing Performance AL with default settings

The express install uses a set of default parameters for the configuration.

The default settings are:

1. Performance AL can be used by anyone who uses the computer.

- 2. The Performance AL service as Local System.
- 3. The Performance AL service starts after installation.
- 4. The default web site in IIS is used.
- 5. The catalog provider is SQL Server.
- 6. When you do a default installation on a system that has no previous installation of Performance AL, the setup tries to validate the local SQL server. This can take a long time. If the validation fails, the SQL Server Catalog Provider dialog box is displayed. In this dialog box you can configure the SQL server settings.
- 7. Installing Performance AL
- 8. The database name for the catalog provider is EVRepository.

The default file locations are as follows:

- Installation directory = <InstallDir>
- Performance AL Server location: <InstallDir>\Server
- License file location: <InstallDir>\Server
- Performance AL Explorer location: <InstallDir>\Explorer
- Performance AL Server Web Service location: <InstallDir>\Server\WebService
- Performance AL Client location: <InstallDir>\Server\WebService\Client
- Performance AL Client Installer location: <InstallDir>\Server\ClientInstaller

Procedure

1. Run the installation file that is made available to you for Performance Analytics, or type

setup.exe /v"/qn INSTALLDIR=##Custom Performance AL Location##" in the command prompt for a silent install.

2. Select the language for the install and follow the instructions on your screen. When the Setup Type dialog box is displayed, select Express. If there are changes made to your system configuration, you may need to restart the computer for the changes to take effect.

Installing Performance AL with custom settings

The Performance AL Server and Performance AL Explorer can be installed onto different systems using custom settings.

The client software is part of the installation of the Performance AL Server. Performance AL can be installed and configured to best meet the needs of your server.

Selecting the install components

Use the custom setup to select the components to install.

When you install Performance AL Server and Performance AL Explorer using the custom

setup, you can select each program component and location of each component.

Procedure

- 1. Run the installation file that is made available to you for Performance AL.
- 2. Select the language for the install and follow the instructions on your screen. When the Setup Type dialog box is displayed, select Custom.
- 3. In the Custom Setup dialog box, select the features you want to install:
 - $\circ~$ Client the files needed to deploy the Performance AL Client from the server.
 - Documentation the complete documentation set.
 - Web service a service that enables Performance AL Explorer or Performance AL Desktop Explorer to connect to the server.
 - $\circ~$ Tools extra tools provided for use for Performance AL, including the Password Encryption tool.
 - Explorer Performance AL Explorer.
 - Anywhere Performance AL Anywhere client.
- 4. In the Install to box, click Change to change the default location of the installation if required.
- 5. In the Install Performance AL for box, select either:
 - Only for me administrator only
 - Anyone who uses this computer all users
- 6. In the Run Performance AL service as box, specify the account the Performance AL service runs on. The most common choice is Local System.
- To use a slave server for process distribution, select Start Performance AL in slave mode. For more information, see "Slave servers". Note: If you choose a slave server for process distribution you must install a master server to be able to:
 - o Configure the catalog provider for Performance AL Server
 - $\circ~$ Configure the security provider for Performance AL Server
 - o Install the Performance AL Web Service
 - Install the Performance AL Client deployment files

For more information about setting up process distribution with Performance AL Explorer, see Process distribution.

For more information about setting up process distribution with Performance AL Desktop Explorer, see Process distribution.

- 8. Click Next.
- 9. Choose the Web site where you want to have the virtual directories. You can only select the Web Site when IIS is installed.
- 10. Click Next and go to the section Specifying the catalog providers.

Specifying the catalog providers

You can choose one of the following for the catalog provider:

To specify **SQL Server** as the catalog provider:

Before you begin do the steps in <u>Selecting the install components</u>.

Procedure

- 1. Select **SQL Server** as the catalog provider.
- 2. Click Next.
- 3. In the **Database Name** box, type the name of the SQL database.
- 4. In the **SQL Server box**, type or select the name of the SQL Server.
- 5. To validate the SQL Server during installation select the Validate SQL Server check box.
- 6. To connect to the SQL Server check with either **Windows Integrated Authentication** or **SQL Server Authentication**. If SQL Server Authentication is selected, you must type the Login ID and password.
- 7. Click Next.
- 8. Go to Specifying the security providers.

To specify **Oracle** as the catalog provider:

Before you begin do the steps in "Selecting the install components".

Procedure

- 1. Select **Oracle** as the catalog provider.
- 2. Click Next.
- 3. In the **Database Source Name** box, type the name of the Oracle data source.
- 4. Type your ID and password for the Oracle server.
- 5. Click Next.
- 6. Go to Specifying the security providers.

Specifying the security providers

You can choose one of the following as the security provider:

- None, the security provider must be configured manually after the setup is complete.
- Windows
- IBM Cognos 8
- IBM Cognos TM1
- Forms an XML file will be installed with the user administrator set without a password.
- Essbase

To specify **Windows** as the security provider

Procedure

- 1. Select **Windows** as the security provider.
- 2. Click Next.
- 3. Go to Completing the custom installation.

To specify IBM Cognos 8 as the security provider

Procedure

- 1. Select **IBM Cognos 8** as the security provider.
- 2. In the box **Dispatcher Location** either accept the default location or change the default location if you want to connect to Cognos 8 on another machine.
- 3. In the Namespace ID box, type the unique ID for the namespace.
- 4. Type your ID and password for the Cognos 8 server.
- 5. Click Next.
- 6. Go to Completing the custom installation.

To specify IBM Cognos TM1 as the security provider

Procedure

- 1. Select **TM1** as the security provider.
- 2. In the Host Name box, type the host name.
- 3. In the Server Name box, type the names of the server.
- 4. Type your ID and password for the Cognos TM1 server.
- 5. Click Next.
- 6. Go to Completing the custom installation.

To specify **Essbase** as the security provider.

Procedure

- 1. Select **Essbase** as the security provider.
- 2. In the **Server Name** box, type the names of the server.
- 3. Type your ID and password for the Essbase server.
- 4. Click Next.
- 5. Go to Completing the custom installation.

To specify OAuth 2.0 as the security provider

Procedure

All required settings can be found in Preparing Microsoft Azure.

- 1. Select **OAuth 2.0** as the security provider.
- 2. In the Authorization Endpoint (v2) box, type the correct Authorization endpoint URI.
- 3. In the Token Endpoint (v2) box, type the correct Token endpoint URI.
- 4. Enter Logout Endpoint (v2)
- 5. Type the registered **Application (client) ID**.
- 6. Type Server location.
- 7. Add Permission.
- 8. Add Client secret
- 9. Type administrator name

10. Click Next.

11. Go to Completing the custom installation.

Completing the custom installation

Procedure

- 1. Make sure the installation summary is correct. If not, click **Back** to edit the information.
- 2. Click Install.
- 3. Wait while the features you selected are installed. This may take several minutes.
- 4. Click Finish.

Results

If there are changes made to your system configuration, you may need to restart the computer for the changes to take effect.

Installing Performance Analytics using silent install

You can run the installation as a silent install, so that no user interface shows and no additional actions are necessary to complete the install.

The Performance Analytics installation is based on the Microsoft Windows Installer technology and uses the general Windows Installer options.

Procedure

To run the installation as a silent install, use the following command prompt: setup.exe /v"/qn"

The following is an example command prompt to specify the installation location: setup.exe /v"/qn INSTALLDIR=##Custom Performance AL Location##"

Installing Performance Analytics Desktop Explorer

Performance AL Desktop Explorer needs to be installed separately from the main installation sequence.

After the installation it will be available in Microsoft Windows Explorer and as an icon (

) on your desktop. Performance AL Desktop Explorer is available in 32-bit and 64-bit versions.

During the installation of Performance AL Desktop Explorer, Performance AL Client is installed.

The default Performance AL Server that is added during the installation of Performance AL Desktop Explorer uses the TCP protocol for the connection to Performance AL Server.

Procedure

- 1. Click the installation file for Performance Analytics Desktop Explorer.
- 2. Follow the instructions on your screen.

3. Click Finish.

Installing Performance Analytics Client

Performance AL Client is deployed as a client software program.

There are five ways to get the client program:

- From a view or canvas item in Performance AL Explorer, Performance AL Client is installed automatically on your system when you open either a view or a canvas.
- From a URL request from your browser, either as a link from an HTML web page or by typing the URL directly into the web browser. A request is sent as an HTTP Request to Performance AL Server. This HTTP Request is processed by the HTTP Handler and returns either a Web Service Call or a URL API Call.
- From a launch command in the start menu. After you have completed an express install of Performance AL Explorer, the shortcut to an internet page Client is available. Click **Start > All Programs > Serviceware Performance Analytics > Client**.
- From an object in HTML code. See <u>Installing Performance AL Client from a link on an</u> HTML page.

If you have a Performance AL Client installed on your system that is a different version than the one you are installing, two separate Performance AL Clients are installed on your system. If the version of the Performance AL Client that is installed is the same as the version of the Performance AL Client you are about to install, the installed Performance AL Client will be replaced by the new one.

Setup Location:

The client setups can be found in the following location:

- <INSTALL_DIR>\Server\ClientInstallers\setup.exe (32 bit client)
- <INSTALL_DIR>\Server\ClientInstallers\setup64.exe (64 bit client)

Note: Only one client can be installed on the same machine at the same time. This means either the 32 bit or 64 bit client must be used, not both together.

Non-Admin Installation

The methods described above to install the Performance AL client are always performing a Non-Admin Installation. In this case the following script is executed in the background. setup.exe /v"MSIINSTALLPERUSER=1" /v"ALLUSERS=2"

Installation path: "C:\Users\%Username%\AppData\Local\Programs\Common\cubus shared\"

Admin Installation

To perform an Admin Installation, the setup.exe can be executed without any parameters.

Installation path: "C:\Program Files (x86)\Common Files\cubus shared\"

Note: For integration into Microsoft Office (Excel, Powerpoint, Word) an Admin Installation is required.

Install options:

The client setup can be installed/uninstalled with the following options:

- Silent Install: setup.exe /S /v/qn
- Silent Uninstall: setup.exe /X /S /v/qn

For further information concerning the parameters see https:// helpnet.flexerasoftware.com/installshield19helplib/helplibrary/ IHelpSetup_EXECmdLine.htm.

Installing Performance Analytics Desktop

Performance AL Desktop is deployed as a ClickOnce application.

To install the application you have to navigate to the following URL:

http://<yourservername>/EVServer/EVDesktopApp

Note: The ClickOnce deployment technology uses case sensitive URLs. Ensure that the provided installation link for the users matches the pattern above.

Each ClickOnce application is installed in a per-user, per-application cache folder. This folder can be found at the following location:

• C:\Users\<username>\AppData\Local\Apps\2.0

Deployment Package Location:

The deployment package can be found on the server at the following location:

• <EV_INSTALL_DIR>\Server\WebService\DesktopApp

For further information concerning the ClickOnce deployment technology see https://docs.microsoft.com/en-us/visualstudio/deployment/clickonce-security-and-deployment

Installing Performance AL Client from a link on an HTML page

Performance AL Client can be embedded in Microsoft Internet Explorer by using a customized HTML page. Access to an HTML page with references to specific files is required. This HTML page can be accessed with Internet Explorer via Internet or your Intranet using the HTTP protocol. It can also be accessed directly when it is available on your local network.

The following files are needed when using a customized HTML page:

- Ctrl.cab The cab file contains the requirements to setup Performance AL Client. This file is in the subdirectory WebService\Client of the Performance AL Server directory.
- The HTML page

An HTML page, containing the correct references. You can create this file based on the example below

```
<html>
<html>
<head>
<title>View Name</title>
</head>
<body topmargin="0" leftmargin="0" scroll="no">
<object ID="EVObject" name="EVObject" lang="en"
height="100%" width="100%"
classId="clsid:CLASSID"
codeBase="http://YourEVServer/EVServer/Client/
Ctrl.cab#version=EVVERSIONNUMBER">
<param name="Networkersion=EVVERSIONNUMBER">
<param name="Server" value="YourEVServer" />
<param name="Server" value="YourEVServer" />
<param name="DefaultView" value="/View Name" />
</object>
</body>
</html>
```

Further possibilities can be found in the *Client Integration Guide*.

Description of the example page

The descriptions for each of the element titles are as follows:

- <title>View Name</title> This is the title that is displayed in the caption bar. This title contains free text. It can be replaced with your text, for instance 'Monthly Views'.
- <body topmargin="0" leftmargin="0" scroll="no">
 Default properties for the margins and the presence of the scroll bar.
- object ID="EVObject" name="EVObject" lang="en" height="100%" width="100%" classid="clsid:7EAC1200-0BBE-499A-A9E9-5F334DBC8E89"
 The objectID in combination with the name and the CLASSID uniquely identifies Performance AL Client. The Windows registry contains a link between this ID and the actual control after installation. The language is set to default to English. The size of Performance AL Client is set to default 100%, filling the entire screen.
- codebase="http://YOURSERVER/ EVServer/Client/Ctrl.cab#version=10,5,0,0 The 'codebase' refers to the cab file in the Performance AL Server/Client directory. You can change this link, for example to the same directory as the HTML page but make sure the cab file is in the same location. Note that the name of the cab file is case sensitive. Microsoft Internet Explorer checks if the version number in the HTML page is newer than the version of Performance AL installed on the computer. If this is the case, installation starts.
- <param name="Server" value="YOUR Performance AL SERVER" /> The parameter Server. The value is the Performance AL Server name. This is necessary to let Performance AL Client connect to a Performance AL Server.
- <param name="SessionID" value="d17bf6f0-8ce8-4d2a-9f83-2cecd1b0407d" />
- <param name="DefaultView" value="/View Name" /> The parameters SessionID and DefaultView are properties added by the URL API. These properties are not necessary when using your own customized HTML page.

Installing the Performance AL Client after editing the HTML page

When a user accesses the HTML files, the web browser checks if Performance AL Client is installed previously, and if so, which version. If Performance AL Client is not installed, or

the version is older than the version specified in the HTML page, Performance AL Client is downloaded and installed.

Procedure

- 1. If alerted, allow blocked content, click the information bar and select Allow Blocked Content. Click Yes.
- 2. When the Microsoft Internet Explorer Security Warning dialog box is displayed, click Install to start the installation.

Checking the security settings of the internet browser

If Performance AL Client does not download when the HTML page is accessed, or starts to download every time the HTML page is opened, then the security settings must be adjusted for your internet browser. The internet browser must be set to allow:

- Download signed ActiveX controls.
- Run ActiveX controls and plug-ins.
- Script ActiveX controls marked save for scripting.
- File downloads.

The security level should also be set to medium or medium low.

Changing the language setting for Performance AL Client

The language for Performance AL Client can be changed to one of the following language settings:

Language	Language code
Chinese Simplified	zh-CN
Chinese Traditional	zh-TW
Danish	da-DK
Dutch	nl-NL
English	en-US
French	fr-FR
German	de-DE
Italian	it-IT
Japanese	ja-JP
Korean	ko-KR
Portuguese - Brazilian	pt-BR
Spanish	es-ES

The order that the language is set is determined by:

1. The language set in the Object element of the HTML page, or set by the URL API. For

more information, see URL API syntax.

2. The language set for the internet browser. See the documentation for your internet browser.

Configuring Performance AL Server

After you have installed Performance AL, certain components need to be specified and, if required, configured:

- Specify the connection to Performance AL Server. This is required when the Performance AL Server is on a different system than the Performance AL Explorer. More than one Performance AL Server can be specified.
- Configure the connection to the data sources for the OLAP databases. There are two Performance AL Explorer applications that can be used to specify and configure the Performance AL Server:
 - Performance AL Explorer requires IIS (Internet Information Service). Refer to Performance AL Explorer.
 - Performance AL Desktop Explorer necessary for systems that do not have IIS. Refer to Performance AL Desktop Explorer.

Note: The Performance AL Desktop Explorer can also be used on systems that do have IIS installed.

Specifying a Performance AL Server

This section explains how to specify a Performance AL Server using Performance AL Explorer.

These instructions are only needed to specify a new instance of Performance AL Server. When Performance AL Server and Performance AL Explorer are on the same system, Performance AL Explorer is already configured for the Performance AL Server.

During the process you are asked for the location of Performance AL Server and the CAB locations.

Procedure

1. Start Performance AL Explorer or Desktop Explorer.

For Performance AL Explorer, click **Start > All Programs > Serviceware Performance Analytics > Explorer** from the program list.

For Performance AL Desktop Explorer, double click *My Performance Analytics* from Microsoft Windows Explorer.

- 2. Right click on the **Home page** of Performance Analytics. Select **Add EV Server**. The **Server Information** dialog box opens.
- 3. In the **Name** box, type the name of the new Performance AL Server.
- 4. In the **Description** box, type a description of the new Performance AL Server.
- In the Location box, type the location of the new Performance AL Server. The location box needs a valid URI as input that consists of three parts, <Protocol>:// <Host>:<Port>, for example, tcp://172.31.254.1:7113.
 - Protocol HTTP, HTTPS, TCP
 Note: HTTP and HTTPS are used to connect Performance AL to the Performance AL Server via the Web Service. When the protocol is not specified, HTTP is used

as the default protocol.

TCP is used to connect Performance AL Explorer to the Performance AL Server when Performance AL Explorer is on the same system as Performance AL Server or the network cannot use HTTP or HTTPS. When the Performance AL Explorer is on the same system as Performance AL Server, TCP is the default protocol.

- Host The Host represents the host name of the Performance AL Server system. For example: demo.company.com
- $\circ~$ Port The port number defines the protocol port that is used for contacting the Host referenced in the URI. The valid ports are:

HTTP = Port 80 HTTPS = Port 443 TCP = 7113

If there is no location specified, the value of the **Name** box is used for the value of the Location box.

6. In the **Cab Location** box, type the location of the Cab files for the Performance AL Client.

The CAB location box is the location of the Performance AL Client cab files. By default when connecting to Performance AL Server with HTTP or HTTPS, this box is empty and the Client Directory that is used is in the Virtual Directory:

http://<Name>/EVServer/Client

If you connect to Performance AL Server via TCP, you should specify the location of the Cab files for the Performance AL Client.

If Performance AL Explorer is on the same system as Performance AL Server, the Cab Location is the Client Directory in the Virtual Directory. If the Web Service is not installed during the installation, the Cab Location of the Performance AL Server is empty.

- 7. If you want to select the **Automatic logon**, click the check box. If you enable Automatic logon, the logon process evaluates the availability of the following security providers in the order:
 - Windows Integrated Authentication.
 - $\circ~$ A Logon Form shows and the user is prompted to enter credentials.
- 8. In the **Security Namespace** box, type the name of the security provider. When empty, the default provider is used. The default provider is the first configured security provider. Depending on the security provider used, Performance AL Server can retrieve the user credentials automatically. The IBM Cognos 8 Security provider can have multiple security namespaces.
- 9. Click Add to add Performance AL Server to the list of available servers.

10. Go to Configuring the data source.

Configuring the data source

After you specify Performance AL Server, the data source needs to be configured.

The files for the data sources can be installed in any folder. The generic folders for the data sources, databases and images are to help the installer. If you select a different folder you need to reconfigure the search paths, for more information, see <u>Setting the search paths</u> for the Performance AL Explorer, or <u>Setting the search paths</u> for Performance AL Desktop Explorer. The data sources that are available are:

- IBM Cognos
- Microsoft Analysis Services or SQL Analysis Services
- Oracle Essbase

Configure IBM Cognos TM1

The steps needed to configure the data source for IBM Cognos TM1.

Enter the name of the 'adminhost', followed by a pipe character (|) and then enter the TM1 server name.

For example: TM1_demo|tm1srv.

You can find the TM1 server name by using IBM Cognos TM1 Architect. If you type the incorrect credentials in more than three times, you must restart the TM1 service.

Procedure

- 1. Click the icon for the Performance AL Server you have just created > **System**. Enter access credentials if required.
- 2. Right-click Data Sources and select Add Item > Data Source.
- 3. In the Name box, type a name for the data source. You can create your own name.
- 4. In the **Description** box, type a description of the data source.
- 5. Click Add.
- 6. In the Data Source Type box, select TM1.
- 7. In the **OLAP Server** box, type the name of the server.
- 8. In the **OLAP Administrator** box type your administrator name for the OLAP server.
- 9. In the **Password** box, type the password and confirm the password for the administrator name.
- 10. The other fields are not required for the install process.
- 11. Click Update.
- 12. Right-click the data source that you just created and select **Database Wizard**.
- 13. If the credentials are correct, the Database Wizard shows a list of all the databases. If you are asked to enter the credentials, type them here.
- 14. Select the check boxes for all the databases that you want to associate with Performance AL.
- 15. Click **Register**. The **Database Wizard** reports when each database is created successfully.
- 16. Click Close.

Configure Microsoft Analysis Services or SQL Analysis Services

The steps needed to configure the data source for Microsoft Analysis Services or SQL Analysis Service.

Procedure

To set the data sources, right-click the Performance AL Server icon = then click
 System > Data Sources. Enter access credentials if required.

- 2. Right-click Data Sources and select Add Item > Data Source.
- 3. In the Name box, type a name for the data source. You can create your own name.
- 4. In the **Description** box, type a description of the data source.
- 5. Click Add.
- 6. In the Data Source Type box, select MSAS.
- 7. In the **OLAP Server** box, type the name of the server. The name can be an IP address, DNS name or server name.
- 8. In the OLAP Administrator box type your administrator name for the server.
- 9. In the **Password** box, type the password for the administrator name.
- 10. The other fields are not required for the install process.
- 11. Click Update.
- 12. Right click the data source that is just created and select Database Wizard.
- 13. If the credentials are correct, the Database Wizard shows a list of all the databases. If you are asked to enter the credentials, type them here.
- 14. Select the check boxes for all the databases that you want to be associate with Performance AL.
- 15. Click **Register**. The **Database Wizard** reports when each database is created successfully.
- 16. Click Close.

Note: Please ensure that the OLAP Administrator has local administrative rights on the Performance AL Server machine and has an admin role on the Microsoft Analysis Server (a role with the "Full control" option checked). If the loading/instantiating of the AMO Server still fails please run the Performance AL Server under the OLAP Administrator account.

Configure Oracle Essbase

The steps needed to configure the data source for Oracle Essbase.

Procedure

- To set the data sources, in Performance Analytics, right-click the Performance AL Server icon
 Then, click System > Data Sources. Enter access credentials if required.
- 2. Right-click **Data Sources** and select **Add Item > Data Source**.
- 3. In the Name box, type a name for the data source. You can create your own name.
- 4. In the **Description** box, type a description of the data source.
- 5. Click Add.
- 6. In the Data Source Type box, select Essbase.
- 7. In the **OLAP Server** box, type the name of the server.
- 8. In the **OLAP Administrator** box type your administrator name for the server.
- 9. In the **Password** box, type the password for the administrator name. The other fields are not required for the install process.
- 10. Click Update.

11. Right click the data source that you just created and select Database Wizard.

- 12. If the credentials are correct, the Database Wizard shows a list of all the databases. If you are asked to enter the credentials, type them here.
- 13. Select the check boxes for all the databases that you want to associate with Performance AL.
- 14. Click **Register**. The **Database Wizard** reports when each database is created successfully.
- 15. Click Close.

Note: The value of Essbase substitution members can define one or more Essbase member names. The member names must be separated by blank characters. When the value of a substitution member contains only one member you have to enclose the member name with double quotes.

Run the Performance AL Web Service on another Server than the Performance AL Server

This section explains how to run the Performance AL Web Service on another machine than the Performance AL Server.

- 1. Go on the machine where the Web Service should run and open the web.config of the Web Service that can be found in <InstallDir>\Server\WebService.
- 2. Navigate to the <appSettings> section, which should contain the following parameters:

```
<add key="CustomServer" value=""/>
<add key="CustomServerPort" value=""/>
<add key="CustomServerProtocol" value=""/>
<add key="CustomServerRemotingPort" value=""/>
```

- 3. Adjust the parameters according to the following settings of the EVServer.exe.config on the machine which runs the Performance AL Server:
 - Use the hostname of the machine, which the Performance AL Server as value for CustomServer.
 - Use the value of ServerPortNumber/HTTPPortNumber/HTTPSPortNumber depending on the ServerProtocol as value of CustomServerPort.
 - Use the value of ServerProtocol as value of CustomServerProtocol if you are using http or https as ServerProtocol. If you use TCP as ServerProtocol you should set CustomServerProtocol to either http or https depending on how the Web Service is reachable for clients. The Performance AL Web Service will connect to Performance AL via TCP and the web service will then proxy the requests via either http or https to the clients depending on the CustomServerProtocol.
 - Use the value of RemotingPortNumber as value of CustomServerRemotingPort. If the remoting port number has not been changed use the default value of 7113.

Afterwards the IIS on the machine with the Web Service has to be restarted.

Installing maps

Performance AL supports Map. Map is a chart component that adds the support of geographic or structural topography in relation to the database information. Map has to be setup and configured for a specific database model before the graphical feature can be used with a database view.

Adding maps for use by the Performance AL

Customer maps can be added for use by the Performance AL. These maps are made available on the server for the client systems to use.

The database server has one default location for Maps. The organization of Maps into libraries and layers is done by copying the shape file into the correct subdirectories.

Inside this Maps directory, there is one subdirectory for each library. Each library directory contains all the shape files and database files which together make up the layers for that library.

Procedure

1. Make the default directory for Maps. C:\Program Files\cubus\Performance Analytics\Server\Maps

Note: If maps are put in a location other than the specified locations, they will not be available for use.

2. Copy the library you want to this directory.

Understanding layers and shapes

The concepts of layers and shapes must be understood before you arrange the geographic maps for your organization.

Each map is represented by a shape file (.shp) and a corresponding database file (.dbf). The shape file contains vectors that define the map. The database file contains data associated to the map, the regions on the map, the short name of the map or any statistical data.

The shape file and associated database file is called a layer.

In the example layer, the coordinates that give the continent Europe shape is described by the europe.shp file, the regions associated with Europe are listed in the europe.dbf file.



Layers can be classified according to hierarchy. For example, all continents can be given the classification of layer 1 and regions, classification layer 2. The order of layers is important. Layers with the lowest level of detail are lowest in the layer hierarchy, followed by layers with a higher detail. This ensures that states are drawn on top of regions and regions are drawn on top of continents.



All layers that share the same coordinate system and are to be used together either geographically or topographically must be grouped into one library. Therefore, the definition of a library is a collection of layers that share the same coordinate system and together make up one geographic area.

Understand the mapping file

In order to develop the map feature, one of the most important processes is to link members in your OLAP database to the shape and database files for a specific layer.

This is important to ensure that the data for the members are placed in the correct map and at the correct location. For example, the member California in the OLAP database should be mapped to the shape called California in the layer USA.

An intermediary mapping file is used to match members in the OPLAP database to the layers in the map library. The name of this file is libinfo.xml. This file is a read/write XML file, and itcontains the names of all the layers in the map library. The following is an example of a libinfo.xml file.

```
<?xml version="1.0"?>
<LIBRARY NAME="World Library">
 <LAYER FILE="Asia" LEVEL="0">
   <MAPPING COL="CNTRY NAME" ALIASTABLE="Default" />
 </LAYER>
  <LAYER FILE="Europe" LEVEL="0">
   <MAPPING COL="CNTRY NAME" ALIASTABLE="Default" />
 </LAYER>
 <LAYER FILE="Austria" LEVEL="1">
   <MAPPING COL="ADMIN NAME" ALIASTABLE="Default" />
 </LAYER>
  <LAYER FILE="France" LEVEL="1">
   <MAPPING COL="ADMIN NAME" ALIASTABLE="Default" />
  </LAYER>
  <LAYER FILE="Germany" LEVEL="1">
   <MAPPING COL="ADMIN_NAME" ALIASTABLE="Default" />
 </LAYER>
</LIBRARY>
```

The file has three element types LIBRARY, LAYER, and MAPPING. The element LIBRARY is the container for all the LAYER elements.

Library

Description

The LIBRARY element is the first element to be defined in the libinfo.xml file. The

element is used only once to hold the collection of layer elements. This element can also be used to give the library a different name from the directory name.

Syntax

<LIBRARY> </LIBRARY>

NAME

NAME is an optional attribute to give the library a different name from the library directory. If this attribute is omitted, the library is referenced by the directory name.

The library is called World Maps. If the NAME attribute is removed, the library is called by the directory name.

```
<LIBRARY NAME="World Maps">
<LAYER FILE="Asia" LEVEL="0">
<MAPPING COL="CNTRY_NAME" ALIASTABLE="Default" />
</LAYER>
</LIBRARY>
```

Layer

Description

The LAYER element is a child of the LIBRARY element. The element is used to define the behavior of a single layer in the Map library. The element is used to give the layer a name, specify the level of detail and specify one or more mappings.

Syntax

<LAYER> </LAYER> NAME, FILE, LEVEL

NAME is an optional attribute to give the layer a different name other than the file name. This is convenient where layers have file names that are not easy to understand. If this attribute is omitted, the layer is referenced by the file name from the shape and database files.

FILE is a mandatory attribute and defines the layer files used, the shape file and database file, that make up the layer. The name is specified without a file extension.

LEVEL is an optional attribute and defines the level of detail of a layer. The attribute is a number in the range 0-9999, where 0 indicates the lowest level of detail and 9999 the highest level. Layers that have the same level of detail, for example, all continent Maps, have the same level number.

Example: The name Australia is mapped to the database file au.dbf. The region, Australia, has a level 2 set. Level 1 could be Australasia and Level 0 Southern Hemisphere.

```
<LIBRARY>
<LAYER NAME="Australia" FILE="au" LEVEL="2">
<MAPPING COL="CNTRY_NAME" ALIASTABLE="Default" />
```

</LAYER> </LIBRARY>

Mapping

Description

The MAPPING element is a child of the LAYER element. The element is used to link a member in the OLAP database to a specific layer.

Syntax

<mapping> </mapping>

Attributes

COL, QUERY, LEVEL, GENERATION, MEMBERNAME, DIMENSION, ANCESTER, PARENT, ALIASTABLE

COL is a mandatory attribute and defines the field type in the layer database file that the members in the OLAP database should link to. The field type must be specified by name. This attribute is not case-sensitive.

QUERY is an optional attribute that works with the MEMBERNAME attributes. The QUERY attribute defines the record in the layer database file to which a member should be mapped.

MEMBERNAME is an optional attribute that works with the QUERY attribute. This attribute limits the query process to the member in the OLAP database that should be mapped to the QUERY attribute.

PARENT is an optional attribute. This attribute limits the query process to the children of the specified member.

ANCESTOR is an optional attribute. This attribute limits the query process to all descendants of the specified member.

LEVEL is an optional attribute that specifies the level that a member in the OLAP database must be before it is matched to the records in the layer database file. This makes it easy to map, for example, all level 0 members of an outline to layer 0. Level 0 is the lowest leaf in the database.

GENERATION is an optional attribute that specifies the generation that member in the OLAP database must be before it is matched against the records in the layer database file. Generation 0 is the highest leaf in the database.

DIMENSION is an optional attribute. To increase the speed of a search in the OLAP database, you can define this attribute with the specific dimension in the view. Only the specified dimension is searched for a possible match.

ALIASTABLE is an optional attribute and is added to the default libinfo.xml.

The Performance AL Server can use unique member names for members of an OLAP database. The member names shown in Performance AL Client do not have to be the same as these unique member names. To tell Performance AL Server to match the member names in the .dbf files to the member names shown in cubus Ev Client, the attribute 'ALIASTABLE=default' is used. If this Attribute is not added, not all Maps may show.

- Essbase The ALIASTABLE attribute is used to match your database files with an Alias Table in your Essbase outline.
- Other OLAP Servers Performance AL Server may use unique member names for members of an OLAP database. The member names shown in Performance AL Client may not be the same as these unique member names. To tell Performance AL Server to match the member names in the .dbf files to the member names shown in Performance AL Client, the attribute 'ALIASTABLE=default' is used. If this Attribute is not added, not all Maps may show. Therefore, this attribute tag is recommended when connecting to other OLAP Servers, even if the alias table is not a feature of these OLAP Servers.

Example 1: The minimum attributes that the element MAPPING can have. The mandatory attribute COL is set to the field type CNTRY_NAME that is in the Europe.dbf file. The OLAP database does not have an alias table, therefore the alias table is set to default.

```
<LIBRARY>
<LAYER NAME="Europe">
<MAPPING COL="CNTRY_NAME" ALIASTABLE="Default" />
</LAYER>
</LIBRARY>
```

Example 2: The name Germany in the Europe database file is mapped to the member name GM in the OLAP database. The ALIASTABLE is not used because a mapping is specified in the element.

```
<LIBRARY>
<LAYER FILE="Europe">
<MAPPING COL="CNTRY_NAME"
QUERY="CNTRY_NAME='Germany'" MEMBERNAME="GM" />
</LAYER>
</LIBRARY>
```

Example 3: The field FIPS_CNTRY in the Europe database file is mapped to the member name EUROPE in the OLAP database and to the children of the member EUROPE.

```
<LIBRARY>
<LAYER FILE="Europe">
<MAPPING COL="FIPS_CNTRY" PARENT="EUROPE" />
</LAYER>
</LIBRARY>
```

Example 4: The field FIPS_CNTRY in the Europe database file is mapped to the member name EUROPE in the OLAP database and to all ancestors of the member EUROPE.

```
<LIBRARY>
<LAYER FILE="Europe">
<MAPPING COL="CNTRY_NAME" EUROPE="GM" />
</LAYER>
</LIBRARY>
```

Example 5: The query is limited to the Market dimension in the OLAP database.

```
<LIBRARY>
<LAYER FILE="Europe">
```

```
<MAPPING COL="CNTRY_NAME" DIMENSION="Market" />
</LAYER>
</LIBRARY>
```

Example 6: The query is limited to the lowest leaves of the members.

```
<LIBRARY>
<LAYER FILE="Europe">
<MAPPING COL="CNTRY_NAME" LEVEL="0" />
</LAYER>
</LIBRARY>
```

Example 7: The query is limited to the highest leaves of the members.

```
<LIBRARY>
<LAYER FILE="Europe">
<MAPPING COL="CNTRY_NAME" GENERATION="0" />
</LAYER>
</LIBRARY>
```

Installing images for use in Performance Analytics

An image can be used as a background in a chart or canvas in Performance AL. After the installation of Performance AL, sample images are available. These images are made available on the server for the client systems to use. Also, you can add your own images.

Procedure

- 1. Open a Performance AL Server 🚟 and open the Images folder.
- 2. Right-click anywhere on the window and click **Add Item > Image**.
- 3. Type a name and a description for the image.
- 4. Click Add.
- 5. Click **Browse** and select an image. Images can be of the type BMP, GIF, JPEG and PNG.
- 6. Click **Open > Upload** to put the image file in the EVRepository.

Default images are available in the directory C:\Program Files\cubus\Performance Analytics\Server\images

7. Click Add.

Uninstalling Performance AL components

This section describes how to uninstall Performance AL. When upgrading, it is not necessary to uninstall the old version of Performance AL Server. The Repository that contains all Performance AL Items will not be removed during an uninstall. When upgrading, it is not necessary to uninstall the old version of Performance AL Client. When uninstalling Performance AL Client, there will be no loss of Items.

To uninstall Performance AL

To remove Performance AL from the system.

Procedure

1. Open the Control Panel.

- 2. Click Uninstall a program.
- 3. Click Performance Analytics
- 4. Click Uninstall/Change.

To uninstall Performance AL Desktop

To remove Performance AL Desktop from the system.

Procedure

- 1. Open the Control Panel.
- 2. Click Uninstall a program.
- 3. Click Performance Analytics Desktop.
- 4. Click Uninstall/Change.

To uninstall Performance AL Desktop Explorer

To remove Performance AL Desktop Explorer from the system.

Procedure

- 1. Open the Control Panel.
- 2. Click Uninstall a program.
- 3. Click Performance Analytics Desktop Explorer
- 4. Click Uninstall/Change.

To uninstall Performance AL Client

To remove Performance AL Client from the system.

Procedure

- 1. Open the Control Panel.
- 2. Click Uninstall a program.
- 3. Click Performance Analytics Client
- 4. Click Uninstall/Change.

Configuring access for authentification portals

Performance AL allows authentification portals to access the client by passing user credentials in an HTTP POST request. This allows single sign on for users as they have to enter their credentials once in the authentification portal and will be automatically authentificated in Performance AL through the portal. To configure access to the client the following URLs have to be used:

Standard client

```
Example: http://localhost/EVServer/Login.aspx?
ToolBar=true&TabBar=true
```

Credentials

The credentials have to be passed as POST data in the following format:

username=[username]&password=[password]

Example: username=User1&password=Pwd1

5. Configure the service and the configuration file

This section describes:

- The account that runs the Performance Analytics service and how to change the account.
- The configuration file and what it is used for.
- The element values that can be changed in the configuration file.
- How to edit the element values for a particular provider.

Change the Account that runs the Performance AL service

The default account where the Performance AL service runs is Local System. The Local System account has full access to the system and can pose a security threat if the service is compromised. To help secure your system the Local System account can be changed to an authenticated user account that has limited access across the network.

Procedure

- 1. Go to Control Panel > Administrative Tools.
- 2. Select Services.
- 3. Double click on the Serviceware Performance Analytics service.
- 4. Click on the Log On tab.
- 5. Add the account that the Serviceware Performance Analytics service should run on.
- 6. Click Apply > OK.
- 7. Restart the **Serviceware Performance Analytics** service for the changes to take effect.
- 8. Make sure that the system account has the following user right assignments:
 - "Giving the account the rights to replace a process level token"
 - "Giving the account the rights to act as part of the operating system"
 - "Giving the account the rights to impersonate a client after authentication"
 - "Giving the account the rights to log on as a service"
 - "Giving the account the rights for Local Administrator"

The required steps are described in the section below.

Giving the account the rights to replace a process level token

When the Performance AL service runs on a different account than **Local System**, the account must have the rights **Replace a Process Level Token** on the system that runs Performance AL Server.

Procedure

- 1. Go to Control Panel > Administrative Tools.
- 2. Select Local Security Policy > Local Policies > User Rights Assignment.
- 3. Right-click Replace a Process Level Token and select Security or Properties.
- 4. Click Add to add the account Performance AL Server is running on.

Note: For a domain account the 'Domain Security Policy' has to be adjusted.

Giving the account the rights to act as part of the operating system

To allow Performance AL Server to authenticate a user, the account must have the rights **Act as part of operating** system.

Procedure

- 1. Go to **Control Panel > Administrative Tools**.
- 2. Select Local Security Policy > Local Policies > User Rights Assignment.
- 3. Right-click Act as part of Operating system and select Security or Properties.
- 4. Click Add to add the account the Performance AL Server is running on.

Giving the account the rights to impersonate a client after authentication

To allow Performance AL Server to authenticate a user, the user needs to be 'Impersonated'. The account must have the rights **Impersonate a client after authentication**.

Procedure

- 1. Go to Control Panel > Administrative Tools.
- 2. Select Local Security Policy > Local Policies > User Rights Assignment.
- 3. Right-click **Impersonate** a client after authentication and select Security or Properties.
- 4. Click Add to add the account the Performance AL Server is running on.

Giving the account the rights to log on as a service

When the Performance AL service runs on a different account to **Local System**, the account should have the user rights assignment **Log on as a Service**.

Procedure

- 1. Select Control Panel > Administrative Tools.
- 2. Select Local Security Policy > Local Policies > User Rights Assignment.
- 3. Right-click Log on as a service and select Security or Properties.
- 4. Click **Add** to add the account on which the Performance AL service is running on.

Note: For a domain account the Domain Security Policy has to be adjusted.

Giving the account the rights for Local Administrator

When the Performance AL service runs on a different account to Local System, the account should be part of the group 'Administrators' on the system running Performance AL Server.

Procedure

- 1. Go to Control Panel > Administrative Tools.
- 2. Go to **Computer Management**.
- 3. Go to Local Users and Groups > Users.

- 4. Double click on the account you want to give Administrator rights, click Add on the Member Of tab.
- 5. Click Administrators or type Administrators, click Add to add the account.

Log on locally

Users who can not be authenticated using Integrated Authentication must have **Log on locally** rights on the system running Performance AL Server. This is necessary to enable Performance AL Server to impersonate those users.

Procedure

- 1. Select Control Panel > Administrative Tools.
- 2. Go to Local Security Policy > Local Policies > User Rights Assignment.
- 3. Right-click Log on locally or Allow log on locally and select Security.
- 4. Click on Add to add all users or a group of users.

Editing the configuration file

The configuration files are XML files that administrators can use to change how the application runs. Performance Analytics uses the following configuration files that are installed during the setup routine:

- EVServer.exe.config default location C:\Program Files\cubus\Performance Analytics\Server.
- Web.config for Performance AL Explorer default location C:\Program Files\cubus\Performance Analytics\Explorer.
- Web.config for Performance AL Server's Web Service default location C:\Program Files\cubus\Performance Analytics\Server\WebService.

This section describes the EVServer.exe.config configuration file. The Web.config file for Performance AL Explorer or the Web Service should not need adjustment after installation, however if there is a need, these files are referenced to directly.

After you make changes to the EVServer.exe.config file, the Performance AL service needs to be restarted for the changes to take effect.

Example default configuration file structure

```
<configuration>
  <configSections>
    <section name="catalogProvider" type="Provider,Server" />
    <section name="securityProviders" type="Provider,Server" />
    <section name="logProviders" type="Provider,Server" />
    <section name="dataSourceSettings" type="DataSourceSettings,
BackEndWrapper" />
    </configSections>
    <catalogProvider>
        <provider type="SQLServer"
externalName="SQLServerCatalogProvider">
        <dataSource pwdEncrypted="true"
            connectionString="Server=MyServer;
Database=EVRepository;Integrated Security=SSPI;" />
        </provider>
```

```
</catalogProvider>
  <securityProviders>
    <provider type="Windows" externalName="Windows" />
  </securityProviders>
  <logProviders defaultProvider="XMLLogProvider">
    <provider type="XML" externalName="XMLLogProvider">
      <properties>
        <file path="C:\Program Files\cubus\Performance Analytics
\Server\EVServerLog.xml"
              createEvery="day" />
      </properties>
      <logLevelTable>
        <logLevels>
          <logLevel logLevel="Warning" category="*" component="*" />
        </logLevels>
      </logLevelTable>
    </provider>
  </logProviders>
  <appSettings>
    <add key="SessionTimeOut" value="30" />
    <add key="MapsPath" value="C:\Program Files\cubus\Performance</pre>
Analytics\Server\Maps\" />
    <add key="DesktopExplorerOpenViewUrl" value="http://<EVServer>/
EVServer?Item={0}
&ToolBar=True&Theme=Ribbon&Backstage=false" />
    <add key="ChartUrl" value="http://<EVServer>/EVServer/UI/
chart.html"/>
    <add key="EVDesktop SuppressScriptErrors" value="true"/>
    <add key="EVDesktop WebBrowserShortcutsEnabled" value="true"/>
    <add key="EVDesktop_Culture" value=""/>
  </appSettings>
  <dataSourceSettings>
    < mdx >
      <useSumForMultiSelect>true</useSumForMultiSelect>
    </mdx>
  </dataSourceSettings>
</configuration>
```

Configuration file elements

<configSections>

The configSections element declares the names of the providers that are used by Performance AL. The elements in the configSections element should not be changed.

<catalogProvider>

This element contains the settings for the catalog provider. Refer to the section Configuring the catalog provider for settings that can be changed or added.

<securityProviders>

This element contains the settings for one or more Security Provider. Refer to the section Configuring the security provider for settings that can be changed or added.

<logProviders>

This element contains the settings for one or more Log Provider. Refer to the section Configuring the Log Providers for settings that can be changed or added.

<appSettings>

This element contains application specific settings. The following values can be set:

• <add key="SessionTimeOut" value="30"/>

Specifies the time in minutes that a session state is maintained in Performance AL Server. If there is no activity for a period longer then the configured time out value, the session stops. The minimum value is 1, the maximum value is 120. The default value is 30.

Note: As long as the Performance AL Client exists in a browser window, it will send a keep alive in order to keep the session alive. The SessionTimeOut refers to sessions that e.g. have been created from Performance AL Explorer or through the server API.

- <add key="TokenCacheTimeOut" value="X"/> By default Performance AL caches all Microsoft Windows tokens when using Forms, for example the OLAP administrator accounts used to preload a datasource. The TokenCacheTimeOut value specifies the time in minutes in which the token will timeout and will be updated when necessary. Values: -1: unlimited 0: no caching 1: time in minutes when tokens will time out.
- <add key="MapsPath" value="C:\Program Files\cubus\Performance Analytics\Server\Maps\"/> The path to the Maps Libraries.
- <add key="ServerPortNumber" value="7112"/>
 The TCP port number, Performance AL Server uses for client communication.
 Default = 7112.
- <add key="RemotingPortNumber" value="7113"/> The TCP port number that is registered by Performance AL Server to allow communication via remoting.

By default the Performance AL Explorer web application communicates directly with the Performance AL Server over TCP 7113. This can be configured in Performance AL Explorer > right click on the Server > Server Settings > Location. The default URL is tcp://<EVServerHostName>:7113.

For secure communication you can configure https://<EVServerHostName>:443 which will make the Performance AL Explorer communicate with the Performance AL WebService which will also tunnel the communication and forward it via TCP to Performance AL Server on the RemotingPortNumber.

Note: If you set the RemotingPortNumber to another value than 7113 and you want to use the URL API, you must set the RemotingPortNumber to the same value in the **web.config** file of the Performance AL Server WebService.

The default location of the web.config file is C:\Program Files\cubus \Performance Analytics\Server\WebService\.

Add the following lines to the configuration element of the Web Service **web.config** file to set the RemotingPortNumber:

```
<!-- Add the following section into web.config --> <configuration>
```

```
<appSettings>
<add key="RemotingPortNumber" value="7113" />
</appSettings>
</configuration>
```

<add key="ServerProtocol" value="TCP"/>

The protocol that Performance AL clients are using to communicate with Performance AL Server. The default value is TCP. When the ServerProtocol is set to HTTP or HTTPS the Performance AL Server is still listening to the ServerPortNumber and the Performance AL clients are communicating via HTTP or HTTPS with the Performance AL Web Service which is tunneling the request to the Performance AL Server on the ServerPortNumber via TCP.

- <add key="HTTPPortNumber" value="80"/> When ServerProtocol is set to HTTP, this sets the port number. This is the port on which the Performance AL Web Service is listening for Performance AL clients. Default = 80
- <add key="HTTPSPortNumber" value="443"/> When the ServerProtocol is set to HTTPS, this sets the port number. This is the port on which the Performance AL Web Service is listening for Performance AL clients. Default = 443
- <add key="ClientLogon" value="SessionID;WIA;Forms;CAMpassport"/> Restricts the logon type of a client. If set, the client is only allowed to logon in the specified way. If not set, the client is not restricted. The possible string values are SessionID, WIA, Forms and CAMpassport. Each string must be separated by a semicolon. When an invalid type is specified, the server will not start.
- <add key="GatewaySuppliesCredentialInformation" value="true"/>
 When set to True, the Data Source Gateway can supply credential information when
 the security provider does not supply valid credentials, or the session does not have
 valid credentials to logon to the Data Source Gateway. The client asks the user for
 those credentials. If set to False the user does not have access to data sources that
 the user does not have credentials for.
 Default = true
- <add key="ParallelPreload" value="1"/> Specifies the Parallel preload level.
 - 1 = databases and roles will be preloaded sequentially per server.
 - 2 = databases will be preloaded in parallel, roles will be preloaded sequentially per database.
 - 3 = databases will be preloaded sequentially per server, roles will be preloaded in parallel per database.
 - 4 = databases and roles will be preloaded in parallel.

Default = 1

• <add key="RetryDatabasePreload" value="-1"/>

This key defines the behavior when an error occurs during a database preloading. Possible values

- -1 = skip preloading database.
- 0 = try preloading the database and roles immediately.
- 1 (and more) = wait 1 (or more) minutes before trying to preload the database/roles. Multiple values can be separated by comma for the different

tries (*e.g. 1,5,10,20,60*). The last value is used indefinitely for the further tries. Default = -1

If RetryDatabasePreload value is 0 or more (retry preloading) and ParallelPreload value is 1 or 3 (databases will be preloaded sequentially), subsequent databases cannot be loaded until the current database is fully loaded.

- <add key="InboundIPAddress" value="IP_Address"/> Contains a specific subnet, IP_Address or DNS name. When configured, only client connections from a specified subnet are accepted. Default = Any
- <add key="AggressiveMemoryAllocationMaxMB" value="0"/> This key sets the limit for aggressive memory reservation that the server allocates for its buffers. The buffers can still grow beyond this limit, but not aggressively. Default = 0
- <add key="CheckPreloadingTimeOut" value="0"/> This options allows you to specify a time-out interval. After this time-out interval all pre-loaded databases are verified and reloaded if the databases are updated. Default = minimum = 0 minutes (no verification), maximum = 1440 minutes
- <add key="UseCurrentOutlineWhilePreloading" value="false"/> Use this option to connect to a database that has a changed outline and is marked for preload. When set to true, the user uses the current cached outline while in the background the updated database is reloaded. When the reload is finished the user receives the refreshed data when reopening the database connection. When set to false, the user waits until the updated database is reloaded. Default = False
- <add key="SessionProtection" value="None"/> This allows you to protect a session. Possible values are:
 - None

No session protection is applied, this is default behavior.

Lock

The Session is protected/locked by the first client that connects to the server. Other connections are only allowed if they come from the same user.

Restrict

The session is protected/restricted when created. The protection is based on the user who connects. Restrict can only be successfully set when security providers that support impersonation are used. When a security provider that does not support impersonation is used, the value of SessionProtection is set to Lock.

• <add key="TokenCacheTimeOut" value="-1" />

The TokenCacheTimeOut lets you specify the time in minutes a token lasts. Possible values are:

- -1: Unlimited. The time the token lasts will not expire.
- 0 : The token is not cached
- 1 2147483647 : A time-out occurs when the time the token is not being used is longer than the specified time.

If you set the TokenCacheTimeOut to 540 minutes, the token expires from the cache after 9 hours of none use. This makes resources available for other tokens.

Default = -1

- <add key="DesktopExplorerOpenViewUrl" value="https://<EVServer>/ EVServer?Item={0} &ToolBar=true&Theme=Ribbon&Backstage=false" /> This option is configured during the installation and defines the URL which is called by the desktop explorer in order to open a single view or canvas.
- <add key="ViewLinksExpirationDays" value="10" />
 This option specifies, how long view links created by users via the Create Link
 functionality shall exist before they are automatically removed from the repository.
 The value represents the number of days since the last access of the view link by
 any user. Setting the value to zero (0) days disables the automatic cleanup.
 Default = 0
- <add key="EVDesktop_SuppressScriptErros" value="true" /> This option sets a value indicating whether the Desktop application displays dialog boxes such as script error messages. Use this option only for debugging purpose.
- <add key="EVDesktop_WebBrowserShortcutsEnabled" value="true" /> Set this property to false to prevent your users from using Microsoft Internet Explorer keyboard shortcuts with the Desktop application.
- <add key="EVDesktop_Culture" value="" /> Set this property to one of the supported cultures (see <u>Changing the language</u> <u>setting for Performance AL Client</u>) to define the language of the Desktop application.
- <add key="RestApiProtocol" value="https" /> The protocol the Performance AL Anywhere client is using for the communication with the REST server.

Possible values: http (default), https

The value which is entered here will be written to the **<EV_INSTALL_DIR> \Anywhere\config.json** file when the Performance AL service restarts as parameter **RestApiProtocol**.

• <add key="RestApiPortNumber" value="7111" /> The port the Performance AL Anywhere client is using for the communication with the REST server.

If the value is missing, the default value depends on the setting RestApiProtocol. If the protocol is http, the port number is the value of the setting HTTPPortNumber.

Default value is 80 if **RestApiPortNumber** is not defined.

If the protocol is https, the port number is the value of the setting HTTPSPortNumber. Default value is 443 if RestApiPortNumber is not defined.

The value which is entered here will be written to the **<EV_INSTALL_DIR> \Anywhere\config.json** file when the Performance AL service restarts as parameter **RestApiPort**.

• <add key="RestApiCorsOrigins" value="anywhere.company.com, server2:8080" />

The list of web hosts that are allowed to communicate with the REST server. The list can be separated by comma, semicolon or space. By default the list contains already localhost, the hostname, the full qualified hostname and the host's IP addresses. You have to add an entry to the list in the following situations:

If a reverse proxy is between the Performance AL *Anywhere* client and the Performance AL REST server, the name of the reverse proxy must be added to the list.

If an alias is used in the URL for the Performance AL *Anywhere*, the alias must be added to the list. E.g. the hostname of the Performance AL REST server is *MyEvHost*

and the URL is *https://anywhere.company.com*, then anywhere.company.com must be added to the list.

If you use the <u>PowerBI_Visual</u>, this parameter has to be set to "*" to allow access from an undefined origin.

• <add key="AllowLoginOnLicenseViolation" value="true" />

This property helps to ensure that a concurrent user license is met. The default value (true) allows users to login even if the number of currently logged on concurrent users is exceeded. A warning message will be shown to any user logging while the license is exceeded and it will be logged by the system.

Setting this property to false prevents users from logging in if the number of licensed concurrent users is equal to the number of logged on users to ensure that the license is not violated. It does not affect administrators that login into Performance AL Explorer/Performance AL Desktop Explorer.

• <add key="SubscriptionChartUrl" value="http(s)://company.com/ EVServer/UI/chart.html" />

This property defines the url to create reports containing charts and is needed for the Report Subscription feature. It is used to call the URL from the server where Performance AL runs.

• <add key="DesktopAppUrl" value="http(s)://<EVServer>/EVServer/ EVDesktopApp" />

This property defines the URL of the Desktop application. This setting is needed in order to start the DesktopApp from Chrome, Firefox or the Edge browser. If this setting does not exist or is incorrect, you will encounter an error message when you start the Desktop application from one of these browsers. If you are using Internet Explorer, this setting is not needed.

• <add key="MaxNumberOfCores" value="0" />

This property defines how many cores can be used by the Server. If the setting is missing, lower or equal than zero or is larger then the available number of cores, then all cores are used. Otherwise the Server uses only the configured cores.

• <add key="ClassicBorders" value="true" />

This property forces the view to render borders as classic styles before the introduction of border color feature in version 8.5.0. When this property is not set the default value is false.

• <add key="UseOlapConnectionUser" value="true" />

This property determines whether the user access to the OLAP database is done by the connection user or the logged-in user. This parameter is used only with OIDC security provider. If the parameter is set to True, the access will be done by the connection user. If this parameter is set to False, the access will be done by logged-in user. The user needs the appropriate permissions in the OLAP database. When this property is not set the default value is false.

<dataSourceSettings>

This element contains data source specific settings. It is recommended to only add this element in specific situations. Contact our support team for more information. For a comprehensive explanation on the dataSourceSettings, refer to the section <u>Appendix</u>: dataSourceSettings.

<system.net>

This element contains the settings for the mail-server. Refer to the section <u>Configuring</u> the mail-server for settings that can be changed or added.

Configuring the catalog provider

This section describes how to configure all the built-in catalog providers for the Performance AL. This section also describes the system requirements and the specific configuration of the EVServer.exe.config file for each catalog provider.

A Repository can only be used by the Catalog Provider that created it. For example, a repository created by the SQL Catalog Provider can not be used with the Oracle Catalog Provider.

A Password Encryption tool is part of the installation of Performance AL. If the Password Encryption is used to provide the encrypted password, the encryption strength for encrypted elements in the server configuration file is 2048 bits. The password encryption tool generates 2048 bit encrypted values.

The Password Encryption tool can be found here: C:\Program Files\cubus \Performance Analytics\Server\Tools\PasswordEncrypt.

Configuring the SQL Server catalog provider

The SQL Server catalog provider stores the Performance AL Server Repository in a Microsoft SQL Server database.

Microsoft SQL Server

Procedure

1. Add the following lines to the <catalogProvider> element of the EVServer.exe.config file:

```
<catalogProvider>
<provider type="SQLServer"
externalName="SQLServerCatalogProvider">
<dataSource pwdEncrypted="true"
connectionString
="##SQLServerConnectionString##" />
</provider>
</catalogProvider>
```

Note: The element names are case sensitive.

2. Edit the dataSource element.

```
The connectionString SQLServerConnectionString has the following structure:
For standard security:
Server=##SERVERNAME##;Database=EVRepository; UID=##USERNAME##
;Pwd=##PASSWORD##
```

For integrated security:

```
Server=##SERVERNAME##;Database=EVRepository; Integrated
Security=SSPI
```

- Apply password encryption.
 Password encryption applies only to standard security.
 If the pwdEncrypted attribute set to true, the password value should contain an encrypted value.
 Note: You can use the Password Encryption tool to obtain the encrypted password.
- 4. Refer to the SQL Server documentation for more information about connection strings that can be used to connect to SQL Server.

Configuring the Oracle catalog provider

The Oracle Catalog Provider is the Catalog Provider that stores the Performance AL Server Repository in an Oracle database.

An Oracle catalog provider cannot create its own database. The necessary tables are created automatically if the user account has sufficient permissions.

Before you begin

Ensure that the Oracle client is installed.

The open_cursors database parameter must be set to at least 2, in order to start the server.

Procedure

1. Add the following lines to the <catalogProvider> element of the EVServer.exe.config file:

```
<catalogProvider>
<provider type="Oracle" externalName="OracleCatalogProvider">
<dataSource pwdEncrypted="true"
connectionString="##OracleConnectionString##" />
</provider>
</catalogProvider>
```

Note: The element tags are case sensitive.

2. Edit the dataSource element.

```
The connection string OracleConnectionString has the following structure.
Data Source=##TNSNAME##;UID=##USERNAME##;Pwd=##PASSWORD##
```

3. Apply password encryption.

If the pwdEncrypted attribute set to true, the password value should contain an encrypted value.

Note: You can use the Password Encryption tool to obtain the encrypted password.

- 4. The connection user needs the following rights:
 - CREATE PROCEDURE
 - CREATE SESSION
 - CREATE SEQUENCE
 - CREATE TABLE
 - Write access to the corresponding tablespace

5. Refer to the Oracle documentation for more information about connection strings that can be used to connect to Oracle.

Configuring the security provider

This section describes how to configure all the built-in security providers for the Performance AL. This section also describes the system requirements and the specific configuration of the EVServer.exe.config file for each security provider. Only one security provider can be used at any one time.

The file EVServer.exe.config contains the reference to the security provider. Account Name and Credentials are validated with the security provider, which results in a valid or invalid authentication of the account. A valid authentication leads to a Session.

A Password Encryption tool is part of the installation of Performance AL. If the Password Encryption is used to provide the encrypted password, the encryption strength for encrypted elements in the server configuration file is 2048 bits. The password encryption tool generates 2048 bit encrypted values.

The Password Encryption tool can be found here

```
C:\Program Files\cubus\Performance Analytics\Server\Tools\PasswordEncrypt
```

Configuring the IBM Cognos 8 Security Provider

The IBM Cognos 8 security provider uses either Windows Integrated Authentication (WIA), a Cognos 8 passport or credentials that validates against a Cognos Server. When the validation is complete a Cognos 8 passport cookie is created.

In Cognos 8 the concept of security provider is referred to as namespace. The Cognos 8 security provider can represent multiple security namespaces. You can use a subset of the namespaces that are defined in Cognos 8, depending on whether WIA is supported in the defined Cognos 8 namespace.

Before you begin

IBM Cognos 8.4 needs to be installed.

Procedure

1. Add the following lines to the <securityProviders> elements of the EVServer.exe.config file:

```
<securityProviders>
  <provider type="CAM" externalName="CAM">
        <dispatcher location="http://Cognos8SERVER:9300/p2pd/
servlet/dispatch" connectionsLimit="10"/>
        <propagateAnonymousLogon>false</propagateAnonymousLogon>
        <configurationRoot>.\cogroot</configurationRoot>
        <passportTimeOut>3600</passportTimeOut>
        <cookiePath>/cognos8</cookiePath>
        <pathSeparator>##SEPARATOR##</pathSeparator>
        <clonePassportAllowed>true</clonePassportAllowed>
        <namespaces>
        <namespace id="##&quot;NAMESPACEID&quot;##">
        </validator>
        <credential>
```

```
<name>
                <CAMusername>
                  <value>##USERNAME##</value>
                  <credential>
                    <name>CAMpassword</name>
                    <value encrypted="true">
                      <PASSWORD>
                        <password>true</password>
                        <builtInAdministrators>
                          <builtInAdministrator
                             namespace
="##"NAMESPACEID"##">
                            <USER OR GROUP></USER OR GROUP>
                          </builtInAdministrator>
                        </builtInAdministrators>
                      </PASSWORD>
                    </value>
                  </credential>
                </CAMusername>
              </name>
            </credential>
          </credentials>
        </validator>
      </namespace>
    </namespaces>
  </provider>
</securityProviders>
```

Note: The element tags are case sensitive.

- 2. Edit the element tags as follows:
 - <provider>

The <provider> element of the IBM Cognos 8 security provider contains the details needed to make sure this Security Provider operates correctly. One IBM Cognos 8 Security Provider represents one set of users and user groups configured on one or more Cognos 8 servers.

If multiple sets of users and user groups need to be represented, separate instances of this Security Provider with unique external names need to be configured. Each instance has to reference to its own set of servers.

• <dispatcher>

The <dispatcher> element contains the location of the Cognos 8 dispatcher. The dispatcher is used to send requests to the Cognos 8 server. Attribute connectionsLimit defines the maximum Http connections between EVServer and dispatcher. Default value is 10.

<propagateAnonymousLogon>

The <propagateAnonymousLogon> element propagates the anonymous settings of the Cognos 8 installation to Performance AL. This element is optional. If you either do not specify the <propagateAnonymousLogon> element or set it to False, the anonymous user settings of Cognos 8 are not passed on to Performance AL.

<configurationRoot>

The <configurationRoot> element lets you set an alternative configuration root. This element is optional. If you do not specify the <configurationRoot> element, the default value cogroot is used.

<passportTimeOut>

The <passportTimeOut> element lets you set time-out for a passport in seconds. After this time of inactivity the passport is no longer valid. This element is optional. If you do not specify the <passportTimeOut> element, the default value '3600' will be used.

<cookiePath>

The path where IBM Cognos 8 Passport cookies should be generated. These cookies will only be generated when Performance AL is on the same path.

• <pathSeparator>

The <pathSeparator> element lets you specify the character to separate user paths. This element is optional. If you do not specify the <pathSeparator> element, the default value ' \' is used.

• <clonePassportAllowed>

The <clonePassportAllowed> element lets you specify whether making a clone of a passport is allowed, when a user logs on with that passport. This element is optional. If you do not specify the <clonePassportAllowed> element, the default value 'true' will be used.

• <namespaces>

The <namespaces> element contains one or more Security Namespaces. Each namespace needs to contain the correct namespace id which corresponds to the namespace id of the namespace that is defined in Cognos 8. You have to specify credentials for all the disclosed namespaces. The default Cognos 8 namespace will additionally be disclosed.

Note: If the value encrypted attribute set to true, the password value should contain an encrypted value. You can use the Password Encryption tool to obtain the encrypted password.

<builtInAdministrators>

The <builtInAdministrators> element is optional and allows certain users or certain user groups, to be tagged as built-in administrators. Built-in administrators have full access and control over Performance AL Server without having any System or Item Policies specified.

When choosing IBM Cognos 8 as Security Provider during the setup routine, the system administrators group of the built-in Cognos 8 namespace is added as built-in administrator. This is similar to a Windows built-in administrator on the local system who has the same privilege by design. This is to prevent administrators creating a situation where they cannot access Performance AL Server.

3. Apply password encryption.

If the valueEncrypted attribute set to true, the password value should contain an encrypted value.

You can use the Password Encryption tool to obtain the encrypted password.

Configuring the TM1 Security Provider

The IBM Cognos TM1 security provider validates credentials, typically a user name and password combination, against an IBM Cognos TM1 Server. This security provider does not support Windows Integrated Authentication (WIA).

Before you begin

The TM1 OLEDB Provider is installed to connect to IBM Cognos TM1. The version of the

TM1 OLEDB Provider must be exactly the same as the version of TM1 you are using.

Procedure

1. Add the following lines to the <securityProviders> element of the EVServer.exe.config file:

Note: The element tags are case sensitive.

- 2. Edit the element tags as follows:
 - <provider>

The <provider> element of the TM1 security provider contains the details needed to make sure this security provider operates correctly. One TM1 security provider represents one set of users or user groups configured on one or more TM1 servers.

If multiple sets of users and user groups need to be represented, separate instances of this security provider with unique external names need to be configured. Each instance has to reference to its own set of servers.

• <tmlServers>

The <tm1Servers> element contains the list of Cognos TM1 servers that can be used to validate credentials for the users in the represented group. The security provider attempts to connect to the servers in the order as specified. It is assumed that all specified TM1 servers share the same set of users and user groups with their corresponding privileges. Each server in the list is specified in a <tm1Server> element. A TM1 server can be identified by a (http:// or https://) Host:ServerPort string in the element. The host name can be either a netbios or a for fully qualified DNS name, example MyTM1Server or MyTM1Server.mycompany.com.

<adminAccount>

The <adminAccount> element specifies the administrative account that the security provider uses to log on to the specified TM1 Server from the list of TM1 Servers. This account must have sufficient rights on the TM1 server to be able to retrieve information about users and groups.

• <adminPassword>

If the adminPassword encrypted attribute set to true, the password value should contain an encrypted value. You can use the Password Encryption tool to obtain the encrypted password.

• <builtInAdministrators>

The <builtInAdministrators> element is optional and allows certain users or user groups to be set as built-in administrators. Built-in administrators have full access and control over Performance AL Server without having any System or Item Policies specified.

When choosing 'TM1' as the security provider during the setup routine, the specified administrator is added as built-in administrator. This is similar to a Windows built-in administrator on the local system who has the same privilege by design. This is to prevent administrators creating a situation where they cannot access Performance AL Server.

<allowUserToChangePassword>

The optional <allowUserToChangePassword> element allows the user to change the TM1 Data Source credentials. By default a TM1 user is not allowed to change the password. The user needs to contact the TM1 administrator who is allowed the password of the user.

If the <allowUserToChangePassword> element is set to true the Administrator credentials of the TM1 Data Source will be used to allow the user to change his password. This can be useful when the password of the user has expired.

If the <allowUserToChangePassword> element is not specified the value of this element is interpreted as False.

3. Apply password encryption.

If the adminPassword encrypted attribute set to true, the password value should contain an encrypted value.

You can use the Password Encryption tool to obtain the encrypted password.

Configuring the Windows Integrated Security Provider

The Microsoft Windows Integrated Security Provider validates the accounts added to Performance AL Server against the Windows NT Authority System. This security provider supports Windows Integrated Authentication (WIA), so that the user is able to create an Impersonated Session. When an Impersonated Session is created, the user does not have to enter credentials when logging on to Performance AL Server.

Before you begin

The Windows Integrated security provider has no extra system requirements, besides the system requirements to install Performance AL Server. Refer to "Preparing to install".

Procedure

1. Add the following lines to the <securityProviders> element of the EVServer.exe.config file:

</securityProviders>

Note: The element tags are case sensitive.

- 2. Edit the element tags as follows:
 - <domain>

The <domain> element of the Windows Integrated security provider contains the name of the domain that the accounts have to be validated against when System or Item Policies are created, for example: 'cognos.com' for the 'Cognos' domain. **Note:** It is possible to specify multiple domains.

• <builtInAdministrators>

The optional
builtInAdministrators> element allows certain users or users
belonging to certain user groups, to be tagged as built-in administrators. Built-in
administrators have full access and control over Performance AL Server without
having any System or Item Policies specified. The accountname must be fully
specified, including the domain.

The default account on which the Performance Analytics service runs on is 'Local System'. If the Performance Analytics service runs on a different account, settings may need to be adjusted for this account.

<allowNestedGroups>

The optional <allowNestedGroups> element can be used to determine whether nested groups for users should be considered when logging in with username and password. Searching for nested groups can increase the time it takes to login when Windows Intergated Authentication is not possible and the user logs in with username and password. The default value is *false*.

Configuring the Forms Security Provider

The forms security provider is a very plain implementation of a security provider that supports a user password authentication.

Before you begin

The user names and passwords are configured in the EVServer.exe.config file. The security provider does not have any extra system requirements.

When using the forms security provider, Forms should be typed in the Providers field when adding Performance AL Server. This will remove the Domain field from the Logon dialog box.

Procedure

1. Add the following lines to the <securityProviders> element of the of the EVServer.exe.config file:

```
<securityProviders>
<provider type="Forms" externalName="Forms">
<providerCredentials id="userName">
<providerCredential>
</providerCredential>
```

```
</credential>
      <credential>
        <name>password</name>
        <caption>Password</caption>
        <value></value>
        <readonly>false</readonly>
        <password>true</password>
        <optional>false</optional>
      </credential>
    </providerCredentials>
    <users src="users.xml"></users></users>
    <builtInAdministrators>
      <builtInAdministrator>##admin##</builtInAdministrator>
    </builtInAdministrators>
  </provider>
</securityProviders>
```

Note: The element tags are case sensitive.

- 2. Edit the element tags as follows:
 - <providerCredentials>

The <providerCredentials> element of the forms provider configuration contains the user name and password information needed to create a session. This information is required and contains the definition of the user credentials that have to be entered to create a session for this provider.

• <users>

The <users> element contains a reference to an XML file that contains all users known by the forms provider. The credentials specified in this XML have to match the definition specified in the cprovidersCredentials> element.

• <builtInAdministrators>

The <builtInAdministrators> element is optional and allows certain users or user groups to be tagged as built-in administrators. Built-in administrators have full access and control over Performance AL Server without having any System or Item Policies specified.

Note: When choosing forms as security provider during the setup routine, the built-in administrator 'Admin' with no password is added as built-in administrator. This is similar to a Windows built-in administrator on the local system who has the same privilege by design. This is to prevent administrators creating a situation where they cannot access Executive Viewer Server.

3. Add a file with the name users.xml to the same directory as the installation directory of the Performance AL Server. The default directory is: C:\Program Files\cubus\Performance Analytics\Server.

An example users.xml file for one user is as follows:

```
<users>
<users>
<groups>
<group>Group1</group>
</groups>
<userCredentials>
<credential>
<name>userName</name>
<value>User1</value>
</credential>
```

```
<credential>
        <name>password</name>
        <value encrypted="true">encrypted password</value>
      </credential>
    </userCredentials>
    <dataSourceCredentials dataSourceType="##DataSourceType##"</pre>
                           dataSourceServer
="##DataSourceServerName>##">
      <credential>
        <name>userName</name>
        <value>DataSourceUserName</value>
      </credential>
      <credential>
        <name>Password</name>
        <value encrypted="true">
        encrypted DataSourcePassword</value>
        <password>true</password>
      </credential>
    </dataSourceCredentials>
  </user>
</users>
```

- 4. Edit the <user> element tags as follows:
 - <groups> Can be added to specify that a user is part of a group.
 - <userCredentials>
 The credentials of the user that are validated against the Forms Provider.
 - <dataSourceCredentials> The data source credentials. For example, the Data Source Type is 'Essbase' and

the Server Name contains the name of the Essbase server. If a user has created a Session with their credentials, the Forms Provider knows which credentials should be used to log on to the Essbase server. In this way, the Forms Provider provides a 'Single Sign On' environment, preventing the user from having to log on multiple times.

<DataSourceServerName>

The specified server name in the <DataSourceServerName> element must exactly match the OLAP Server name specified in the OLAP Server field when you add a data source in Performance AL Explorer. Refer to "Configuring data sources".

Configuring the Anonymous Security Provider

The anonymous security provider is a security provider that gives the rights to create an anonymous session on Performance AL Server. This Provider supports Windows Integrated Authentication and Forms Authentication. In both of these authentication methods, the user's name during the Session will be 'Anonymous'. System and Item Permissions for this user can be set by adding Policies for the 'Anonymous' account.

Before you begin

The Anonymous Provider has no additional System Requirements.

Procedure

1. Add the following lines to the <securityProviders> element of the EVServer.exe.config file:

Note: The element tags are case sensitive.

2. This Provider does not have any additional configuration settings.

Configuring the Essbase Security Provider

The Essbase Security Provider validates credentials, typically a user name and password combination, against a Oracle Essbase Server. This Security Provider does not support Windows Integrated Authentication.

Before you begin

The proper Essbase Runtime Client needs to be installed on the system running Performance AL Server. The version of the Runtime Client must be exactly the same as the version of Essbase you are using.

Procedure

1. Add the following lines to the <securityProviders> element of the EVServer.exe.config file:

```
<securityProviders>
  <provider type="Essbase" externalName="Essbase"></provider type="Essbase" externalName="Essbase">
    <essbaseServers>
      <essbaseServer>essbase01.company.com</essbaseServer>
      <essbaseServer>essbase02.company.com</essbaseServer>
    </essbaseServers>
    <adminAccount>DemoAdmin</adminAccount>
    <adminPassword encrypted="true">
        encrypted password
    </adminPassword>
    <builtInAdministrators>
      <builtInAdministrator>UserOrGroup01</builtInAdministrator>
      <br/><builtInAdministrator>UserOrGroup02</builtInAdministrator>
    </builtInAdministrators>
  </provider>
</securityProviders>
```

Note: The element tags are case sensitive.

- 2. Edit the element tags as follows:
 - <provider></provider>

The <provider> element of the Essbase Security Provider contains the details needed to make sure this Security Provider operates correctly. One Essbase Security Provider represents one set of users and user groups configured on one or more Essbase servers. If multiple sets of users and user groups need to be represented, separate instances of this Security Provider with unique external names need to be configured. Each instance has to reference to its own set of servers.

• <essbaseServers>

The <essbaseServers> element contains the list of Essbase servers that can be used to validate credentials for the users in the represented group. The Security Provider will attempt to connect to the servers in the order in which they are specified. It is presumed that all specified Essbase servers share the exact same set of users and user groups with their corresponding privileges. Each server in the list is specified by its own <essbaseServer> element. The server name can be either a netbios or a fully qualified DNS name, for example 'MyEssbaseServer' versus 'MyEssbaseServer.mycompany.com'.

• <adminAccount>

The <adminAccount> element specifies the administrative account which the Security Provider should use to log on to (one of) the specified Essbase Server in the list of Essbase Servers. This account should have sufficient rights on the Essbase server to be able to retrieve information about users and groups.

<adminPassword>

The <adminPassword> element specifies the password for the administrative account specified in the <adminAccount> element.

Passwords can be encrypted using the Password Encryption tool.

• <builtInAdministrators>

The <builtInAdministrators> element is optional and allows certain users or user groups, to be tagged as built-in administrators. Built-in administrators have full access and control over Performance AL Server without having any System or Item Policies specified.

Note: When choosing 'Essbase' as Security Provider during the setup routine, the specified administrator is added as built-in administrator. This is similar to a Windows built-in administrator on the local system who has the same privilege by design. This is to prevent administrators creating a situation where they cannot access Performance AL Server.

Configuring the OAuth2 Security Provider

The OAuth 2.0 security provider allows authentication using the <u>OAuth 2.0</u> framework. The OAuth 2.0 mechanism is for example used for the Microsoft Analysis Services cloud version on Azure.

OAuth 2.0 supports different flows for handling credentials. We implement the Authorization Code Grant flow.

Before you begin

The provider supporting the OAuth 2.0 authentication needs to be configured:

• Configuring Azure with OAuth

Procedure

1. Add the following lines to the <securityProviders> element of the EVServer.exe.config file:

```
<tokenEndpoint location="https://login.microsoftonline.com/
[tenant id]/oauth2/v2.0/token"/>
    <logoutEndpoint location="https://login.microsoftonline.com/
[tenant id]/oauth2/v2.0/logout"/>
    <adminRestApi location="https://graph.microsoft.com"
permission="User.ReadBasic.All GroupMember.Read.All"/>
    <application id="[application id]"/>
    <server location="[server url]"/>
    <permission value="Model.ReadWrite.All offline access"/>
    <cacheRetentionPeriod value="1800"/>
    <clientSecret encrypted="false">[client secret]
clientSecret>
   <redirect uri location="https://login.microsoftonline.com/
common/oauth2/nativeclient"/>
   <accessCodeRequestTemplate
value="response type=code&response mode=query&client id=
{applicationID}&redirect uri={redirect uri}
&scope={scope}"/>
   <tokenRequestTemplate
value="grant type=authorization code& client id={applicationI
D}&redirect uri={redirect uri}&scope={scope}
&code={accessCode}"/>
   <builtInAdministrators>
     <builtInAdministrator>UserOrGroup01</builtInAdministrator>
     <builtInAdministrator>UserOrGroup02</builtInAdministrator>
   </builtInAdministrators>
 </provider>
</securityProviders>
```

2. Edit the element tags as follows:

• <authorizationEndpoint>

The endpoint for fetching the OAuth 2.0 access code. For Azure, you need to fill in your tenant id. You can find the full endpoint in the "endpoints" section of your application.

• <tokenEndpoint>

The endpoint for fetching the OAuth 2.0 access token. For Azure, you need to fill in your tenant id. You can find the full endpoint in the "endpoints" section of your application.

- <logoutEndpoint> The endpoint for fetching the OAuth 2.0 access token. For Azure, you need to fill in your tenant id.
- <adminRestApi>
 The endpoint from which Performance Analytics fetches informations about the configured users/groups in Azure. You shouldn't need to change this parameter.
- <application> The application (client) id that will be used to identify the application . For Azure, this is the application (client) ID that you registered for Azure.
- <server> The https address of the server.

• <permission>

The permission that will be requested when logging in. If you followed the steps in <u>Preparing Microsoft Azure</u>, you can keep the value "Model.ReadWrite.All"

• <clientSecret>

A secret string that the application uses to prove its identity when requesting a token. Also can be referred to as application password. In <u>Preparing Microsoft</u> <u>Azure</u> you find a description how to create this value.

<cacheRetentionPeriod>

The Performance Analytics uses a special caching mechanism to store informations about the configured users/groups. This parameter specifies the number of seconds the information stays inside the cache. Afterwards they are removed from the cache and will be fetched again from the Admin REST API. If this parameter is not defined a default value of 30 minutes will be used instead.

 <accessCodeRequestTemplate> This is a template for a request to get an access code. Cannot be defined, default value is

```
"response_type=code&response_mode=query&client_id={app
licationID}&redirect_uri={redirect_uri}
&scope={scope}".
```

<tokenRequestTemplate>
This is a template for a request to get an access token. Cannot be defined,
default value is

```
"grant_type=authorization_code&client_id={applicationID}
&redirect_uri={redirect_uri}&scope={scope}
&code={accessCode}"
```

• <builtInAdministrators>

The <builtInAdministrators> element is optional and allows certain users or user groups, to be tagged as built-in administrators. Built-in administrators have full access and control over Performance AL Server without having any System or Item Policies specified.

See also:

MSAS Data Source Settings

Configuring the OIDC Security Provider

The OIDC Security Provider allows authentication using the <u>OIDC</u> (OpenID Connect) framework. If Keycloak should be utilized as authentication mechanism Performance Analytics has to be configured.

Before you begin

The provider supporting the OIDC authentication needs to be configured:

Preparing Keycloak

Procedure

1. Add the following lines to the <securityProviders> element of the EVServer.exe.config file:

<securityProviders>

```
configurationEndpoint location="https://<root>/auth/realms/
<realm-name>/.well-known/openid-configuration"/>
        <application id="[application id]"/>
        <clientSecret encrypted="false">[client secret]</
clientSecret>
        <redirect_uri location="https://<root>/EVServer"/>
        <adminRestApi location="https://<root>/auth/admin/realms/
<realm-name>"/>
        <builtInAdministrators>
        <builtInAdministrator>UserOrGroup01</builtInAdministrator>
        <builtInAdministrators>
        </builtInAdministrators>
        </builtInAdministrators>
```

- 2. Edit the element tags as follows:
 - <configurationEndpoint>

The endpoint from which Performance Analytics fetches information about the different OpenID connect endpoints. For Keycloak you only need to replace <root> with the address of your server and <realm-name> with the name of your Keycloak realm.

- <applicationId> The application id that will be sent in the access code/token requests.
- <clientSecret>
 The application secret that you created for the application.
- <adminRestApi>

The endpoint from which Performance Analytics fetches informations about the configured users/groups in Keycloak. For Keycloak you only need to replace <root> with the address of your server and <realm-name> with the name of your Keycloak realm.

<builtInAdministrators>
The <builtInAdministrators> element is optional and allows certain users or user
groups, to be tagged as built-in administrators. Built-in administrators have full
access and control over Performance AL Server without having any System or
Item Policies specified.

Overriding request calls

If the OpenID connect provider that is used as authentication provider uses different calls than Keycloak in order to authenticate the client and to refresh the access token it is also possible to override the calls that are made to the OpenID connect server with templates.

1. Enhance the OIDC Provider in the <securityProviders> element of your EVServer.exe.config file so that it looks like this:

```
<application id="[application id]"/>
```

```
<clientSecret encrypted="false">[client secret]
clientSecret>
    <redirect uri location="https://<root>/EVServer"/>
   <adminRestApi location="https://<root>/auth/admin/realms/
<realm-name>"/>
    <accessTokenRequestTemplate
value="response_type=code&response_mode=query&client_id=
{applicationID}&redirect_uri={redirect_uri}"/>
    <tokenRequestTemplate
value="grant type=authorization code&client id={applicationI
D}&redirect_uri={redirect_uri}&code={accessCode}
&client secret={clientSecret}"/>
    <refreshTokenRequestTemplate
value="grant type=refresh token&client id={applicationID}
&refresh token={accessCode}
&client secret={clientSecret}"/>
    <passwordGrantRequestTemplate</pre>
value="grant type=password&client id={applicationID}
&&client secret={clientSecret}&username={username}
&password={password} "/>
   <nativeLogoutRequestTemplate
value="redirect uri={redirect uri}"/>
   <builtInAdministrators>
     <br/><builtInAdministrator>UserOrGroup01</builtInAdministrator>
     <builtInAdministrator>UserOrGroup02</builtInAdministrator>
   </builtInAdministrators>
 </provider>
</securityProviders>
```

- 2. Edit the element tags as follows:
 - <tokenRequestTemplate>
 This parameter can be used to override the HTTP POST call that is made to the
 OIDC server when requesting an access token. The values in brackets (i.e.
 {applicationID}) will be replaced with the
 authentication provider when the call is made.
 - <accessTokenRequestTemplate>
 This parameter can be used to override the HTTP POST call that is made to the
 OIDC server when redirecting the user to the OAuth 2.0 login website. The
 values in brackets (i.e. {applicationID}) will be replaced with the
 configured values in the authentication provider when the call is made.
 - <refreshTokenRequestTemplate>
 This parameter can be used to override the HTTP POST call that is made to the
 OIDC server when requesting a refresh token. The values in brackets (i.e.
 {applicationID}) will be replaced with the configured values in the
 authentication provider when the call is made.
 - <nativeLogoutRequestTemplate>
 This parameter can be used to override the HTTP POST call that is made to the
 OIDC server when logging out of Performance AL Client. It is not used for
 Performance AL Anywhere. The values in brackets (i.e. {applicationID})
 will be replaced with the configured values in the authentication provider when
 the call is made.

<passwordGrantRequestTemplate>

This parameter can be used to override the HTTP POST call that is made to the OIDC server when requesting an access token for the EVCreateReport tool (i.e. when using Subscriptions. The values in brackets (i.e. {applicationID}) will be replaced with the configured values in the authentication provider when the call is made.

Configuring the Log Providers

This section describes how to configure all the built-in log providers for the Performance AL. This section also describes the system requirements and the specific configuration of the EVServer.exe.config file for each log provider.

A Password Encryption tool is part of the installation of Performance AL. If the Password Encryption is used to provide the encrypted password, the encryption strength for encrypted elements in the server configuration file is 2048 bits. The password encryption tool generates 2048 bit encrypted values.

The Password Encryption tool can be found here

```
C:\Program Files\cubus\Performance Analytics\Server\Tools\PasswordEncrypt.
```

Log entry	Description
Severe	The highest level of detail. Only severe errors are logged. These are errors that may cause a situation where Performance Analytics is unusable.
Error	All errors are logged. These are situations where the Performance Analytics Server can run, but, for example, a provider cannot be started.
Warning	Warnings are logged, for example, when a Provider is not correctly configured.
Info	Information is logged, for example the start and stop of the Performance Analytics service.
Verbose	More detailed information is logged, for example the loading of the Catalog Items.
Trace	The same information as in 'Verbose' is logged, only more detailed.
Debug	The lowest level detail. All possible information is logged.

Performance AL Server generates different level of log entries:

Log categories

The log categories are:

• General

- Session
- Security
- Configuration
- InternalError
- UnsupportedType
- ParameterValidation

Log components

The log components are:

Log Component	Name
Server	Server
Log provider	LogProviders.File LogProviders.Mail LogProviders.XML LogProviders.SQLServer LogProviders.Event LogProviders.Console LogProviders.Oracle
Catalog provider	CatalogProviders.SQLServer CatalogProviders.Oracle
Security provider	SecurityProviders.TM1 SecurityProviders.CAM SecurityProviders.Forms SecurityProviders.Anonymous SecurityProviders.Windows SecurityProviders.Essbase
Connect type specific	TM1 OEMProviders.Base Cub Essbase EssbaseDispatch Gateway MDX MSAS MSDSO

Log providers

The <logProviders> element must contain the configured log providers as shown in the example below:

```
<legProviders defaultProvider="##ExternalNameDefaultLogProvider##">
<provider type="##ASSEMBLYNAME##" externalName="##EXTERNALNAME##">
<properties>
<Property PropertyName="##PROPERTYVALUE##" />
</properties>
<logLevelTable>
<logLevels>
<logLevels>
<logLevels>
</logLevels>
```

The element tags have these definitions.

• <logProviders>

The <logProviders> element can contain an extra attribute which specifies the Default Log Provider. Performance AL Explorer only shows the log entries of the Default Log Provider.

Note: When working with the web service of Performance AL Server, the default log provider must support readback if the method GetLogEntries is executed. This means that the log provider is able to read the log entries from the output destination. Not all log providers are able to readback the log entries. If the default log provider does not support readback, this method will fail.

• <properties>

The <properties> element is an aditional tag for some log providers. When this element is specified it configures the log provider. The element is specific for each log provider and is mandatory when specified.

• <logLevelTable> and <logLevels>

The <logLevelTable> element defines which log entries will be logged by the specified Log Provider. This can be specified in the <logLevels> element. This element can contain multiple <logLevel> elements. It is possible to store Log Entries for each Log Category or Log Component.

Example for the XML Log Provider:

```
<legLevelTable>
<logLevels>
<logLevel logLevel="Severe" category="General"
component="Server" />
<logLevel logLevel="Info" category="General" component="MDX" /
>
</logLevels>
</logLevels>
```

This XML Log Provider records all general server log entries that have the logLevel severe and all general MDX log entries that have the logLevel info. A log provider can have more than one logLevel and the EVServer.exe.config can define more than one log provider.

A '*' denotes a wild card. All log entries for these items are recorded.

When a log provider is not configured for Performance AL Server, the Windows Event Log records all log errors of all log components and all log categories with the log level Warning, Error or Severe.

After installation, the default Log Provider is the XML Log Provider on 'Warning' Level. The XML file 'EVServerLog.xml' is created every day in the installation directory, which is by default C:\Program Files\cubus\Performance Analytics\Server.

Configuring the Event Log Provider

The Event Log Provider sends log entries to the Windows Event Log.

This Provider does not support readback. For explanation about readback, refer to "Configuring the Log Providers".

Before you begin

The Event Log Provider has no extra system requirements.

Procedure

 Add the following lines to the <logProviders> element of the EVServer.exe.config file:

Note: The element tags are case sensitive.

 Edit the element <logLevelTable>. Refer to <logLevelTable> and <logLevels> for information.

Configuring the XML Log Provider

The XML Log Provider sends log entries to a file specified in the EVServer.exe.config file. This provider supports readback. For explanation about readback, refer to <logProviders>.

Before you begin

If the Performance AL service runs on an account, this account needs to have 'write' and 'modify' permissions at the location specified in the <file>'path' element.

Procedure

1. Add the following lines to the <logProviders> element of the EVServer.exe.config file:

Note: The element tags are case sensitive.

2. The <file> element has two attributes. Path and createEvery. Edit the Path attribute:

This attribute contains the destination path of the file to which the log entries are written. If the file does not exist, it is created. Some examples are:

- <file path="C:\Temp\EVServer.xml"/>
 Note: Make sure the directory Temp exists.
- <file path="EVServer.xml"/>
 Note: The EVServer.xml log file is created in the same directory as the
 installation directory of Performance AL Server, which is by default C:\Program
 Files\cubus\Performance Analytics\Server\Logs\EVServer.xml
 Make sure that the Logs directory exists.
- 3. Edit the createEvery attribute.

This attribute is optional. The options are:

• Value

Note: The 'createEvery' attribute sets the size of the log file in MB's. If createEvery is set to '2', a new Log File is created when the Log File reaches a size of 2 MB.

- Hour Note: A new log file is created every hour.
- Day Note: A new log file is created every day.
- Week

Note: A new log file is created every week.

Month

Note: A new log file is created every month.

- Year Note: A new log file is created every year.
- 4. Edit the element <logLevelTable>. Refer to <logLevelTable> and <logLevels> for information.

Configuring the Mail Log Provider

The Mail Log Provider sends log entries to the e-mail address specified in the EVServer.exe.config file.

This Provider does not support readback. For explanation about readback, refer to <logProviders>.

Before you begin

The Mail Log Provider needs access to an SMTP server that sends the log entries to the specified e-mail address. Refer to the documentation of the SMTP server for additional requirements.

Procedure

1. Add the following lines to the <logProviders> element of the EVServer.exe.config file:

```
<logProviders
defaultProvider="##ExternalNameDefaultLogProvider##">
  <provider type="Mail" externalName="MailLogProvider">
    <properties>
      <config mailTo="##administrator@company.com##"
              from="##support@company.com##" />
      <network server="##mail.company.com##" />
    </properties>
    <logLevelTable>
      <logLevels>
        <logLevel logLevel="##LOGLEVEL##"
                                       category="##LOGCATEGORY##"
component="##LOGCOMPONENT##" />
      </logLevels>
    </logLevelTable>
  </provider>
</logProviders>
```

Note: The element tags are case sensitive.

- 2. In the the mailTo attribute of the <config> element, type the e-mail address that receives the e-mails generated by the Mail Log Provider.
- 3. In the from attribute of the <config> element, type the e-mail adress from where the mail is sent.
- 4. In the server attribute of the <network> element, type the SMTP mail server that sends the e-mails generated by the Mail Log Provider.
- 5. In the port attribute of the <network> element, type the port of the SMTP mail server from where the mail has to be sent. The port attribute is optional.
- 6. Edit the element <logLevelTable>. Refer to <logLevelTable> and <logLevels> for information.

Configuring the SQL Server Log Provider

The SQL Server Log Provider stores log entries in a SQL Server database.

This Provider supports readback. For explanation about readback, refer to <logProviders>.

Before you begin

Microsoft SQL Server

Procedure

1. Add the following lines to the <logProviders> element of the EVServer.exe.config file:

```
<logProviders
defaultProvider="##ExternalNameDefaultLogProvider##">
                                                  type="SQLServer"
                    <provider
externalName="SQLServerLogProvider">
    <properties>
      <dataSource pwdEncrypted="false"</pre>
                                    connectionString="##SQLSERVER
CONNECTIONSTRING##" />
    </properties>
    <logLevelTable>
      <logLevels>
        <logLevel logLevel="##LOGLEVEL##"
                                        category="##LOGCATEGORY##"
component="##LOGCOMPONENT##" />
      </logLevels>
    </logLevelTable>
  </provider>
</logProviders>
```

Note: The tags are case sensitive.

 Edit the dataSource element. The connectionString SQL Server Connection String has the following structure: For standard security: Server=##SERVERNAME##; Database=EVLog; UID=sa;Pwd=##PASSWORD##

For integrated security: Server=##SERVERNAME##; Database=EVLog;Integrated Security=SSPI

- Apply password encryption.
 Password encryption applies only to standard security.
 If the pwdEncrypted attribute set to true, the password value should contain an encrypted value.
 You can use the Password Encryption tool to obtain the encrypted password.
- 4. Edit the element <logLevelTable>. Refer to <logLevelTable> and <logLevels> for information.
- 5. Refer to the SQL Server documentation for more information about connection strings that can be used to connect to SQL Server.

Configuring the Oracle Log Provider

The Oracle Log Provider stores log entries in an Oracle database.

This Provider supports readback. For explanation about readback, refer to <logProviders>.

Before you begin

Ensure that an Oracle client is installed.

Procedure

1. Add the following lines to the <logProviders> element of the EVServer.exe.config file:

```
<logProviders
defaultProvider="##ExternalNameDefaultLogProvider##">
  <provider type="Oracle" externalName="OracleLogProvider">
    <properties>
                       <dataSource connectionString="##ORACLE</pre>
CONNECTIONSTRING##" />
   </properties>
    <logLevelTable>
      <logLevels>
        <logLevel logLevel="##LOGLEVEL##"
                                       category="##LOGCATEGORY##"
component="##LOGCOMPONENT##" />
      </logLevels>
   </logLevelTable>
  </provider>
</logProviders>
```

Note: The tags are case sensitive.

- Edit the dataSource tag. The connectionString Oracle connectionString has the following structures: Data Source=##TNSNAME##; UID=##USERNAME##; Pwd=##PASSWORD##;
 - 3. Apply password encryption.

If the pwdEncrypted attribute set to true, the password value should contain an encrypted value.

You can use the Password Encryption tool to obtain the encrypted password.

- 4. The connection user needs the following rights:
 - CREATE PROCEDURE
 - CREATE SEQUENCE
 - CREATE SESSION
 - CREATE TABLE
 - Write access to the corresponding tablespace
- 5. Refer to the Oracle documentation for more information about connection strings that can be used to connect to Oracle.

Configuring the Shared Backend Log Provider

The Shared Backend Provider is a special provider. It writes logs to a separate log files. Only the file path and the log level are configurable for this Provider.

Before you begin

The Shared Backend Log Provider has no extra system requirements.

Procedure

 Add the following lines to the <logProviders> element of the EVServer.exe.config file:

Note: The element tags are case sensitive.

- 2. In the the path attribute of the <file> element, type the destination path of the file to which the log entries are written. If the file does not exist, it is created.
- 3. In the the logLevel attribute of the <logLevel> element, type the desired log level.

Configuring the mail-server

The configured mail-server is used for sending the scheduled report subscriptions.

Before you begin

Ensure the required SMTP server is up and running. Also check if the user is set up on the mail-server and has the required permissions.

Procedure

 Add the following lines to the <system.net> element of the EVServer.exe.config file:

```
<system.net>
<mailSettings>
<smtp>
<network defaultCredentials="false" enableSsl="false"
host="##SMTPSERVERNAME##" userName="##SMTPUSERNAME##"
password="##SMTPPASSWORD##" />
</smtp>
</mailSettings>
</system.net>
```

2. Restart the **Performance Analytics** service for the changes to take effect.

6. Performance AL Server API

Performance AL Server has an API (Application Progam Interface). This API is available as a web service.

A web service API is an API that allows you to perform operations on a remote system that hosts a particular service. In this case the Performance AL Server.

For example you can use the web service of Performance AL Server to dynamically retrieve HTML code for the Performance AL Client, create and manage items, set security or view log entries.

You can also create scripts to automate tasks, for example to create a backup, migrate from one (test) environment to another environment or call these methods from a DTS (Data Transformation Services) package.

You can use these web service API methods to create your own (ASP.NET) application. An example of how to use the web service of Performance AL Server is Performance AL Explorer.

For more information, see the *Performance Analytics Server API Reference*.

URL API

The URL API makes views in the Performance AL Server repository adressable through a URL.

When you enter a URL in your browser an HTTP request is sent to Performance AL Server. This HTTP request is processed by the HTTP handler and results in either a web service call or a URL API call. The result is an HTML page that contains Performance AL Client with a specific view or canvas. The syntax and the options of this URL are explained in this section.

The URL API is installed when you install Performance AL Server.

HTTP handler

The Performance AL HTTP handler enables you to either send requests to Performance AL Server Web Service or to use the functionality of the URL API.

By default Microsoft Internet Information Server (IIS) passes the HTTP requests to a web application to request a file that needs to be on the Server.

To enable the URL API functionality the following code is added to the web.config file that is located C:\Program Files\cubus\Performance Analytics\Server\WebService.

<httpHandlers> <add verb="*" path="URL API"type="Cognos.EV.ServerURLAPIHandler,

```
WebService"
    validate="false" />
</httpHandlers>
```

The <httpHandlers> element tells IIS that HTTP requests to the path http:// ##ServerName##/EVServer are managed by the HTTP handler. The HTTP handler determines if the request is either a Web Service call or a URL API call.

URL API syntax

The URL of the URL API is specified by "http://<ServerName>/EVServer" followed by a set of URL API options for both IIS and the Web Service.

To pass options to the URL API, the following syntax is used:

```
http://<ServerName>/EVServer?<option>=<optionvalue>&<option>=<optionvalue>
http://<ServerName>/EVServer?Action=Render&item=<ItemPath>
```

The first option is preceded by "?". The second and subsequent options are preceded by "&". The option value is assigned to the option by "=".

Note: Some characters in a HTTP request need to be encoded when using the URL API. For more information, see URL API - encoded characters.

Generic option parameters

The URL API defines a set of general URL API option parameters. These parameters are:

- Action
- Title
- BG Color
- TextColor
- Authentication

Action

The action parameter describes the specific setting that the URL API is required to do. The actions are that the URL API can return are:

- Render
- UpdatePreload
- Image
- CustomItem
- ListItems
- listnamedusers
- listconcurrencycounters

If an action is not specified in the URL API, then the default value of the action depends of the type of item that is specified in the item parameter. When you specify an item to have the item type image or custom, then the default action is either Image or CustomItem.

In all other cases the default action is Render. This also includes cases when no item at all is specified.

Title

The title parameter describes the title of the HTML page. If there is no title or an empty title parameter, and the Action parameter is set to Render the following applies:

- For a specified item, the title of the page contains "Performance AL Client" followed by the name of the requested item.
- For a none specified item the title of the page is "Performance AL Client".

BG Color

The background color parameter for the HTML page. The possible values are:

- All known system colors. The value can be an RGB value or an hexadecimal value. The hexadecimal value can have values between "000000" and "FFFFFF" predefined with an optional "#".
- Default value: none

TextColor

The text color of the HTML page. The possible values are:

- All known system colors. The value can an RGB value or an hexadecimal value. The hexadecimal value can have values between "000000" and "FFFFFF" predefined with an optional "#".
- Default value: none

Authentication

The authentication parameter applies the system and item security. For Performance AL Server to be able to authenticate a user a session is created.

A Performance AL Server session is created when a user logs on to Performance AL Server. After the user is successfully authenticated, then the Performance AL Server retrieves the appropriate permissions, for example to use views or to connect to an OLAP database. During the creation of a session credentials are passed to the Performance AL Server.

Performance AL Server passes these credentials to a configured security provider. This security provider validates whether the user is allowed to log on to the system with the specified credentials. Once a session is created, this session provides the access to Performance AL Server.

The "Authentication" parameter of the URL API enables you to specify which security provider should be used to create a Performance AL Server session. The "Authentication" URL API parameter must match the "externalName" of the configured security provider that needs to be used.

Security providers can require credentials such as a user name and a password. If the specified security provider requires these credentials, these credentials must be specified in order to enable the security provider to validate whether the user is allowed to create a Performance AL Server session.

For information about security providers, see "Specifying the security providers".

• Possible values: The possible values of the "Authentication" parameter depend on which security providers are configured for Performance AL Server. If the specified

security provider requires credentials, then you have to add these credentials to the URL API request as well. For example, if a security provider requires a user name and a password to validate a user, then the following needs to be added to the URL API request:

http://<ServerName>/EVServer?

<ItemPath>&Authentication=Example&UserName=<UserName>&Password=<Password>

• Default value: There is no default value for this option.

Action: render

The render action results in an HTML page that contains Performance Analytics Client with the requested item. If Performance AL Client is not installed on your system, you are prompted to install the software.

For more information, see Installing Performance AL Client.

The following parameters apply to the action: render.

- RenderType
- XSLT

RenderType

The type of output that renders the view. The possible RenderType settings are:

• ActiveX

If the RenderType is set to "ActiveX", then the URL API returns an HTML page that contains the Performance AL Client that shows the requested item. If no RenderType is specified, then the RenderType is set to "ActiveX".

• XML

If the RenderType is set to "XML", then the URL API returns either XML or transformed XML.

• GridXML

If the RenderType is set to "GridXML", then the URL API returns an XML or transformed XML representation of the grid of a view item.

To retrieve transformed output from the URL API, you have to add an extra XSLT parameter to the URL API Request.

When the RenderType is set to "ActiveX", then the returned HTML page is created by using the "Default.xslt" file. The "Default.xslt" file is available in the installation directory of the web service. The default location of the "Default.xslt" file is "C:\Program Files \cubus\Performance Analytics\Server\WebService\XSLT". It is not possible to specify an additional XSLT parameter if the RenderType is set to ActiveX.

When the RenderType is set to "XML", then the URL API returns XML or transformed XML. If you do not specify an XSLT parameter or if you specify an empty XSLT parameter, then the URL API returns an XML file. This XML file contains the following information:

```
<EVClient>
<object displayMode="">
<id />
<name />
```

```
<width />
   <height />
   <codeBase />
    <classId />
   <server />
    <protocol />
   <port />
    <camPassport />
   <sessionId />
   <help />
   <theme />
    <enableToolbar />
    <defaultView />
   <enableTabBar />
   <enableViewsButton />
   <viewLocations />
   <tabbarPosition />
  </object>
</EVClient>
```

Parameter	Description	Opt	Default value
Item	The item to be opened by Performance AL Client. Value = A path to an item or an item name if the item is located in the root folder The ItemType must be view, canvas, or folder. If a canvas or folder item is specified, then Performance AL Client opens all associated views. Returned in the <defaultview> element</defaultview>	Yes	Performance AL Client is rendered without an active view.
or	lame>/EVServer? <itempath lame>/EVServer?Item=<iten< td=""><td></td><td>></td></iten<></itempath 		>
ControlID	The ID of the <object> element that contains the Performance ALcontrol.</object>	Yes	EVObject
DisplayMode	Sets the type of control that is used to show the view. Value = View	Yes	View

Syntax http:// <servern< th=""><th>ame>/EVServer?DisplayMod</th><th>de=Vi</th><th>ew</th></servern<>	ame>/EVServer?DisplayMod	de=Vi	ew
TabBar	Sets the tab bar to show or not. Value = true or false	Yes	false
Syntax			
http:// <servern< td=""><td>ame>/EVServer?DisplayMod</td><td>de=Vi</td><td>ew&TabBar=true</td></servern<>	ame>/EVServer?DisplayMod	de=Vi	ew&TabBar=true
TabBarPosition	Sets the position of the tab bar. Value = Top, Bottom, or Theme. If set to theme then the position is: Classic = bottom Sky = top Ocean = top Desert = top Forest = top Olive = top Silver = top	Yes	Theme
Toolbar	Sets the tool bar to show or not. Value = True or False	Yes	False
Syntax http:// <servern< td=""><td>ame>/EVServer?DisplayMod</td><td>de=Vi</td><td>ew&Toolbar=true</td></servern<>	ame>/EVServer?DisplayMod	de=Vi	ew&Toolbar=true
Theme	Sets the background theme for Performance AL. Values = Classic, Sky, Ocean, Desert, Forest, Olive, Silver	Yes	Classic
CreateControl Uri	Sets the address location of the .js file Value = The path to the CreateControl.js file.	Yes	/EVServer/ CreateControl.js
Culture	Sets the language culture for Performance AL Client Values = da-DK, de-DE, en-US, es-ES, fr-FR, it-IT, ja-JP,	Yes	Culture of the system

	ko-KR, nl-NL, pt-BR, zh-CN, zh-TW.		
Syntax http:// <server< td=""><td>name>/EVServer? DisplayMo</td><td>de=V</td><td>iew&TabBar=true&culture=en</td></server<>	name>/EVServer? DisplayMo	de=V	iew&TabBar=true&culture=en
Help	The path to a help file or a set of help files in Performance AL Client. Once set, a help button is added to the toolbar. Value = A valid URL to an HTML page The HTML page can be either your own HTML page or the Performance Analytics User Guide as a HTML file.	Yes	None
•	name>/EVServer?DisplayMoo /EVExplorer/WebHelp/index		ew&Toolbar=true&Help=http://

Display mode:

The following options are dependent of the chosen "DisplayMode":

Viewlocations

Option that specifies the exact location where views or canvases are stored in the repository.

Possible values: A string that contains a valid view location. The logical name and the location (path) are separated by an "=" character. To specify more than one view location, separate the entries a semi-colon ";". The syntax is for example:

Sales Views = /Sales/SalesView; Marketing Views = /Marketing/ MarketingFolder

- Optional: yes
- Default value: empty
- o Dependent on: only available for the DisplayMode "View".

ViewsDialog

Option to show the "Views" button on the toolbar.

- Possible values: "True" or "False"
- Optional: yes
- Default value: "True"
- Dependent on: only available for the DisplayMode "View".

RenderType is set to GridXML:

• Item

The item that needs to be opened by Performance AL Client.

 Possible values: A path to an item. A name of an item if this item is located in the root folder. For more information about the root folder, see "Folders that are added during the installation of Performance AL".
 In both cases this item needs to have the ItemType "View"

In both cases this item needs to have the ItemType "View".

no

- Optional:
- Default value: Since this parameter is not optional, a default value is not applicable.
- Syntax: In contrast to other URL API options it is possible to specify an item without entering the Option by adding "Item=" to the HTTP Request. This Item needs to be defined immediately after the "?" character.

For example: http://<ServerName>/EVServer?<ItemPath> has the same result as:

http://<ServerName>/EVServer?Item=<ItemPath>.

• Context

Context of the data as a string. Context represents an XML document that holds the context of the data to be returned. The context can be used to define the offspread selection of the view.

Possible value:

The format of the context XML is as follows:

```
<root>
  <context>
    <dimension>plan_time</dimension>
    <member>2006</member>
  </context>
    <dontext>
    <dimension>plan_region</dimension>
    <member>USA</member>
  </context>
</root>
```

- Optional: yes
- Remark: The value of the Context option is XML. Some characters in this XML need to be encoded when using the URL API. For more information, see "URL API - encoded characters".

• DimensionInfo

The status of information for each dimension in the generated XML as a boolean.

Possible values:

"True": Additional information for each member and dimension is generated in the XML.

"False": Additional information for each member and dimension is not generated in the XML.

- Optional: yes
- Default value: "True"
- Formatting

The status of formatting of a view in the generated XML as a boolean.

Possible values:

"True": The formatting of the view will be included in the generated XML.

"False": The formatting of the view will not be included in the generated XML.

- Optional: yes
- Default value: "True"

• Offspread

The status of the offspread area in the generated XML as a boolean.

- Possible values:
 "True": The offspread area is generated in the XML.
 "False": The offspread area is not generated in the XML.
- Optional: yes
- Default value: "True".

• Table

The status of the table grid in the generated XML as a boolean.

- Possible values:
 "True": The table grid is generated in the XML.
 "False": The table grid is not generated in the XML.
- Optional: yes
- Default value: "True"

XSLT

With the "XSLT" parameter you can specify the XSLT that needs to be used for the XSLT transformation.

The value of the "XSLT" parameter will only be interpreted when the "RenderType" parameter has been set to either "XML" or "GridXML". For more information, see "RenderType". The possible values are:

• An XSLT file name

If you specify the XSLT file name, then the URL API loads the file from the default XSLT directory.

When the XSLT file name is specified, a user does not have to add the ".xslt" extension to the file name.

The default XSLT directory is set to "C:\Program Files\cubus\Performance Analytics\Server\WebService\XSLT".

You can change the default XSLT directory by setting the "XsltPath" in the "web.config" file. The default location of the "web.config" file is

"C:\Program Files\cubus\Performance Analytics\Server\WebService\".

If the XsltPath has been set, then the URL API checks this directory for the specified XSLT.

Add the following code to the <configuration> section in the "Web.Config" file of the web service to set the XsltPath:

```
<configuration>
<appSettings>
<add key="XsltPath" value="Your XSLT Path" />
```

</appSettings> </configuration>

• An XSLT file location

When you specify the XSLT file location, then you must also specify the ".xslt" extension like:

http://localhost/EVServer?Toolbar=true&RenderType=Xml&Xslt=http://localhost/ EVServer/Xslt/yXslt.xslt

or

http://localhost/EVServer?Toolbar=true&RenderType=Xml&Xslt=C:\Temp\ MyXslt.xslt

It is possible to specify a local directory, such as "c:\", a web location: "http://", or, a relative path to the XSLT path.

The relative path is derived from the default XSLT directory. The default XSLT directory is set to "C:\Program Files\ cubus\Performance Analytics\Server \WebService\XSLT".

You can change the default XSLT directory by specifying the "XsltPath" in the "web.config" file.

The default location of the "web.config" file is "C:\Program Files\ cubus \Performance Analytics\Server\WebService\". If this XsltPath has been set, then the URL API checks this directory for the specified XSLT.

Add the following code to the "configuration" section of the Web Service's "Web.Config" file to set the XsltPath:

```
<configuration>
<appSettings>
<add key="XsltPath" value="Your XSLT Path" />
</appSettings>
</configuration>
```

Please make sure the user has sufficient rights to access the specified XSLT file.

• Default value: empty. If the "XSLT" parameter is empty, then XML will be returned by the URL API. Depending on the RenderType, a set of render options is supported.

Examples

Example 1

If you want to render Performance Analytics Client that show the view "MyView", with the tab bar enabled and using the theme "Ocean", then the URL to type in your browser looks like:

http://<ServerName>/EVServer?MyView&Tabbar=True&Theme=Ocean

Example 2

Below is an example of the encoded notation for the view "Profit & Loss" in the folder "Financial". For more information, see "URL API - encoded characters" on page 96.

http://<ServerName>/EVServer?/Financial/Profit%20%26%20Loss

Example 3

It is not necessary to specify an item in the URL.

The example below results in only the Performance AL Client being displayed, without a

view.

http://<ServerName>/EVServer?DisplayMode=View

Action: updatepreload

The UpdatePreload URL API action triggers Performance AL Server to verify if the preloaded databases need to be updated and does so when necessary.

This action updates the preloaded databases by specifying:

- An item (database or data source)
 If a database has been specified, the preload of this particular database will be verified. In the case of a data source the preloads of all databases that use the specified data source will be verified.
- A filter specified by a DataSourceType and optional Server and database name. In this case all databases that match the criteria (DataSourceType, Server and database name) will be verified and updated when necessary.
 Note: The UpdatePreload action preloads only those databases that are marked for

Note: The Update Preload action preloads only those databases that are marked for preloading.

The following options apply to the UpdatePreload action:

• Item

The database item or data source item that needs to be verified for preloading.

• Possible values:

A path to a database item or a data source item.

A name of a database item or a data source item if this item is located in the root folder. For more information about the root folder, see "Folders that are added during the installation of Performance AL".

- o Optional: yes. Either an item or a filter has to be specified.
- Syntax: It is possible to specify an item without entering the option by adding "Item=" to the HTTP request. This needs to be defined immediately after the "?" character.

For example: <u>http://<ServerName>/EVServer?<ItemPath></u> has the same result as: <u>http://<ServerName>/EVServer?Item=<ItemPath></u>

• DataSourceType

The DataSourceType determines which databases, referring to a data source that have the specified DataSourceType, need to be verified.

- Possible values: "TM1", "MSAS", "Essbase"
- Optional: If an item has been specified, then this option will be ignored. If a filter has been specified (DataSourceType, Server, Database), then you must set this option.

• Server

The name of the Server determines which databases, referring to a data source that connects to the specified Server, need to be verified.

- Possible values: The name of the Server that needs to be filtered.
- Optional: If an item has been specified, then this option will be ignored. In the case of a filter the Server name is optional.
- Database

The name of the physical database which needs to be verified.

- $\circ\,$ Possible values: The name of the physical database that needs to be filtered.
- Optional: If an item has been specified, this option will be ignored. In the case of a filter the database name is optional.

Examples

Example 1

The following UpdatePreload example uses a database item or a data source item: http://<ServerName>/EVServer?action=UpdatePreload&item=<ItemPath>

Example 2

The following UpdatePreload example uses a filter (required: DataSourceType, optional: Server name and database name):

```
http://<ServerName>/EVServer?action=UpdatePreload&server=<physicalserver>
&database=<physicaldatabase>&datasourcetype=<datasourcetype>
```

Example 3

The following UpdatePreload example uses ForcePreload set to true forces the Performance AL Server to do a preload or reload of the specified database.

```
http://<ServerName>/EVServer?action=UpdatePreload&item=<ItemPath>
&forcepreload=true
```

Action: image

The image URL API action triggers Performance AL Server to return the requested image item as a file.

The following options apply to the image action:

Item: The image item that needs to be triggered for downloading.

- Possible values: A path to a valid image item. A name of an image item if this item is located in the root folder.
- Optional: no
- Syntax: It is possible to specify an item without entering the option by adding "Item=" to the HTTP request. This needs to be defined immediately after the "?" character.

For example:

```
http://<ServerName>/EVServer?<ItemPath>
has the same result as
```

http://<ServerName>/EVServer?Item=<ItemPath>

Examples

Example 1

The following example results in the retrieval of the requested image item:

http://<ServerName>/EVServer?action=Image&item=<ItemPath>

Example 2

The following example results in the retrieval of the requested image item:

http://<ServerName>/EVServer?<ItemPath>

Note: In this example the ItemPath needs to represent the path to an image item in the repository.

Action: customitem

The CustomItem URL API action triggers Performance AL Server to return the requested custom item as a file.

The following options apply to the CustomItem action:

Item: The custom item that needs to be triggered for downloading.

- Possible values: A path to a valid custom item. A name of a custom item if this item is located in the root folder.
- Optional: no
- Syntax: It is possible to specify an item without entering the option by adding "Item=" to the HTTP request. This needs to be defined immediately after the "?" character.

For example:

http://<ServerName>/EVServer?<ItemPath>
has the same result as:
 http://<ServerName>/EVServer?Item=<ItemPath>

Examples

Example 1

This example results in the retrieval of the requested custom item: http://<ServerName>/EVServer?action=CustomItem&item=<ItemPath>

Example 2

This example results in the retrieval of the requested custom item: http://<ServerName>/EVServer?<ItemPath>

Note: In this example the ItemPath needs to represent the path to a custom item in the repository.

Action: listitems

This action triggers Performance AL Server to extract data from the Performance AL Server repository.

Calling the list method via the URL API list is done in the following way:

```
http://<servername>/EvServer?action=ListItems&<field>=<value>...&fields=<field>
```

action

The action that has to be performed by the URL API. If you want to use the list method via the URL API you must define which list you want to receive. You do this by specifying an action. For the list method currently the "ListItems" is supported. The list method "ListItems" returns all items in the repository.

fields

The fields that have to be returned. This is a comma separated list that specifies the desired field names.

Generic item fields

<items>

Examples

Example 1

Shows all views:

```
http://<YourEVServer>/EvServer?action=ListItems&type=view
http://<YourEVServer>/EvServer?action=ListItems&type=canvas
```

Example 2

Shows all valid items:

http://<YourEVServer>/EvServer?action=ListItems&status=valid

Example 3

Shows all items modified from February, 1st 2010:

```
http://<YourEVServer>/EvServer?action=ListItems&modificationDate=20100201-
```

Action: listnamedusers

This action triggers Performance AL Server to list the named users that access the specified Performance AL Server.

For more information, see Monitoring.

Using the listnamedusers method you can use the "listnamedusers" method via the URL API.

Procedure

1. Open Microsoft Internet Explorer.

```
2. Enter the following URL:
    http://<yourevserver>/evserver?action=listnamedusers
```

Results

The XML that is returned looks like this:

```
<?xml version="1.0" encoding="utf-8"?>
<licenseMonitoring>
  <namedUsers>
    <namedUser>
      <uniqueUserName>User 1</uniqueUserName>
      <userName>My Name 1</userName>
      <provider>Forms</provider>
      <firstConnect>2009-10-19T00:00:00</firstConnect>
      <lastConnect>2009-10-19T10:00:00</lastConnect>
    </namedUser>
    <namedUser>
      <uniqueUserName>User 2</uniqueUserName>
      <userName>My Name 2</userName>
      <provider>Forms</provider>
      <firstConnect>2009-11-20T00:00:00</firstConnect>
      <lastConnect>2009-11-21T11:00:00</lastConnect>
    </namedUser>
  </namedUsers>
</licenseMonitoring>
```

Action: listconcurrencycounters

This action triggers Performance AL Server to list the concurrent ports and the concurrent users that acces the specified Performance AL Server.

For more information, see Monitoring.

Using the listconcurrencycounters method you can use the listconcurrencycounters method via the URL API.

Procedure

1. Open Microsoft Internet Explorer.

```
2. Enter the following URL:
    http://<yourevserver>/evserver?action=listconcurrencycounters.
```

Results

The XML that is returned looks like this:

```
<portCount>2</portCount>
<userCount>3</userCount>
</counter>
</concurrencyCounters>
</licenseMonitoring>
```

URL API - encoded characters

Some characters need to be encoded when using the URL API, otherwise these characters are not interpreted as part of the specified name.

The encoded character consists of "%" character followed by the hexadecimal representation of the specified character.

For example:

```
http://<ServerName>/EVServer?Item=Profit & Loss&BGColor=#dde4ed
should be typed as:
    http://<ServerName>/EVServer?Item=Profit%20%26%20Loss&BGColor=%23dde4ed
```

The second "&" is a reserved character to separate the request parameters. Therefore this character does not have to be replaced.

The following characters must be encoded with the hexadecimal value:

- All characters with ASCII decimal values between 0 and 31.
- All characters with ASCII decimal values equal or greater than 127.
- All unsafe characters. A character can be unsafe for many reasons. For example, the character "#" is used in World Wide Web to delimit a URL from a fragment identifier that follows it.
- All reserved characters. Many URL schemes reserve characters for a designated semantic.

Unsafe Characters	Example	Hexadecimal Value
Space		20
Quotation mark	н	22
Pound character	#	23
Percent character	%	25
Plus	+	2B
Minus	-	2D
Less than symbol	<	3C
Greater than symbol	>	3E
Left square bracket	[5B

Backslash	١	5C
Caret	۸	5E
Right square bracket]	5D
Grave accent	、	60
Left curly brace	{	7B
Vertical pipe	1	7C
Right curly brace	}	7D
Tilde	~	7E

Reserved Characters	Example	Hexadecimal Value
Ampersand	&	26
Forward slash	1	2F
Colon	:	3A
Semi-colon	;	3B
Equals	=	3D
Questionmark	?	3F
At-Symbol	@	40

Error messages

If an error occurs, then the URL API will display one of the following error messages.

The URL API Method "<Action Name>" is not supported.

The RenderType "<rendertype>" is not supported.

The parameter "<paramname>" is not specified. This parameter should be specified when calling the requested Method "<Action Name>".

The URL API could not create a Session. Please check the specified parameters in the url and the configuration of the server.

Missing parameter: UpdatePreload must be called with eiter an item or a valid DataSourceType.

Unsupported ItemType: The Item "<itempath>" having ItemType "<itemtype>" is not

supported for the specified URL API Action "<Action Name>".

Invalid Image format: Supported file types are "jpeg", "gif", "bmp" and "png".

Invalid Item Status: The Item Status of the specified Item "<itempath>" is invalid.

No Item Data: The specified Item "<itempath>" does not contain any Item Data. Invalid list specified.

The XSLT Transformation failed. Additional Information: <additionalinfo>.

The specified Xslt file location did not contain the ".xslt" file extension.

The specified Render Option Value is not supported for this Render Option.

Note: The possible exceptions defined by the "Render" action can also occur when using the URL API.

The possible exceptions defined by the "UpdatePreload" action can also occur when using the URL API.

Consult the Performance Analytics Server API Reference for an overview of these errors.

7. Performance AL Explorer

Performance AL Explorer is used to manage and configure Performance AL on one or more servers. It can also create, browse and organize items. Performance AL is used by both business users and the system administrator. The user interface adapts to the rights of the user.

The illustration below shows how Performance AL Explorer connects to a Performance AL Server. Performance AL Explorer uses only the available methods of the Web Service of Performance AL to communicate with Performance AL Server. For more information about the Web Service of Performance AL, see the document *Performance Analytics Server API* Reference.

Starting Performance Analytics

You can use Performance Analytics Explorer on another system than the one where Performance AL Server is installed. This way you can perform actions on any Performance AL Server you have access to. You can manage multiple Performance AL Servers with Performance AL Explorer.

Procedure

Do one of the following:

- To start Performance AL Explorer on a remote system, enter the following URL in an internet browser: http://<name>/EVExplorer. Where <name> is the name of the system running Performance AL Explorer.
- To start Performance AL Explorer on the system where Performance AL Server is installed, enter the following URL in your browser: http://localhost/ EVExplorer

Tip: You can also start Performance AL Explorer from the Windows Start menu.

The interface of Performance AL Explorer

The user interface of Performance Analytics Explorer uses the toolbar buttons as described in the table below.

Icon	Purpose
⊜	Change the way the servers and items are listed. This can be in list mode or block mode.
~	Change the size of the toolbar.
6	Go back one item.
8	Log off.

Managing Performance AL Server

There are settings you need to configure in Performance AL Server. You can configure these settings by using Performance AL Explorer.

Changing the environmental properties of Performance AL Server

The environmental properties specify the name and port number that gives access to a Performance AL Server from an external location. Changing the environmental properties can be necessary when a client system cannot resolve the internal Performance AL server name or when the external port for a certain protocol is different than the port that is used internally.

The environment variables apply to each session created on Performance AL Server and are valid for the session. For more information, see "Sessions" .

The order in which the server name and port number are applied for a session is as follows:

- 1. The external name or port number as set in Performance AL Explorer.
- 2. The name or port number as set in the URL. For example: http:// demo.company.com:8080.
- 3. The defaults as set on the system running Performance AL Server.

To change the external name or port number set in Performance AL Explorer do these steps.

- 1. From Performance AL Explorer, right-click a Performance AL Server 🚟 and then click Server Settings > Advanced.
- 2. Change the values of the fields as described in the table below.

Environmental property	Description
External Server Name	The external name of the server as a string. For example "demo.company.com".
External Native/TCP Port	The external port number when using Native/TCP connectivity to connect to a Performance AL Server. The possible values are 0 to 65535.
External HTTP Port	The external port number when using the HTTP protocol to connect to a Performance AL Server. The possible values are 0 to 65535
External HTTPS Port	The external port number when using the HTTPS protocol to connect to a Performance AL Server. The possible values are 0 to 65535.

Changing the properties of the Performance AL repository

To change the properties of the Performance AL Server repository you access the root folder information.

Procedure

- 1. Open Performance AL Server .
- 2. Next to the Performance AL Server name, click Properties. You can change the following properties.

Property	Purpose	
General	The name of the generic root folder and its description	
User-defined Properties	Manage the User-defined Properties.	
Policies	Manage or review the folder policies.	

Changing the server settings for a Performance AL Server

Use Performance AL Explorer to change the properties of a Performance AL Server.

- 1. From Performance AL Explorer, right-click a Performance AL Server and then click Server Settings.
- 2. You can change the following properties.

Property	Description		
Name	The name of the Performance AL Server		
Description	An optional description		
Location	The name of the system on which Performance AL Server is running, or the location of the WebService.asmx file. If the Location field is left empty, then the name specified in the Name field will be used.		
Logon Type	 Specifies how Performance AL Server connects to the provider that is specified in the Providers field. You can choose either: Automatically logon using Windows Integrated Authentication or Display Logon Form: The user will be prompted to enter credentials. 		

Providers	The names of one or more security providers. If you specify multiple provider names, then separate them with a comma. To specify all providers, enter "*". You can configure one or more security providers on a Performance AL Server. When you leave this field empty, the default provider is used. This is the first security provider that is configured. If for the Logon Type the option Windows Integrated Authentication is chosen, the first provider that
	supports Automatically logon using Windows Integrated Authentication is used.

Viewing the version information for a Performance AL Server

Procedure

- 1. Right-click a Performance AL Server and click Manage 🔀.
- 2. The Version Information section 🤨 shows the version of Performance AL Server.

Removing a Performance AL Server

You can remove Performance AL Servers that are listed in Performance AL Explorer.

Note: If you use Performance AL Explorer to remove a Performance AL Server, it is not removed from the system. Only the reference to the Performance AL Server is removed.

Procedure

- 1. Right-click a Performance AL Server 📅 and then click Remove.
- 2. Click Yes.

Managing folders and items

A Performance AL Server contains a repository with items. Items can be of the following types:

• Folder

Used to organize items. A folder can contain child items of all defined item types. You can set item security on folders and their child items.

- View Contains the view of the data stored in the OLAP database. The view connects to a database.
- Canvas A collection of views.
- Database The link between the view and the data source.
- Data source The OLAP database that provides the raw data.

- Image Can be used as a background image in a chart.
- Custom item Allows users to store a custom file. This data can be of any type.
- Shortcut A shortcut link to any item, except folder.

Folders that are added during the installation of Performance AL

During the installation of Performance AL, the following folder items are added to the Performance AL Server repository.

The root folder has the following sub folders:

- \$Private Items contains all of the My Items folders for all users. A user has a My Items folder when the Has Private Folder system permission is granted.
 For more information, see Item security and System security.
- **My Items** contains the items for each user that has the **Has Private Folder** system permission.

For more information, see System permissions and roles.

- System contains the following sub folders:
 - o Data Sources
 - o Databases
 - o Images

The item structure can be adapted to your own situation. Items can be moved, deleted, and created. This initial folder structure is to help you set up your own environment.

These items (with the sub folders of the System folder) are available to the accounts that are built-in administrators. Built-in administrators are accounts that are part of the built-in administrator group on the system that runs Performance AL Server or to the accounts specified as built-in administrator in the EVServer.exe.config file. For more information, see Configure the service and the configuration file.

Managing items

After an item is added you can manage items in the repository.

- 1. Open a Performance AL Server.
- 2. Right-click and choose one of the menu options from the next table.

Icon	Description		
	Opens the data source item		
≅	Opens the database item		

5	Opens the view item or opens all view items				
5	Opens the folder item				
	Opens the image item				
Þ	Opens the custom item				
رای	Opens a canvas item				
Î	Deletes the item				
*	Cuts the item				
G	Copies the item				
B	Shows the properties of an item				
Ê	If an item is copied, the option Paste is added to the options that are shown when you right- click anywhere on the window.				
	If an item is copied, the option Paste Shortcut is added to the options that are shown when you right-click anywhere on the window. Note: You cannot create a shortcut to a folder.				

Creating an item

You can create a folder or item with Performance AL Explorer. The generic folder **Data Sources** can be used to add data source items. The generic folder **Databases** can be used to add database items. The generic folder **My Items** can be used to add view and canvas items. The generic folder **Images** can be used to add image items.

- 1. Open a Performance AL Server 🗮.
- 2. Right-click anywhere on the window or on a folder and click Add Item > Folder 🧰.
- 3. Choose one of the following:
 - Folder
 - Data Source
 - Database
 - View
 - Canvas
 - Image

- Custom Item
- 4. Type a name and a description for the folder or item.
- 5. For an image item:
 - a. Click Add
 - b. Click **Browse** and select an image. Images can be of the type BMP, GIF, JPEG and PNG.
 - c. Click **Upload** to put the image file in the Performance AL repository.

A spark on the image icon indicates that the image item is new and does not contain item data. For more information on the status an item can have, see "ItemStatusType Enumeration" in the *Performance AL Server API Reference*.

6. For all other items, Click Add.

Creating a shortcut item

You can create a shortcut item. **Note:** You cannot create shortcut items for folder items.

Procedure

- 1. Open a Performance AL Server 🧮
- 2. Right-click any item and click Copy.
- 3. Right-click in any folder where you want to add the shortcut and click Paste Shortcut

Results

The shortcut is added to the repository. When you are logged in as a user that has the **Manage** item permission on this shortcut, the shortcut can be recognized by a little arrow in the left bottom corner. Another user, who does not have the **Manage** system permission, does not see this arrow, and has no indication that the item is a shortcut. For this type of user, the shortcut item is shown as an item of the item type it refers to. If a shortcut item is not valid (if it refers to an invalid item, for example an item that no longer exists), the user will not see this shortcut item.

A red shortcut indicator indicates that the shortcut item does not refer to an item of the correct type.

An exclamation mark and a shortcut indicator on the database icon indicates that for example the data source item to which the database refers could not be found at the specified location.

A spark and a shortcut indicator on the database icon indicates that the database item does not contain item data. For more information on the status an item can have, see "ItemStatusType Enumeration" in the Performance AL Server API Reference.

Opening items

The following table provides an overview of what happens when you open an item in Performance AL Explorer.

Item	What happens when you open the item
------	-------------------------------------

Folder	The contents of the folder are shown.	
Data Source	The data source type and the OLAP server of the data source are shown.	
Database	The data source item that connects to the database and the database name on the OLAP server are shown.	
Image	The program associated with the image starts and shows the image.	
View	Performance AL Client starts and shows the view. The view displays the data that is stored in the OLAP database. Depending on the installation and configuration of the security providers, Performance AL Server can authenticate the user. Otherwise you have to enter the credentials in order to log on to the specified database when you open a view.	
Canvas	Performance AL Client starts and shows the canvas and any associated views.	
Custom Item	The custom item is opened by the application associated with the file extension and the MIME Type of the custom item.	
Shortcut	The action that the item refers to starts.	

Procedure

- 1. Open a Performance AL Server 🗮.
- 2. Click an item.

Specifying a data source item

After you have created a data source item you can specify the details of the data source item.

Data source items refer to the OLAP database server. The OLAP server name depends on the type of OLAP server. For TM1 the name has a specific syntax. See <u>Configuring data</u> sources.

- 1. Open the Data Source item.
- 2. From the Data Source Type menu, choose the data source type.
- 3. In the **OLAP Server** field, specify the name of the OLAP server.
- 4. In the User Name field, enter the OLAP administrator user name.
- 5. In the **Password** and **Confirm Password** fields, enter the OLAP administrator password.
- 6. Set the data source specific items. The database settings available depend on the chosen Data Source type. For more information, see <u>Configuring data sources</u>.

- 7. Click **Test Connection** if you want to test the connection details that you have specified.
- 8. Click **Update** to save the data source settings.

Results

A spark on the data source icon indicates that the data source item is new and does not contain item data. For more information on the status an item can have, see "ItemStatusType Enumeration" in the Performance AL Server API Reference.

Specifying a database item

The database item refers to a specific database on an OLAP database server. This OLAP server is specified in the data source item to which the database item refers.

After you have created a database item you can specify the details of the database item. A database item is also created when a data source item is configured.

Procedure

- 1. Open the Database item.
- 2. From the Data Source Type menu, choose the data source type.
- 3. In the **Data Source** field, specify the data source by either typing the name or selecting the name from the menu.
- 4. In the **Database Name** field, specify the database name or the cube name by either typing the name or selecting the name from the menu. If you type the name, use the following format: <data source name>\<database name>.
- 5. Set the database specific items. The database settings available depend on the chosen Data Source type.
- 6. Click **Update** to save the database settings.

Results

An exclamation mark on the database icon \Im indicates a problem. The data source item to which the database item refers could not be found at the specified location.

A spark on the database icon indicates that the database item is new and does not contain item data. For more information on the status an item can have, see "ItemStatusType Enumeration" in the Performance AL Server API Reference.

Properties of a Database item

- Name
 - Specifies the display name of the database within the cube selection dialog, when creating a new view. Also the reference of the database within a view or view template is defined by this name.
- Description

• A text area to add a descriptive text for the database.

• Update all views using this database

 \circ If the name of the database is changed and if there are already one or more views

defined which use this database, the name of the database will also be updated within the views / view templates (see **Name** property), when this checkbox is active. If the checkbox is not checked, the database name within the views will not be updated and the view will refer to the old name of the database.

Changing the properties of an item

You can change the properties of an item.

Procedure

- 1. Open a Performance AL Server 🗮 and go to the item to be changed.
- 2. Right-click the item and click **Properties**. You can change the following properties:

Property	Purpose	
General	The name of the item and its description	
User-defined Properties	Add or change the User-defined Properties.	
Policies	Manage or review the folder policies.	

Creating user-defined properties

Each item in the Performance AL Server catalog can have user-defined and system properties associated with it.

A property is a user-defined or system attribute with a Name, a Data Type and a Value. The number of properties that an item can have is unlimited.

The Name is a unique identifier for the property. The Value is a simple-type that can contain textual, numerical or date-time information.

Procedure

- 1. Open a Performance AL Server 🚟.
- 2. Right-click an item and click **Properties** > **User-defined Properties**.
- 3. Click New.
- 4. Enter the Name, the Data Type, and the Value for the user defined property.
- 5. Click Add.

The following table shows the data types that are supported for user-defined properties:

Data Type	Possible value	
boolean	true/false	
byte	0255	

9			
9			
-32,768 32,767			
-2,147,483,648 2,147,483,647			
54,775,807			

Changing the MIME type of a custom item

You can change the MIME type of a custom item.

The custom item will be opened by the application that is associated with the file extension and the MIME Type of the custom item.

Procedure

- 1. Open a Performance AL Server 🗮.
- 2. Right-click a custom item 盲 and click **Open**.
- 3. Use the **MIME Type** field to specify the MIME type.
- 4. Click Update.

Connecting a view item to a database item

After you have created a view item you can open the view in Performance AL Client.

Depending on the installation and configuration of the security providers, Performance AL Server can authenticate the user. Otherwise you have to enter the credentials in order to log on to the specified database when you open a view.

For more information, see "Installing Performance AL Client".

Procedure

- If Performance AL Client is not installed, you will be prompted to install it. Once Performance AL Client is installed, the **Connection Information** dialog is displayed.
- 2. From the Database menu select the **database** you have configured within Performance AL Server.
- 3. Click OK.

Results

The created view is shown. The view displays the data that is stored in the OLAP database.

An exclamation mark on the view icon kindicates a problem. The data source item to which the database item refers could not be found at the specified location.

A spark on the view icon indicates that the view item is new and does not contain item data. For more information on the status an item can have, see "ItemStatusType Enumeration" in the Performance AL Server API Reference.

Associating a view item with a canvas

After you have created a canvas item you can insert a view item to the canvas as a panel.

Procedure

- 1. Click the canvas item you have created in Performance AL Explorer.
- 2. Click Views.
- 3. Select the view to include in the canvas.
- 4. Click Open.

Results

The view shows in the canvas as a panel. The view displays the data that is stored in the OLAP database. More than one view can be associated with a single canvas.

View item

This initial situation is added to help you get started setting up your own environment. A user has a **My Items** folder when a user has the System Permission **Has Private Folder**.

Views can be added in any folder or canvas to organize your own environment.

A view item contains the view definition of the data stored in the OLAP database to which the view refers. A view connects to a database item and that database item connects to a data source.

Shortcut item

A shortcut item inherits the type of the item it refers to. A shortcut can refer to all item types except the item type folder.

Property inheritance

For a shortcut item, system- and user-defined properties are inherited from the referenced item. If an item has a property "New", then shortcuts to this item also have access to the same property "New". When retrieving the list of properties from the shortcut item, the property "New" will be included in the list.

It is not possible to change the value of an inherited property on the shortcut. The value can only be changed on the original item.

If the shortcut itself has a property "New", the value of the property "New" belonging to the shortcut will be retrieved instead of the value of property "New" of the item the shortcut refers to.

In case of a chain of references (shortcuts referencing to shortcuts, referencing to an item) this inheritance continues. This means when you retrieve the properties of the last shortcut Item in the chain, all properties of all (shortcut) items are retrieved.

Database wizard

The Database Wizard enables you to register databases for a data source.

Using the Database Wizard

Procedure

- 1. Right-click a valid data source 📰 and click **Database Wizard**.
- 2. Enter the OLAP credentials if they are required by the data source.
- 3. Click Login. An overview of the databases that can be registered is shown.
- 4. In the **Destination Folder** field, specify the folder where the databases have to be created. By default the **Database Post Search** Path is used. If there is no destination folder specified, the database Items will be created in the current folder.
- 5. In the **Database Name Prefix** field, specify a prefix for the database name. This optional prefix will be added to the name of the created database item.
- 6. Click **Register**.

Note: The registration can take some time.

Results

When the databases have been registered, a status overview of the created databases is shown. Click on a link of a registered database to change the settings for preloading or process distribution. The databases are added to the Performance AL Server repository.

You can register the same databases in a different destination folder by specifying another folder.

Process distribution

Process distribution allows you to load cubes into separate sub processes that run parallel to the main process. Performance AL maximizes the memory available for the cubes to be loaded. To extend the process distribution, you can also configure master and slave servers.

When you have enabled process distribution, you can:

- configure process distribution for data source and database items.
- add slave servers to extend process distribution.
- use the isolation level to group specific cubes and load them in separate processes.

Using the combinations of master and slave servers and the isolation levels, you can configure process distribution to exactly fit your needs.

For more information on the installation of Performance AL Server and slave servers, see <u>Selecting the install components</u>.

Note: Process distribution settings are only available if you are logged in as administrator.

The configuration of process distribution consists of the following parts:

- Enabling process distribution on the Performance AL Server.
- Specifying a port range on either the Performance AL master server or the slave server.
- Adding slave servers.
- Setting process distribution on a data source item.
- Setting process distribution on a database item.

How it works


Modern CPUs provide multiple CPU cores, which can work in parallel. Using more than one CPU core increases the performance and uses the CPU more efficiently.

To solve these problems the Performance Analytics Server supports process distribution, where multiple Sub-Processes are being created automatically to distribute the application load and memory usage.

These processes can either be created on the main Performance AL Server machine, or on <u>Performance AL Server slave installations</u> which can be set up on other physical or virtual machines.


Note: The communication with the Performance Analytics Clients is always being routed over the Performance AL Server Master process.

Default behavior




The default behavior of the Performance AL server doesn't use any distribution. All cubes, outlines and data are stored in the memory of the EVServer.exe master process and all client requests are handled by the master process.

Group Cubes from this Data Source




If you choose **Group Cubes from this Data Source**, an EVServer.exe Sub-Process will be created for each configured Data Source.

Group Cubes by Application




If you choose **Group Cubes by Application**, an EVServer.exe Sub-Process will be created for each Application in Essbase; respectively Catalogs in TM1.

Each Cube separately



If you choose **Each Cube separately**, a new EVServer.exe Sub-Process will be created for each Database.

Inheritance



Process distribution can be configured either on Data Sources or on Databases. By default, Databases inherit from their Data Source and apply their settings. However, in some special cases, it can be necessary to remove this inheritance and define a distribution for a specific Database.


In this example, Datasource 1 is configured to create one Sub-Process for each Application. However, Database 3 should be separated in an extra process as well.

Therefore, the inheritance for Database 3 was disabled and its isolation level set to **This Cube Individually**.

Using Slave Servers

It's possible to distribute the server load and memory usage across multiple physical or virtual machines. Therefore, the Performance AL Server has to be installed in slave mode, which can be selected during the installation procedure.

First, select the **Custom** setup type ...



Setup Type

Choose the setup type that best suits your needs.


○ <u>E</u> xpress					
1 1 1	Common program features will be installed. Please note: By default it will validate the local SQL Server when you click Next.				
Custom					
1 ⁴		Choose which program features you want to install and where to install them. Recommended for advanced users.			
InstallShield					
ino canon nerca		< <u>B</u> ack	<u>N</u> ext >	Cancel	
and then th	e slave mode .				
🖟 Performanc	e Analytics (64-bit)			×	
Application S	ettings				
Select applic	ation settings.			\sim	
Install Perfor	mance Analytics (64-bi	it) for			
Only for	me (cubusadmin)				
Anyone v	who uses this computer (all u	users)			

After the installation, they have to be registered on the master server, to make them available for distribution use. See the chapter <u>Adding a slave server to Performance AL</u> <u>Server</u> for further setup information.

 \times

Note: There is no (additional) license file required to run an Performance AL Server in slave mode.

Note: An Performance Analytics Server running in slave mode cannot be accessed by a client directly.



A process distribution using a slave server could look like this.

Enabling process distribution on Performance AL Server

To enable process distribution do the following steps.

- 1. Right-click a Performance AL Server and click Manage > Settings > Process Distribution.
- 2. In the Process Distribution section, select Process Distribution and click Update.
- 3. Note: If no slave servers are configured, a port range on the master server must be

specified to allow the processes to communicate with the Performance AL Server master process.

- 4. In the **Port Range** field, enter port numbers for example [1;3;5] or a port range, for example [1-12]. Valid Port Numbers are: 1 65535.
- 5. Click Update.

Note: If you specify too few ports, the loading of more than one cube may fail.

Configuring process distribution for a data source item

If you have enabled process distribution on the Performance AL Server, you must configure process distribution on a data source item. Do the following steps to select the server and specify the isolation level.

Procedure

- 1. Open a Performance AL Server 🗮.
- 2. Open a data source item 📰
- 3. In the Process Distribution select from the Server list to load the cubes to either the master or the slave server.
- 4. In the Isolation Level section, select the isolation level for this data source:

Data Type	Possible value	
None	All cubes from this Data Source are loaded by the main process on the specified Server.	
Group cubes from this Data Source	One sub process is started to load all cubes from this Data Source on the specified Server.	
Group cubes by Catalog (see note)	One sub process per Catalog is started to load cubes from this Data Source on the specified Server.	
Each Cube separately	A separate sub process is started for each cube from this Data Source on the specified Server.	

Note: Group cubes by Catalog will be named **Group cubes by Server** when you use TM1 as a data source and **Group cubes by Application** when you use Essbase as a data source.

Configuring process distribution on a database item

After process distribution is enabled on the Performance AL Server, you must configure process distribution for a database item. Do the following steps to set the server location, isolation level.

- 1. Open a Performance AL Server 🗮.
- 2. Open a database item 🚟.
- 3. In the **Inherent From Parent Data Source** section, select if you want the process distribution settings of the database item to be inherited from the data source item it connects to. By default the settings are inherited.
- 4. In the **Process Distribution E** section, select from the **Server** menu whether you want the cubes to be loaded on the master or the slave server.
- 5. In the Isolation Level section, select the isolation level for this database:

Isolation Level	Explanation	
None	This cube is loaded by the main process on the specified server.	
Group with cubes from this Data Source	One sub process is started to load all cubes, that use the same data source and have the same isolation level, on the specified server.	
Group with cubes from the same Catalog (see note)	One sub process per catalog is started to load all cubes, that use the same data source and have the same isolation level, on the specified server.	
This cube individually	A separate sub process is started for this cube on the specified server.	

Note: Group with cubes from the same Catalog will be named Group with cubes from the same Server when you use TM1 as a data source and Group with cubes from the same Application when you use Essbase as a data source.

Adding a slave server to Performance AL Server

If one or more slave servers are available, you can specify the slave server to be used for process distribution. To add a slave server do the following steps.

Procedure

- 1. Right-click a **Performance AL Server > Manage > Settings > Process Distribution**.
- 2. In the Slave Servers section, click New.
- 3. In the Slave Server Information section, specify the following:
 - In the **Name** field, type a unique name.
 - In the **Location** field, specify a valid location for the slave server. You can extend the location with :ServerPortNumber. You must specify the **ServerPortNumber** when it is set to a value other than 7112. The ServerPortNumber is set in the EVServer.exe.config file.

For more information, see Editing the configuration file.

• In the **Port Range** field, enter port numbers or port ranges. Port numbers are specified as 1;3;5;7. Port ranges are specified as 1-3;5-12. Valid Port Numbers are:

1 - 65535.

Note: If you specify too few ports, the loading of more than one cube may fail.

4. Click Add.

Results

The slave server will be added to the list of configured slave servers.

This icon 🚟 indicates that the slave server is running.

This icon 🚟 indicates one of the following problems:

- The version of the slave server is not the same version as the master server.
- The location of the slave server is not valid.
- Communication with the slave server is not possible.

Accounts

An account can be made for a single user, for a group of users, or for a user role.

System Roles (with their **Permissions**) are attached to an account. This is called a system policy.

Item Roles (with their **Permissions**) are attached to an account and to an item. This is called an item policy.

After installation of Performance AL, only the account **Everyone** appears. The created account **Everyone** represents all users that can be validated by the installed **Security Provider**.

Accounts are added when setting **Item Policies** or **System Policies**. Accounts cannot be added individually.

Performance AL Server uses the specified accounts through one or more **Security Providers**. Performance AL Server does not have accounts of its own.

When a system or item policy is set for a specified account, this account appears on the **Accounts** list.

Viewing Accounts

Procedure

1. Right-click a Performance AL Server and click Manage > Security 💙 > Accounts.

2. In the 🏞 Accounts section you can view the available accounts.

Security

Performance AL Server security can be divided in two groups: system security and item security.


This means it is possible to set permissions: item permissions and system permissions. Item permissions apply to items in the repository.

System permissions apply to the system: Performance AL Server.

Note: A built-in administrator can always manage the security on a Performance AL Server by using Performance AL Explorer. This is to prevent administrators from creating a situation where they are locked out or cannot access Performance AL Server as a result of changing the System Security settings.


Item security

An item role (with its item permissions) is attached to an account and to an item. This is called an item policy.



System security

A system role (with its system permissions) is attached to an account. This is called a system policy.



To be able to organize and structure permissions, they are attached to roles. A role contains one or more permissions.

The item permissions and system permissions are a fixed set of permissions. After installation, several item roles and system roles are created, to help you get started with Performance AL Server security. You can modify, delete, and to create new roles.

After the installation of Performance AL Server, one system policy is added. For the root item and the items **\$Private Items** and **System** one item policy is added. These policies can be modified, or deleted and you can create your own policies.

Sessions

To apply system and item security, Performance AL Server must be able to authenticate a user. This is done via a session.

A Performance AL Server session is created when a user logs on to Performance AL Server. After the user is successfully authenticated, the Performance AL Server retrieves the appropriate permissions, for example to use views or to connect to an OLAP database. During the creation of a session, credentials are passed to the Performance AL Server. Performance AL Server will pass these credentials to a configured security provider. This security provider validates whether the user is allowed to log on to the system with the specified credentials. Once a session is created, this session provides the access to Performance AL Server.

A session can be created by a portal (for example Performance AL Explorer) by using the CreateSession method, or by Performance AL Client creating an instant session.

For more information about the "CreateSession" method, see the Performance AL Server API Reference.

For information about Security Providers, see "Configuring the security provider".

Item permissions and roles

You can set permissions on an item. A named combination of these permissions is called an Item Role.

Available permissions

The next table shows the available permissions.

Permission	Description	
List	List the items in the parent folder.	
Read	Read the contents of an item.	
Modify	Modify an item.	
Manage	Manage an item. Items can be created, deleted, and renamed.	
Full Control	With Full Control permission, you can change the security on an Item.	

For comments, the following permissions are available.

Permission	Description	
Manage Comments	Manage the comments of all users in the database.	
Write Comments	Read all comments, write and modify your own comments in the database.	
Read Comments	Read all comments in the database.	

Permissions implications

Item permissions are dependent on each other. Setting a permission may imply other permission settings. The next table shows an overview of these implications.

- x = set permission
- o = implied permission

	Full Control	Manage	Modify	Read	List
Full Control	х				
Manage	0	х			
Modify	0	0	х		
Read	0	0	0	х	0
List	о			0	х

For comments, the item permissions partially depend on each other as well. The following table shows how the permissions are implied.

	Manage Comments	Write Comments	Read Comments
Manage Comments	х		
Write Comments	0	х	
Read Comments	0	0	х

Setting permissions for an item

Procedure

- 1. Right-click a Performance AL Server and click **Manage** > **Security** > **Item Roles**. The available predefined Item Roles are shown.
- 2. Click an item role and set the permissions.
- 3. Click Update.

Comments

Comment item permissions take only effect when they are set on a **Database** item. Then, the policy applies for all views, which use this particular database item as its data source.

Item roles

An item role contains item permissions. After installation, the following predefined Item Roles are available.

Item role	Description
Administrator	Has these permissions:
	Full
	Control
	Manage
	Modify
	Read
	List
	Manage Comments
	Write Comments
	Read Comments
Author	Has these permissions:
	Manage
	Modify
	Read
	List
	Write Comments
	Read Comments
Consumer	Has Read permissions.
Reviewer	Has Read and List permissions.

Adding an item role

Procedure

- 1. Right-click a Performance AL Server and click **Manage** > **Security** > **Item Roles**. The available predefined **Item Roles** are shown.
- 2. Right-click and click New Item Role.
- 3. Specify the following for the item role:
 - A Name
 - A Description
 - The Item Permissions
- 4. Click Add.

Opening an item role

When you open an item role you can modify the item role and set its permissions.

- 1. Right-click a Performance AL Server and click **Manage** > **Security** > **Item Roles**. The available **Item Roles** are shown.
- 2. Right-click an item role and click **Open**.

Item Policies

After installation of Performance AL, an item policy is added for the root item. This policy gives the account **<Everyone>** the item role **Reviewer**. This means all users, that are allowed to log on to Performance AL Server, can read and list the items in the repository.

For the items **\$Private Items** and **System** an item policy is added that gives the account **<Everyone>** the item role **Consumer**. This means all users, that are allowed to log on to Performance AL Server, can read the items. This is necessary in order to let users access databases or data sources that are specified in the System folder.

An item role with its **Item Permissions** is attached to an account and to an item. This is called an item policy. You can set an item policy on an item.

Adding Item Policies

Procedure

- 1. Open a Performance AL Server 🗮
- 2. Right-click an item and click **Properties > Policies > New**.
- 3. Specify the following:
 - The Account Type
 - The Account Name
 - One or more Item Roles
- 4. Click Add.

System permissions and roles

You can set permissions for a system. A named combination of these permissions is called a System Role.

Available permissions

The next table shows the available permissions.

Permission	Description
Logon	Logon to Performance Analytics Server. If this permission is not set for a system role, then the user cannot create a session and is refused to logon to Performance AL Server.
Manage Roles	Create, view, modify and delete roles.
Manage System Policies	Create, view, modify and delete System Policies.
Manage Sessions	View and invalidate sessions.
Manage Item Policies	Create, view, modify and delete Item Policies.
Manage Folders	Create, modify and delete folders.
Manage Views/Canvases	Create, modify and delete views and canvases.

Manage Databases	Create, modify and delete databases.	
Manage Data Sources	Create, modify and delete data sources.	
Manage Images	Create, modify and delete images.	
Manage Custom Items	Create, modify and delete custom items.	
Manage Logging	View logging.	
Manage Subscriptions	Create, modify and delete subscriptions.	
Has Private Folder	Allowed to have a Private Folder.	
	Note: If this permission is not set for a role, then the ev client doesn't show the following folders in the backstage area for this user:	
	Recent Views	
	• My Views	
	My Templates	
Use Comments	Use any comment related functionality.	
Use Subscriptions	Determines if the subscription functionality is available to the user.	

The following system permissions apply for the corresponding item type:

- Manage Folders
- Manage Views/Canvases
- Manage Databases
- Manage Data Sources
- Manage Images
- Manage Custom Items.

The user that has these permissions, can create, modify and delete the item types at system level. For individual items, you have to set the item permissions.

For example: in order to set item policies on an item, a user needs to have the system permission **Manage Item Policies** and the Item Permission **Full Control** on the item for which to set the policy.

Setting system permissions

- 1. Right-click a Performance AL Server and click **Manage** > **Security** > **System Roles**. The available predefined **System Roles** are shown.
- 2. Click a system role and set the permissions.
- 3. Click Update.

System roles

A system role contains system permissions. After installation, the following predefined System Roles are available.

Permission	Description	
System Administrator	Has all system permissions, except the Has Private Folder system permission.	
Logon	Has Logon Permission, has a private folder and can use comments.	

Adding System Roles

Procedure

- 1. Right-click a Performance AL Server and click **Manage** > **Security** > **System Roles**. The available predefined **System Roles** are shown.
- 2. Right-click and click New System Role.
- 3. Specify the following for the system role:
 - A Name
 - A Description
 - The System Permissions
- 4. Click Add.

Editing system roles

When you open a system role you can modify the system role and set its permissions.

Procedure

- 1. Right-click a Performance AL Server and click **Manage** > **Security** > **System Roles**. The available **System Roles** are shown.
- 2. Right-click a system role > **Open**.

System Policies

System Roles (with their system **Permissions**) can be attached to an account. These are called System Policies.

After the installation of Performance Analytics, two System Policies are added: Logon User and Evaluation User. For information on the Evaluation User, see Evaluation_roles and policies.

Logon User

A system policy is added that gives the all users the system role Logon User.

This means that all users in the account **Everyone** can logon to Performance AL Server, which is needed in order to create a session.

Adding System Policies

Procedure

- 1. Right-click a Performance AL Server and click Manage > Security > System Policies.
- 2. In the Policies section, click New.
- 3. Specify the following:
 - The Account Type
 - The Account Name
 - One or more System Roles
- 4. Click Add.

Evaluation roles and policies

Some users who evaluate Performance AL do not have local administrator permissions. If a user does not have the local administrator permissions, the restricted permissions that are defined for the default Everyone Account will be used.

For evaluation purposes, evaluation roles and policies are available.

The **Evaluation User** system role and item role offer administrator permissions to change the Performance AL repository. After evaluation and defining the desired repository security, remove the **Evaluation User** roles. They should not be available in a production environment.

Note: The Evaluation User roles are created only after initialization of the Performance AL repository. The Performance AL repository is initialized when Performance AL Server is started for the first time.

Initial situation

To set the system so that all users have access during evaluation:

- The role Evaluation User is added to System Roles and item roles.
- The policy Evaluation User is added to System Policies and item policies.

Evaluation User system roles

The properties for a user can be changed according to the role that is set.

For the **Evaluation User** system role the following **Permissions** are set initially:

- Logon
- Manage Roles
- Manage System Policies
- Manage Sessions
- Manage Item Policies
- Manage Folders
- Manage Views/Canvases

- Manage Databases
- Manage Data Sources
- Manage Images
- Manage Custom Items
- Manage Logging
- Has Private Folders

Changing properties of the Evaluation User system role

Procedure

- 1. Right-click a Performance AL Server and click **Manage** > **Security** > **System Roles**.
- 2. Click the Evaluation User system role.
- 3. Change the following properties of the system role:
 - Name
 - Description
 - Permissions
- 4. Click Update.

Evaluation User item roles

For the **Evaluation User** item role the following **Permissions** are set initially:

- List
- Read
- Modify
- Manage
- Full Control

Changing properties of the Evaluation User item role

Procedure

- 1. Right-click a Performance AL Server and click **Manage** > **Security** > **Item Roles**.
- 2. Click the **Evaluation User** item role.
- 3. Change the following properties of the item role:
 - Name
 - Description
 - Permissions
- 4. Click Update.

Viewing the system policy Evaluation User

The policy **Evaluation User** has been added to **System Policies**. You can add this system policy to an item.

- 1. Open a Performance AL Server.
- 2. Right-click an item and click **Properties**.

Results

In the Policies section, the Account Evaluation User is shown.

Active Sessions

If you have the system permission to manage sessions then you can view and terminate active sessions of Performance AL on a Performance AL Server.

Viewing Active Sessions

To view active sessions and the last used session of Performance AL on a Performance AL Server.

Procedure

- Right-click a Performance AL Server and click Manage > Activity & Log > Active Sessions. In the Active Sessions table, the active sessions of Performance AL are listed with the following details:
 - User
 - Host address
 - Creation time
 - Last used. Last used is updated when a user performs an action on Performance AL Server.
 - Description
- 2. You can sort the table of **Active Sessions** by clicking on a detail you want to sort on.

Terminating Active Sessions

You cannot terminate your own session within Performance AL Explorer. You can only terminate other sessions.

Procedure

- 1. Right-click a Performance AL Server and click Manage > Activity & Log > Active Sessions.
- 2. In the **Active Sessions** table, select the active session you want to terminate and click **Terminate**.
- 3. Click Yes.

Server Log

The Performance AL Server log contains the following entries:

Log entry	Explanation	
Category	Shows the category of the log. For example General, or Security.	

Component	Shows the component that logged the log entry. For example the Security Provider or the Catalog Provider.
Level	Shows the log level.
Message	Contains the actual log message.
Process ID	Contains the ID of the Performance AL Server Process.
Thread ID	Contains the ID of the thread in the Process.
Session ID	Contains the ID of the Session.
Date-Time	Contains the date and time.

Showing and browsing the Log entries

Procedure

- 1. Right-click a Performance AL Server and click **Manage** > **Activity & Log** > **Log entries**.
- 2. If you have process distribution enabled with master and slave servers, you can specify the server for which you want to view the log entries.
- 3. You can browse the **Log entries** by clicking the following buttons:
 - First
 - Prev
 - Next
 - Last

Setting a filter on the Log entries

You can set a filter if you do not want to see all Log entries.

- 1. Right-click a Performance AL Server and click **Manage** > **Activity & Log** > **Log entries**.
- 2. Click **Filter**. The following table lists the available filter options.

Filter	Explanation
Thread ID	Specify the Thread ID to view the log entries for, or "*" for all.
Session ID	Specify the Session ID to view the log entries for, or "*" for all.
Process ID	Specify the Process ID to view the log entries for, or "*" for all.
Level	Severe The less detailed level.

	Only severe errors are logged. These are errors that may cause a situation where Performance AL Server is unusable.
	Error All errors are logged. These are situations where Performance AL Server can run but a provider cannot be started.
	Warning Warnings are logged, for example when a provider is not correctly configured.
	Info Information is logged, for example the start and stop of Performance Analytics.
	Verbose More detailed information is logged, for example the loading of the catalog items.
	Trace The same information as in Verbose is logged, only more detailed.
	Debug The most detailed level. All possible information is logged.
	Note: The levels Severe , Error and Warnings give you information about (possible) errors that occur in Performance AL Server.
	The levels Warning , Info and Verbose contain information about the status or activities of Performance AL Server. The levels Trace and Debug are recommended in case
	you experience problems with Performance AL Server and you want to see all detailed information.
Sort order	Ascending or Descending
Components	For more information, see <i>"Components used by Performance Analytics"</i> . The possible Components are: Server

	The Log providers are: LogProviders.Event LogProviders.File LogProviders.Mail LogProviders.Oracle LogProviders.SQLServer LogProviders.XML
Components	The Catalog providers are: CatalogProviders.Oracle CatalogProviders.SQLServer
Components	The Categories are: Configuration General InternalError ParameterValidation Security ServerProtocol Session UnsupportedType WorkerProcessProtocol
Begin Date-Time	The start date for the filter.
End Date-Time	The end date for the filter.

Activity Log

The activity log is a easy way to see which items are used in Performance Analytics. It can be found by right-clicking a Performance AL Server and choosing **Manage** > **Activity & Log** > **Activity log**.

The activity log contains the following columns:

Property	Explanation
Path	The path under which the item can be found in folder hierarchy.
Туре	The type of the item (i.e. View)
Accessed	Then time stamp when the item was last opened by a user
User	The user that last accessed the Item
Created	The time stamp when the item was created

Modified	The time stamp when the item was last modified and saved
Description	The description of the item if there was any set
Count	The number of times the item was accessed

Search paths

Performance AL Server has a search logic for resolving items that are referenced. Some item types link to another item. For example a view item can link to a database or an image, or a shortcut can link to any other item type.

The search order to find these linked items is:

- 1. The search Pre paths.
- 2. Search in the current folder and its ancestor folders from the specified item to the root folder.
- 3. The search **Post paths**.

For the item types data source, database and image, the search **Pre paths** and the search **Post paths** can be set. By default, the search **Pre paths** is empty and the search **Post paths** is the first sub folder in the **System** folder with the item type name. For example for item type images this is **/System/Images**.

Setting the search paths

Procedure

- 1. Right-click a Performance AL Server and click **Manage** > **Settings** > **Search Paths**.
- 2. For the item types **Data Source**, **Database** and **Image** you can set the **search paths** in the **Pre path** and **Post path** fields. You can define multiple search paths on new lines. Press the Enter key to create a new line.
- 3. Click Update.

Monitoring

You can monitor the present users and the number of users who have connected to a Performance AL Server over a period of time using Monitoring.

Note: Only users of Performance AL Client are registered. Users of Performance AL Explorer and Performance AL Desktop Explorer are not registered.

Viewing named users

- 1. Right-click a Performance AL Server and click Manage > Monitoring .
- 2. Select Named Users.

- 3. The **Named Users** table shows the individual users of Performance AL Client that have connected to the system at any time. For each user the following data is shown:
 - User Name The name of the user
 - Security Namespace The security provider that is used by the user.
 - First Connected The date on which the user first connected.
 - Last Connected The date on which the user last connected.

Viewing concurrent users

Procedure

- 1. Right-click a Performance AL Server and click Manage > Monitoring .
- 2. Select Concurrency counters
- 3. The **Concurrency counters** table shows the maximum number of simultaneous connections to Performance AL Server per day. The following data is shown:
 - Date

The date for the concurrency counters

• Timestamp

The time of the day when the maximum of concurrent users was attained for the first time. Note that this value is only populated since the 8.7.0 release and is set to 00:00:00 for all prior entries.

Concurrent Users

Represents the maximum number of users that access the system simultaneously on this date.

Maximum concurrent users

The maximum number of concurrent users that are registered on any day.

Note: If no user does log on or off on a particular day, that day will not be shown in the list of concurrent users.

Integration

Portal Integration

It is possible to integrate Performance AL in custom websites and company portals. If the portal has a login mechanism it is possible to automatically sign on in Performance AL. The following steps need to be carried out in order to do this.

Portal Web Page

The portal integration web page should be used in order to integrate Performance AL in portals. The portal integration web page can be found in the Performance AL Explorer

web application. For example:

http://<ServerName>/EVExplorer/PortalIntegration.aspx

This web page should be called or embedded in the portal you wish to integrate into, and the appropriate parameters should be specified.

The portal integration web site accepts the following parameters:

- UserName The user connecting to the Performance AL server.
- UserToken The authentication token that is used for verifying user access.
- Item The full path to the view or canvas that should be displayed.
- ServerName The server name to be used for authentication. (Optional).
- Authentication The authentication provider to be used for verifying the user. (Optional).
- ViewType The view type to be displayed. (Optional).

```
Static- Static Report, no user interaction.OffgridOnly- OffgridOnly Report, allowing the user to select off-grid items.UIActive- UiActive Report, allowing the user to add and/or removecolumns/rows.- Adhoc The entire Performance AL functionality can be used forthe creation, development, and modification of workbooks. This does not includesave.- Full Performance AL functionality including save.
```

• **Pov** – The point of view to be displayed. The member or the alias displayed in the Performance AL view must be passed; it is not possible to pass an alias from an alias table that is not in use. (Optional).

Pov=<Dimension1>=<MemberOrAlias>|<Dimension2>=<MemberOrAlias>

```
http://<ServerName>/EVExplorer/PortalIntegration.aspx?UserName=MyUser
&UserToken=MyUserToken&Item=/Views/MyView&ServerName=Server&Authentication=Essb
&ViewType=Adhoc&Pov=Dimension1=MemberName|Dimension2=MemberName
```

User Token

The user token must be retrieved from the repository in order for a successful login. This user token must then be passed to the portal integration web page with the corresponding user name. After a successful login, this user token will be changed and will need to be read again for the next time that the page is loaded.

An example SQL query can be seen below, showing how the user token can be read from the repository.

```
SELECT p.Value FROM CATALOGITEM c, PROPERTY p
WHERE c.ID = p.ITEMID
AND c.TYPE = 9
AND p.Name = '_UserToken'
```

Connection User

The portal integration web site uses a connection user in order to connect to the data source. The passed user name is given a prefix, in this case "CubusEV_". This means that the resulting user name that is used for creating an Performance AL session is "CubusEV_<UserName>". This user will also be used for the data source credentials.

This means, for example, if you are using Essbase as an authentication provider, the user "CubusEV_<UserName>" will need to be configured, this can be done with the UserManagement console.

User Management

Users in Performance AL can be managed using the UserManagement console application. Please refer to the documentation in UserManagement

Limitations

When using Essbase as security provider, only the Essbase native directory is supported.

CXO Software Integration

It is possible to integrate into CXO Software. The minimal required CXO version is 6.3.2.

There are two ways to integrate Performance AL in CXO Software.

- 1. Define a link to an existing report.
 - Item The path to the view that should be opened.
 - UseAliasTableForSetPov This parameter defines which alias table in Performance AL will be used to set the members, CXO typically passes the member name. This parameter will be used to set the point of view and then the stored alias table will be used to display the alias names in Performance AL.
 - **POV** The point of view to be set in the offgrid. This is to be defined in the following way.

pov=Dimension1:Member1|Dimension2:Member2

CXO has a mechanism to dynamically read the current selections for dimensions. For example, "YER":"[YER].name". Please see the CXO documentation for further explanation of this functionality.

An example can be seen below.

```
http://localhost/EVServer/?Toolbar=True&Tabbar=True&Item=/CXO/CXO
PL&pov="YER":"[YER].name"|"PER":"[PER].name"&UseAliasTableForSetPov=Name
```

2. Click on the start Adhoc analysis button

The start Adhoc Analysis button in CXO opens Performance AL and creates a table based on the current CXO point of view. This allows users to perform an adhoc analysis based on a CXO report. A link to Performance AL has to be defined in CXO Software in order to use this functionality. See the CXO documentation in order to configure this functionality.

Comments

When comments shall be used, ensure that the following configuration has been applied correctly.

Database and Data Source settings

The database must be configured to allow comments. There are two options available to achieve that.

- 1. Navigate to the Data Source item which is shall be allowed
- 2. Select an Allow Comments option
 - \circ Never

Disables comments for all **Database** items which use this Data Source, regardless of their **Allow Comments** checkbox state.

o Always

Enables comments for all **Database** items which use this Data Source, regardless of their **Allow Comments** checkbox state.

o Database Specific

Allows to configure the **Allow Comments** setting per **Database** item individually. The checkbox of the **Database** item applies now.

System roles

The logged in user has to be allowed to Use Comments in general.

- 1. Right click on a Performance AL server and select Manage
- 2. Click on System Roles
- 3. Select the role, which shall be allowed to use comments
- 4. Ensure, the **Use Comments** checkbox is checked
- 5. Click OK

System policies

Also ensure, that the user which shall use comments, owns a System Role which is allowed respectively.

- 1. Right click on a Performance AL server and select Manage
- 2. Click on System Policies
- 3. Ensure the users, which shall be allowed to use comments, have the correct **System Roles** assigned

Item roles

Define, which item role has which comment permission. An user can be allowed to read,

write or manage comments. For a more detailed description see available permissions.

- 1. Right click on a Performance AL server and select Manage
- 2. Click on Item Roles
- 3. Select the role, which shall be configured for certain comment permissions
- 4. Check or uncheck the corresponding checkboxes depending on the required user permissions

Item policies

The detailed user permissions for Read, Write and Manage Comments have to be set for each Database item individually.

- 1. Navigate to the **Database** item for which the user permissions shall be configured
- 2. Click on Properties
- 3. Update policy settings for this item by adding or removing user and role combinations correspondingly

Desktop Application

This chapter describes how to create a deployment package for the Desktop Application.

During the first start of the server after the software installation the Desktop App deployment package is created automatically.

It may be required to create additional packages using the Performance AL Explorer in the following scenarios:

- deploy different versions for different environments (e.g. test and production) to the same client machine
- deploy a hotfix

The source files for creating the package are located in the folder "<INSTALL_DIR>\Server \DesktopApp".

Any changes to the source must take place in this folder.

The deployment package is created in the **output directory** "<INSTALL_DIR>\Server \WebService\EVDesktopApp".

In order to install multiple Desktop Application versions on the same client machine a unique ID is required. This is often the case when a newer software version is installed on the test server and an older software version is installed in the production environment. This may also be the case when using multi-production server deployments. E.g. one server for Europe and a second server for Asia. The **assembly identity name** is used for identifying a unique client. **Product name** is the visible name of the Performance AL Desktop Application, and it appears in the start menu. These values need to be unique in order for different client versions to be deployed in parallel to the same client machine.

Warning: If the assembly identity name is changed, all users need to install a new

Performance AL Desktop application using the URL: <u>http://<yourservername>/EVServer/</u> <u>EVDesktopApp</u> and uninstall the old one (if they don't need it). Otherwise there will be two (or more) versions of the Performance AL Desktop application in the system.

Version number is the number for the next package. It will be automatically increased every time you create a new package.

We recommend to sign the deployment package. Therefore you need a code signing certificate. The certificate file has to be copied in the directory "<INSTALL_DIR>\Server\". In the section **appSettings** in the file EVServer.exe.config add the key **CodeSigningCertFileName** with the certificate file name as value and the key **CodeSigningCertFilePassword** with the encrypted password for the certificate as value.

Note: The certificate password has to be encrypted with the tool "*<INSTALL_DIR>\Server* *Tools\PasswordEncrypt*" before you add it to the appSettings. During package creation the server checks for an internet connection. If there is no certificate specified or no internet connection exists, the package will be created, but **not signed with the certificate**. In this case the package will get a **publicKeyToken** equal to 0. During installing or updating the Performance AL Desktop Application on the client machine the "Unknown Publisher" security warning appears on the client machine. The client will receive the same warning if there is no internet connection when installing the package.

If you do not provide a code signing certificate but you want to install multiple Desktop Applications on the same machine from different locations, every package must have a **different version number**. Otherwise it will **not be possible to install** a second application with the same version and the same **publicKeyToken**.

8. Performance AL Desktop Explorer

Performance AL Desktop Explorer provides a user interface to Performance AL Server via Microsoft Windows Explorer.

Performance AL Desktop Explorer is a client application for Performance AL Server. Performance AL Desktop Explorer creates a virtual folder in Microsoft Windows Explorer that is called My Performance AL.

You can use this virtual folder to perform tasks similar to those of Performance AL Explorer. The use of Performance AL Desktop Explorer is similar to the use of other folders and files in Microsoft Windows Explorer. You can use the commonly used Microsoft Windows procedures, such as Drag&Drop and Copy&Paste, to perform tasks.

Note:

Desktop Explorer does not support OAuth2.0 and OIDC security providers.

Starting Performance AL Desktop Explorer

You can start Performance AL Desktop Explorer in two ways.

Procedure

Do one of the following:

- Double-click the Performance AL Desktop Explorer icon (
- Start Microsoft Windows Explorer.

Windows Setting Show all Folders

In order to use the Performance AL Desktop Explorer within the navigation area of the windows explorer, the option "Show all folders" needs to be activated.

on vour desktop.

This can be found within the folder options of windows.

Changing the language of Performance AL Desktop Explorer

You can change the language of Performance AL Desktop Explorer after the installation of the software by changing the installation files of the Performance AL Desktop Explorer.

- 1. In Microsoft Windows, click Start > Settings > Control Panel.
- 2. Double-click Add or Remove Programs.
- 3. Click Performance AL Desktop Explorer.
- 4. Click Change.
- 5. On the Performance Analytics Desktop Explorer setup screen, click Next.
- 6. On the Program Maintenance screen, click Modify > Next.
- 7. Select the desired language and click **Next**.

8. Click Install and Finish to set the desired language.

Adding a Performance AL Server

When you start Performance AL Desktop Explorer for the first time, there will be no servers available.

Except when Performance AL Server is running on the system where you installed Performance AL Desktop Explorer the Server will be automatically added.

Procedure

- 1. Right click the My Performance AL window and select Add Server.
- 2. Specify the following:

• In server name field the name of the Performance AL Server

- A **Description** of the Server
- The Location of the Server Depending on the server protocol of the Performance AL Server the location is either tcp://<Servername>, http://<Servername> or https://<Servername>.

Note: If you want to add a Performance AL Server with a version number before 8.5 you have to use either http://<Servername> or https://<Servername>.

- If you want to use Automatic Logon.
- The Security Namespace.
- 3. Click OK.

Removing a Performance AL Server

You can remove Performance AL Servers that are listed in Performance AL Desktop Explorer.

Note: If you remove a Performance AL Server via Performance AL Desktop Explorer, then the Performance AL Server is not removed from the system. Only the reference to the Performance AL Server will be removed from Performance AL Desktop Explorer.

Procedure

1. Right-click a Performance AL Server 🔲 and click **Delete**.

2. Click Yes.

Items

A Performance AL Server contains a repository with items. Items can be of the following type:

- Folder
- Data source
- View
- Canvas

- Image
- Custom item
- Shortcut

The item type **View** contains the view of the data stored in the OLAP database. A view connects to a database. A database connects to a data source.

The item type **Canvas** contains a collection of views.

The item type **Image** can be used as background image in a chart.

The item type **Folder** can be used to organize items in a folder structure. A folder can contain child items of all defined item types. This helps to organize all views and other items in the repository. You can set item security on folders and their child items.

A **Custom item** allows users to store a custom file. This data can be of any type. A shortcut item can be created which refers to any other item, except items of the type folder.

Default settings after installation

After the installation of Performance AL, the following folder items are added to the Performance AL Server repository.

- The root folder with sub folders.
- **\$Private Items** This folder contains all **My Items** folders of all users. A user has a My Items folder when a user has the **Has Private Folder** system permission.
- The **My Items** folder is created for each user that has the Has Private Folder system permission.
- The **System** folder is the generic system folder. It contains the following sub folders:
 - **Data Sources** In this folder you can add data sources. A database item connects to a data source.
 - **Databases** In this folder you can add databases. Databases connect to data sources. A view connects to a database.
 - Images In this folder you can add images. Images can be used as a background in a chart.

Note: If the Has Private Folder system permission is enabled, a folder **My Items** is also added. For more information, see System permissions and roles.

The complete item structure can be adapted to your own situation. Items can be moved, deleted and created. This initial situation is added to help you getting started setting up your own environment.

These items (with the sub folders of the System folder) are available to the accounts that are built-in administrators. Built-in administrators are accounts that are part of the built-in administrator group on the system that runs Performance AL Server or to the accounts specified as built-in administrator in the EVServer.exe.config file.

Adding items

With Performance AL Desktop Explorer you can add items to the repository.

New items of the type **Image**, **Custom**, **Data Source**, **Database**, **View** and **Canvas** can also be added via the commonly used Microsoft Windows procedures, such as Drag&Drop and Copy&Paste from and to the file system.

The following table shows how files from the Windows file system convert to Item types in Performance AL Desktop Explorer.

File types in the Microsoft Windows file system	Item types in Performance AL Desktop Explorer
.bmp	Has all system permissions, except the Has Private Folder system permission.
.jpg	Has Logon Permission.
.gif	image
.png	image
.pvwx	view
.canvas	canvas
other	custom
.xml	database or data source depending on the content of the .xml file

Procedure

- 1. Open a Performance AL Server.
- 2. Right-click and click New.
 - Folder *i*
 - Data Source
 - Database 📁
 - Image 🛋
 - View 🔽
 - Canvas 🗔
 - Custom Item 🗎

Note: When you use Drag&Drop from or to Performance AL Desktop Explorer, then the items or files are always copied and not moved.

Managing items

After an item is added you can manage items in the repository with Performance AL Desktop Explorer.

If an item is copied, the options **Paste** and **Paste Shortcut** are added to the options that show when clicking on screen or on a folder with your secondary mouse button.

Note: It is not possible to create a shortcut to a folder.

Procedure

- 1. Open a Performance AL Server.
- 2. Right-click an item. The following options can be available:
 - Explore the item (only on folder items)
 - Open the item
 - Open all Views (only on folder items)
 - Preview the item (only on images and custom items)
 - Delete the item
 - Cut the item
 - Copy the item
 - Rename the item
 - See the Properties of an item

Opening items

The following table provides an overview of what happens when you open an item in Performance AL Desktop Explorer.

Item	What happens when you open the item			
Folder	The content of the folder is shown.			
Data Source	The properties of the data source are shown.			
Database	The properties of the database are shown.			
Image	The program associated with the image is started to show the image.			
View	Performance AL Client is started to show the view.			
Canvas	Performance AL Client starts and shows the canvas and any associated views.			
Custom Item	The program associated with the custom item is started to show the custom item.			
Shortcut	Opening a shortcut triggers the same action as the item it refers to.			

Security warning when opening a view

When you open a view or canvas in Performance AL Desktop Explorer, then the Performance AL Client starts in Microsoft Internet Explorer. Depending on how the security settings are set in Internet Explorer on your system, a message is presented stating Internet Explorer has restricted this webpage from running scripts or ActiveX controls that could access your computer. As a result the Performance AL Client will not be started.

You can resolve this security restriction by allowing the active content to run in files on "My Computer". Please refer to the documentation of Internet Explorer on how to do this.

Opening an item

Procedure

- 1. Open a Performance AL Server.
- 2. Double-click an item.

The folder item in Performance Analytics Desktop Explorer

Items of the type folder can be used to organize items in a folder structure. After installation of Performance AL Server, all predefined items are created in the root folder.

Note: The root folder cannot be deleted.

A folder can contain child items of all defined item types. It can be seen as a container for all other items, including folder Items.

This facilitates the overview of the Performance AL implementation and makes it easier to perform backup procedures, maintenance and migration from one (test) environment to another.

Creating a folder item

You can create a folder item with Performance AL Desktop Explorer.

Procedure

- 1. Open a Performance AL Server.
- 2. Right-click on screen or on a folder and click **New > Folder** 🧀.
- 3. Enter a name for the folder item.

Changing the properties of a folder item

You can change the properties of a folder item with Performance AL Desktop Explorer.

Procedure

1. Open a Performance AL Server

2. Right-click a folder item and click Properties 🕒. You can change the following properties:

Properties on tab	Purpose
General	The name of the folder item and its description
User Properties	Add or change the User Properties.
Item Policies	Manage or review the folder policies.

Creating a data source item

The predefined folder Data Sources is meant to be used to add items of the type data source.

Database items connect to data source items. Data source items refer to the OLAP database server.

Procedure

1. Open a Performance AL Server.

2. Right-click New > Data Source



Results

Now you can specify the data source item.

Specifying the details of a data source item

After you have created a data source item you can specify the details of the data source item.

Procedure

- 1. Open a Performance AL Server.
- 2. Right-click on a data source item 🗾 and click **Properties**.
- 3. Click the **Data Source** tab.
- 4. From the Data Source Type menu, choose the data source type.
- 5. In the OLAP Server field, specify the name of the OLAP server.
- 6. In the **User Name** field, enter the OLAP administrator user name.
- 7. In the **Password** and **Confirm Password** fields, enter the OLAP administrator password.
- 8. Set the data source specific items. The database settings available depend on the chosen Data Source type. For more information, see *Configuring data sources*.
- Click Test Connection if you want to test the connection details that you have specified.

10. Click **OK** to save the data source settings.

Results

A spark on the data source icon indicates that the data source item is new and does not contain item data. For more information on the status an item can have, see "ItemStatusType Enumeration" in the *Performance AL Server API Reference*.

Changing the properties of a data source item

You can change the properties of a data source item with Performance AL Desktop Explorer.

Procedure

- 1. Open a Performance AL Server.
- 2. Right-click a data source item and click Properties. You can change the following properties:

Properties on tab	Purpose
General	The name of the data source item and its description
User Properties	Add or change the User Properties.
Item Policies	Manage or review the data source policies.
Data Source	The details of the data source item.
Process Distribution	The Process Distribution settings for the data source item.

Database item in Performance Analytics Desktop Explorer

The predefined folder **Databases** is meant to be used to add items of the type database.

Views connect to database items. Database items connect to data source items. The database item refers to a specific database on an OLAP server. This OLAP server is specified in the data source item to which the database item refers.

Creating a database item

You can create a database item with Performance AL Desktop Explorer.

Procedure

- 1. Open a Performance AL Server.
- 2. Right-click and click **New > Database**.
- 3. Enter a name for the database item.

Results

Now you can specify the database item.

Specifying the details of a database item

After you have created a database item you can specify the details of the database item.

Procedure

- 1. Open a Performance AL Server.
- 2. Right-click on a database item = and click **Properties**.
- 3. Click the **Database** tab.
- 4. From the **Data Source Type** menu, choose the data source type.
- 5. In the **Data Source** field, specify the data source by either typing the name or selecting the name from the menu.
- 6. In the **Cube Name** field, specify the database name or the cube name by either typing the name or selecting the name from the menu. If you type the name, use the following format: "<data source name>\<database name>".
- 7. Set the database specific items. The database settings available depend on the chosen Data Source type. For more information, see *"Configuring data sources"*.
- 8. Click **OK** to save the database settings.

Results

An exclamation mark on the database icon \leq indicates a problem. For example the data source item to which the database item refers could not be found at the specified location.

A spark on the database icon indicates that the database item is new and does not contain item data. For more information on the status an item can have, see "ItemStatusType Enumeration" in the *Performance AL Server API Reference*.

Changing the properties of a database item

You can change the properties of a database item with Performance AL Desktop Explorer.

Procedure

- 1. Open a Performance AL Server.
- 2. Right-click a database item and click **Properties**. You can change the following properties:

Properties on tab	Purpose
General	The name of the database item and its description
User Properties	Add or change the User Properties.
Item Policies	Manage or review the database policies.

View item in Performance Analytics Desktop Explorer

The predefined folder **My Items** can be used to add items of the type view. This initial situation is added to help you get started setting up your own environment. A user has a **My Items** Folder when a user has the System Permission **Has Private Folder**.

Views can be added in any folder or canvas to organize your own environment. A view item contains the view definition of the data stored in the OLAP database to which the view refers. A view connects to a database item and that database item connects to a data source.

Creating a view item

You can create a view item in Performance AL Desktop Explorer.

Procedure

- 1. Open a Performance AL Server.
- 2. Right-click and click **New** > **View W**.
- 3. Enter a name for the view item.

Opening a view after creation of a view item

After you have created a view item with Performance AL Desktop Explorer you can open the view in Performance AL Client.

Depending on the installation and configuration of the security providers, Performance AL Server can authenticate the user. Otherwise you have to enter the credentials in order to log on to the specified database when you open a view.

For more information, see "Installing Performance AL Client".

Procedure

- If Performance AL Client is not installed, you will be prompted to install it. Once Performance AL Client is installed, the **Connection Information** dialog is displayed.
- 2. From the **Database** menu select the database you have configured within Performance AL Server.
- 3. Click OK.

Results

The created view is shown. The view displays the data that is stored in the OLAP database.

An exclamation mark on the view icon \overline{N} indicates a problem. For example the data source item to which the database item refers could not be found at the specified location.

A spark on the view icon indicates that the view item is new and does not contain item data. For more information on the status an item can have, see "ItemStatusType Enumeration" in the Performance AL Server API Reference.

Changing the properties of a view item

You can change the properties of a view item with Performance AL Desktop Explorer.

Procedure

- 1. Open a Performance AL Server.
- 2. Right-click a view item and click **Properties**. You can change the properties as specified in the next table.

Properties on tab	Purpose
General	The name of the view item and its description
User Properties	Add or change the User Properties.
Item Policies	Manage or review the view item policies.

Canvas item in Performance Analytics Desktop Explorer

The predefined folder **My Items** can be used to add items of the type canvas. Canvases can be added in any folder to organize your own environment.

A canvas item contains the associated views. The associated views connect to a database item and that database item connects to a data source.

Creating a canvas item

You can create a canvas item in Performance AL Desktop Explorer.

Procedure

- 1. Open a Performance AL Server
- Right-click and click New > Canvas
- 3. Enter a name for the canvas item.

Opening a canvas after creation of a canvas item

After you have created a canvas item with Performance AL Desktop Explorer you can open the canvas in Performance AL Client.

Depending on the installation and configuration of the security providers, Performance AL Server can authenticate the user. Otherwise you have to enter the credentials in order to log on to the specified database when you open a view.

- If Performance AL Client is not installed, you will be prompted to install it. Once Performance AL Client is installed, the **Connection Information** dialog is displayed.
- 2. From the Database menu select the database you have configured within Performance AL Server.
- 3. Click **OK**.

Results

The canvas displays the associated views.

An exclamation mark on the canvas icon indicates a problem.

A spark on the view icon indicates that the view item is new and does not contain item data.

Associating a view item with a canvas with Performance AL Desktop Explorer

After you have created a canvas item with Performance AL Explorer you can insert a view item to the canvas as a panel.

Procedure

- 1. Click the canvas item you have created in Performance AL Explorer.
- 2. Click Views.
- 3. Select the view to include in the canvas.
- 4. Click Open.

Results

The view shows in the canvas as a panel. The view displays the data that is stored in the OLAP database. More than one view can be associated with a canvas.

Changing the properties of a canvas item

You can change the properties of a canvas item with Performance AL Desktop Explorer.

Procedure

1. Open a Performance AL Server

2. Right-click a canvas item and click **Properties**. You can change the properties as specified in the next table.

Properties on tab	Purpose
General	The name of the canvas item and its description
User Properties	Add or change the User Properties.
Item Policies	Manage or review the canvas item policies.

Image item in Performance Analytics Desktop Explorer

The data in a view can be displayed as a chart. You can use an image item as a background image in that chart.

The predefined folder **Images** can be used to add items of the type image. For more information, see the Performance Analytics User Guide.

Creating an image item

You can create an image item in Performance AL Desktop Explorer.

Procedure

- 1. Open a Performance AL Server.
- 2. Right-click and click **New** > **Image** .
- 3. Enter a name for the image item.
- 4. Right-click the image item and click **Properties**.
- 5. Click the **Image** tab.
- 6. Click **Browse** and select an image. Images can be of the type BMP, GIF, JPEG and PNG.
- 7. Click **Upload** to put the image file in the Performance AL repository.
- 8. Click **OK**.

Results

A spark on the image icon indicates that the image item is new and does not contain item data. For more information on the status an item can have, see "ItemStatusType Enumeration" in the Performance AL Server API Reference.

Changing the properties of an image item

You can change the properties of an image item with Performance AL Desktop Explorer.

Procedure

- 1. Open a Performance AL Server.
- 2. Right-click an image item and click **Properties**. You can change the properties as specified in the next table.

Properties on tab	Purpose
General	The name of the image item and its description .
Image	A preview of the image and the possibility to upload an image.
User Properties	Add or change the User Properties.
Item Policies	Manage or review the image item policies.

Custom item in Performance Analytics Desktop Explorer

A custom item allows you to store a custom file. This data can be of any type.

Creating a custom item

You can create a custom item with Performance AL Desktop Explorer.

Procedure

- 1. Open a Performance AL Server.
- 2. Right-click and click Add Item > Custom Item 🗎.
- 3. Enter a name and a description for the custom item.
- 4. Right-click the image item and click **Properties**.
- 5. Click the **Custom Item** tab.
- 6. Click Browse and select a file.
- 7. Click **Upload** to put the file in the Performance AL repository.
- 8. Click **OK**.

Results

A spark on the custom icon indicates that the custom item is new and does not contain item data. For more information on the status an item can have, see "ItemStatusType Enumeration" in the *Performance AL Server API Reference*.

Opening a custom item

You can open a custom item in Performance AL Desktop Explorer.

The custom item will be opened by the application that is associated with the file extension and the MIME Type of the custom item.

Procedure

- 1. Open a Performance AL Server
- 2. Double-click a custom item 🗎.

Changing the MIME type of a custom item

You can change the MIME type of a custom item with Performance AL Desktop Explorer.

The custom item will be opened by the application that is associated with the file extension and the MIME Type of the custom item.

- 1. Open a Performance AL Server
- 2. Right-click a custom item 🗎 and click **Properties**.
- 3. Click the Custom Item tab.
- 4. Use the **MIME Type** field to specify the **MIME type**.
- 5. Click **OK**.

Changing the properties of a custom item

You can change the properties of a custom item in Performance AL Desktop Explorer.

Procedure

- 1. Open a Performance AL Server.
- 2. Right-click a custom item and click **Properties** . You can change the properties as specified in the next table.

Properties on tab	Purpose
General	The name of the custom item and its description
Custom Item	The possibility to upload a file. Upload a file Set the File Name Set the MIME Type
User Properties	Add or change the User Properties.
Item Policies	Manage or review the custom item policies.

Shortcut item in Performance Analytics Desktop Explorer

A shortcut item inherits the type of the item it refers to. A shortcut can refer to all item types except the item type folder.

Creating a shortcut item

You can create a shortcut item with Performance AL Desktop Explorer. **Note:** You cannot create shortcut items for folder items.

Procedure

- 1. Open a Performance AL Server.
- 2. Right-click an item and click Copy.
- 3. Right-click in any folder where you want to add the shortcut > Paste Shortcut 🖧.

Results

The shortcut is added to the repository. When you are logged in as a user that has the Manage item permission on this shortcut, the shortcut can be recognized by a little arrow \mathbb{Z} in the left bottom corner. Another user who does not have the necessary permission, neither sees the arrow, nor knows that the item is a shortcut. For this user, the shortcut item is shown as an item of the item type it refers to. If a short cut item is not valid (if it refers to an invalid item, for example an item that no longer exists), the user does not see it.

A red shortcut indicator indicates that for example the shortcut item does not refer to an item of the correct type.

An exclamation mark and a shortcut **s** indicator on for example the database icon indicates that for example the data source item to which the database refers could not be found at the specified location.

A spark and a shortcut indicator on for example the database icon indicates that the database item does not contain item data. For more information on the status an item can have, see "ItemStatusType Enumeration" in the Performance AL Server API Reference.

Property inheritance

In case of a shortcut item, system- and user-defined properties are inherited from the referenced item. This means if an item has a property "New", then shortcuts to this item also have access to the same property "New". When retrieving the list of properties from the shortcut item, the property "New" will be included in the list.

It is not possible to change the value of an inherited property on the shortcut. The value can only be changed on the original item.

If the shortcut itself has a property "New", the value of the property "New" belonging to the shortcut will be retrieved instead of the value of property "New" of the item the shortcut refers to.

In case of a chain of references (shortcuts referencing to shortcuts, referencing to an item) this inheritance continues. This means when you retrieve the properties of the last shortcut item in the chain, all properties of all (shortcut) items are retrieved.

Database wizard in Performance Analytics Desktop Explorer

The Database Wizard enables you to register databases for a data source.

- 1. Right-click a valid data source is and click **Database Wizard**.
- 2. On the Welcome to the Database Wizard screen click Next.
- 3. Enter the OLAP credentials if they are required by the data source. An overview of the databases that can be registered is shown.
- 4. In the **Destination Folder** field specify the folder where the databases have to be created. By default the **Database Post Search** Path is used. If there is no destination folder specified, the database Items will be created in the current folder.
- 5. In the **Database Name Prefix** field specify a prefix for the database name. This optional prefix will be added to the name of the created database item.
- Click Next.
 Note: The registration can take some time.
- 7. When the databases have been registered, a status overview of the created databases is shown. The databases are added to the Performance Analytics Server repository.
- 8. Click Finish.

Item system properties and view system properties

System properties are defined by Performance AL Server. In general, it is not possible to delete a system property of an item. Some system properties are marked as read-only (RO). If this is the case, the value of the property cannot be changed. System properties have the prefix "_" in the property name. The following table shows the available system properties:

Name	Туре	Description	State
_Description	string	Description of the item. Available for all items, optional for shortcut. Can be created or deleted only for shortcut.	RW
_DateCreated	datetime	Date item is created. Available for all items, except shortcut. Cannot be created or deleted.	RO
_UserCreated	string	Date item is created. Available for all items, except shortcut. Cannot be created or deleted.	RO
_DateModified	datetime	Date of modification. Available for all items, except shortcut. Cannot be created or deleted.	RO
_UserModified	string	Name of the user who modified the item. Available for all items, except shortcut. Cannot be created or deleted.	RO
_DateAccessed	datetime	Date of last access. Available for views and canvas. Cannot be created or deleted.	RO
_UserAccessed	string	Name of the user who accessed the item. Available for views and canvas. Cannot be created or deleted.	RO
_AccessCount	int64	Cumulated access count. Available for views and canvas. Cannot be created or deleted.	RO
_Link	string	Path to the item of the shortcut. Cannot be created or deleted.	RW
_Database	string	The database that the view connects to. Can be created or deleted.	RW
_Datasource	string	The data source that the database connects to. Can be created or deleted.	RW

	The data source type of the data source and the database. Can be created or deleted.	RW
--	--	----

The following table shows the available system properties that apply to the item type view. They contain meta information about a view.

Name	Туре	Description
_Notes	string	The notes in a view. If a view does not contain a note, this system property is not available.
_ScalingFactor	double	The scaling factor that is applied to the view. This is the scaling factor set on the Numbers tab of the Options dialog. This system property is not available if the scaling factor is set to default value 1.
_DynaSelectText	string	The text of the DynaSelect. If the view does not contain a DynaSelect, this system property is not available.
_DisplayMode	string	The parts that the view contains. Possible values are: table notes drillthrough line bar pie area radar maps bubble range scatter The names are separated with a comma.
_PrintOrientation	string	The print orientation of the view. Possibilities are: default portrait landscape

Properties

Each item in the Performance AL Server catalog can have user-defined and system properties associated with it.

A property is a user-defined or system attribute with a **Name**, a **Data Type** and a **Value**. The number of properties that an item can have is unlimited.

The **Name** is a unique identifier for the property. The **Value** is a simple-type that can contain textual, numerical or date-time information.

User-defined properties

The following table shows the data types that are supported for user-defined properties:

Data Type	Possible value
boolean	true/false
byte	0255
char	Unicode character 0x0000 0xFFFF
datetime	12:00:00 AM, 0001-01-01 11:59:59,31.12.9999
decimal	+79,228,162,514,264,337,593,543,950,335 -79,228,162,514,264,337,593,543,950,335
double	±5.0 * 10E-324 ±1.7 * 10E308
guid	unique 128 bit number {F9168C5E-CEB2- 4faa-B6BF-329BF39FA1E4}
int16	-32,768 32,767
int32	-2,147,483,648 2,147,483,647
int64	-9,223,372,036,854,775,808 9,223,372,036,854,775,807
sbyte	-128 127
single	±1.5 * 10E-45 ±3.4 * 10E38
string	Sequential collection of Unicode characters
timespan	-9,223,372,036,854,775,808 9,223,372,036,854,775,807 (can be represented as [-]d.hh:mm:ss.ff)
uint16	0 65,535
uint32	0 4,294,967,295
uint64	0 18,446,744,073,709,551,615

Creating user-defined properties

Procedure

1. Open a Performance AL Server.

- 2. Right-click an item and click **Properties** > **User Properties**.
- 3. Click Add.
- 4. Enter the Name, the Data Type and the Value for the user defined property.
- 5. Click **OK**.

Managing Performance AL Server with Performance AL Desktop Explorer

There are settings you need to configure in Performance AL Server. You can configure these settings by using Performance AL Desktop Explorer.

Viewing the version information

Procedure

- 1. Right-click a Performance AL Server and click **Properties**.
- 2. On the **Info** tab, the **Version Information** section shows the version of Performance AL Server.

Accounts

An account can be made for a single user, for a group of users, of for a user role.

System Roles (with their **Permissions**) are attached to an account. This is called a system policy.

Item Roles (with their **Permissions**) are attached to an account and to an item. This is called an item policy.

After installation of Performance Analytics, only the account Everyone appears.

The created account **Everyone** represents all users that can be validated by the installed **Security Provider**.

Accounts are added when setting **Item Policies** or **System Policies**. Accounts cannot be added individually.

Performance AL Server uses the specified accounts through one or more **Security Providers**. Performance AL Server does not have accounts of its own.

When a system or item policy is set for a specified account, this account appears on the **Accounts** list.

Viewing Accounts

Procedure

- 1. Right-click a Performance AL Server and click **Security** > **Accounts**.
- 2. In the Accounts section you can view the available accounts.

Deleting Accounts

- 1. Right-click a Performance AL Server and click **Security** > **Accounts**.
- 2. Select the account you want to delete and click **Delete**.

Results

After deleting an account, all associated Item Policies and System Policies of the account are deleted from Performance AL Server.

When an account has no Item Policies and System Policies defined, the account is no longer available from Performance AL Server.


Security

Performance AL Server security can be divided into two groups: system security and item security. You can set both permissions: item permissions and system permissions. Item permissions apply to items in the repository. System permissions apply to the system: Performance AL Server.

Note: A built-in administrator can always manage the security on a Performance AL Server by using Performance AL Desktop Explorer. This is to prevent administrators creating a situation where they are locked out or cannot access Performance AL Server anymore as a result of changing the System Security settings.


Item security

An item role (with its item permissions) is attached to an account and to an item. This is called an item policy.



System security

A system role (with its system permissions) is attached to an account. This is called a system policy.



To be able to organize and structure permissions, they are attached to roles. A role contains one or more permissions.

The item permissions and system permissions are a fixed set of permissions. After installation, several item roles and system roles are created, to help you get started with Performance AL Server security. You can modify, delete, and to create new roles.

After the installation of Performance AL Server, one system policy is added. For the root item and the items **\$Private Items** and **System** one item policy is added.

These policies can be modified, or deleted and you can create your own policies.

Sessions

To apply system and item security, Performance AL Server must be able to authenticate a user. This is done via a session.

A Performance AL Server session is created when a user logs on to Performance AL Server. After the user is successfully authenticated, the Performance AL Server retrieves the appropriate permissions, for example to use views or to connect to an OLAP database. During the creation of a session, credentials are passed to the Performance AL Server. Performance AL Server will pass these credentials to a configured security provider. This security provider validates whether the user is allowed to log on to the system with the specified credentials. Once a session is created, this session provides the access to Performance AL Server.

A session can be created by a portal (for example Performance AL Explorer) by using the CreateSession method, or by Performance AL Client creating an instant session.

For more information about the "CreateSession" method, see the *Performance AL Server API Reference*.

For information about Security Providers, see "Configuring the security provider".

Item permissions and roles

You can set permissions on an item. A named combination of these permissions is called an Item Role.

Available permissions

The next table shows the available permissions.

Permission	Description
List	List the items in the parent folder.
Read	Read the contents of an item.
Modify	Modify an item.
Manage	Manage an item. Items can be created, deleted, and renamed.

Full Control	With Full Control permission, you can change the
	security on an Item.

For comments, the following permissions are available.

Permission	Description
Manage Comments	Manage the comments of all users in the database.
Write Comments	Read all comments, write and modify your own comments in the database.
Read Comments	Read all comments in the database.

Permissions implications

Item permissions are dependent on each other. Setting a permission may imply other permission settings. The next table shows an overview of these implications.

- x = set permission
- o = implied permission

	Full Control	Manage	Modify	Read	List
Full Control	x				
Manage	0	х			
Modify	0	0	х		
Read	0	0	0	х	0
List	0			0	x

For comments, the item permissions partially depend on each other as well. The following table shows how the permissions are implied.

	Manage Comments	Write Comments	Read Comments
Manage Comments	х		
Write Comments	0	х	
Read Comments	0	0	х

Setting permissions for an item

Procedure

- 1. Right-click a Performance AL Server and click **Security** > **Item Roles**. The available predefined Item Roles are shown.
- 2. Select an item role and click **Edit**.
- 3. Set the **Permissions** for the item role.
- 4. Click OK.
- 5. Click Close.

Comments

Comment item permissions take only effect when they are set on a **Database** item. Then, the policy applies for all views, which use this particular database item as its data source.

Item roles

An item role contains item permissions. After installation, the following predefined Item Roles are available.

Item role	Description
Administrator	Has these permissions:
	Full
	Control
	Manage
	Modify
	Read
	List
	Manage Comments
	Write Comments
	Read Comments
Author	Has these permissions:
	Manage
	Modify
	Read
	List
	Write Comments
	Read Comments
Consumer	Has Read permissions.
Reviewer	Has Read and List permissions.

Adding an item role

Procedure

- 1. Right-click a Performance AL Server and click **Security** > **Item Roles**. The available predefined Item Roles are shown.
- 2. Right-click and click New Item Role.
- 3. Specify the following for the item role:
 - A Name
 - A Description
 - The Item Permissions
- 4. Click Add.

Opening an item role

When you open an item role you can modify the item role and set its permissions.

Procedure

- 1. Right-click a Performance AL Server and click **Security** > **Item Roles**. The available Item Roles are shown.
- 2. Right-click an item role and click Edit.

Item Policies

After installation of Performance AL, an item policy is added for the root item. This policy gives the account **<Everyone>** the item role **Reviewer**. This means all users, that are allowed to log on to Performance AL Server, can read and list the items in the repository.

For the items **\$Private Items** and **System** an item policy is added that gives the account **<Everyone>** the item role **Consumer**. This means all users, that are allowed to log on to Performance AL Server, can read the items. This is necessary in order to let users access databases or data sources that are specified in the System folder.

An item role with its **Item Permissions** is attached to an account and to an item. This is called an item policy. You can set an item policy on an item.

Adding Item Policies

- 1. Open a Performance AL Server .
- 2. Right-click an item and click **Properties**.
- 3. On the Item Policies tab click Add.
- 4. Specify the following:
 - The Account Type
 - The Account Name
 - One or more Item Roles
- 5. Click **OK**.

- 6. Select an account and in the policies area specify one or more **Roles**.
- 7. Click **OK**.

System permissions and roles

You can set permissions for a system. A named combination of these permissions is called a System Role.

Available permissions

The next table shows the available permissions.

Permission	Description
Logon	Logon to Performance Analytics Server. If this permission is not set for a system role, then the user cannot create a session and is refused to logon to Performance AL Server.
Manage Roles	Create, view, modify and delete roles.
Manage System Policies	Create, view, modify and delete System Policies.
Manage Sessions	View and invalidate sessions.
Manage Item Policies	Create, view, modify and delete Item Policies.
Manage Folders	Create, modify and delete folders.
Manage Views/Canvases	Create, modify and delete views and canvases.
Manage Databases	Create, modify and delete databases.
Manage Data Sources	Create, modify and delete data sources.
Manage Images	Create, modify and delete images.
Manage Custom Items	Create, modify and delete custom items.
Manage Logging	View logging.
Has Private Folder	Allowed to have a Private Folder.
	 Note: If this permission is not set for a role, then the ev client doesn't show the following folders in the backstage area for this user: Recent Views My Views
Lico Commonto	My Templates
Use Comments	Use any comment related functionality.

The following system permissions apply for the corresponding item type:

- Manage Folders
- Manage Views/Canvases
- Manage Databases
- Manage Data Sources
- Manage Images
- Manage Custom Items.

The user that has these permissions, can create, modify and delete the item types at system level. For individual items, you have to set the item permissions.

For example: in order to set item policies on an item, a user needs to have the system permission **Manage Item Policies** and the Item Permission **Full Control** on the item for which to set the policy.

Setting system permissions

Procedure

- 1. Right-click a Performance AL Server and click **Security** > **System Roles**. The available predefined **System Roles** are shown.
- 2. Select a system role and click Edit.
- 3. In the Edit System Roles window set the Permissions.

System roles

A system role contains system permissions. After installation, the following predefined System Roles are available.

Permission	Description
System Administrator	Has all system permissions, except the Has Private Folder system permission.
Logon	Has Logon Permission, has a private folder and can use comments.

Adding System Roles

- 1. Right-click a Performance AL Server and click **Security** > **System Roles**. The available predefined *System Roles* are shown.
- 2. Right-click and click Add.
- 3. Specify the following for the system role:
 - A Name
 - A Description
 - The System Permissions
- 4. Click Add.

Editing system roles

When you open a system role you can modify the system role and set its permissions.

Procedure

- 1. Right-click a Performance AL Server and click **Manage** > **Security** > **System Roles**. The available System Roles are shown.
- 2. Right-click a system role > **Open**.

System Policies

System Roles (with their system **Permissions**) can be attached to an account. These are called **System Policies**.

After the installation of Performance Analytics, two System Policies are added: **Logon User** and **Evaluation User**. For information on the Evaluation User, see "Evaluation roles and policies".

Logon User

A system policy is added that gives the all users the system role **Logon User**.

This means that all users in the account **Everyone** can logon to Performance AL Server, which is needed in order to create a session.

Adding System Policies

Procedure

- 1. Right-click a Performance AL Server and click **Manage** > **Security** > **System Policies**.
- 2. In the Policies section, click **New**.
- 3. Specify the following:
 - The Account Type
 - The Account Name
 - One or more System Roles
- 4. Click Add.

Evaluation roles and policies

Some users who evaluate Performance AL do not have local administrator permissions. If a user does not have the local administrator permissions, the restricted permissions that are defined for the default Everyone Account will be used.

For evaluation purposes, evaluation roles and policies are available.

The **Evaluation User** system role and item role offer administrator permissions to change the Performance AL repository. After evaluation and defining the desired repository security, remove the **Evaluation User** roles. They should not be available in a production environment. **Note:** The **Evaluation User** roles are created only after initialization of the Performance AL repository. The Performance AL repository is initialized when Performance AL Server is started for the first time.

Initial situation

To set the system so that all users have access during evaluation:

- The role Evaluation User is added to System Roles and item roles.
- The policy Evaluation User is added to System Policies and item policies.

Evaluation User system roles

The properties for a user can be changed according to the role that is set. For the **Evaluation User** system role the following **Permissions** are set initially:

- Logon
- Manage Roles
- Manage System Policies
- Manage Sessions
- Manage Item Policies
- Manage Folders
- Manage Views/Canvases
- Manage Databases
- Manage Data Sources
- Manage Images
- Manage Custom Items
- Manage Logging
- Has Private Folders

Changing properties of the Evaluation User system role

Procedure

- 1. Right-click a Performance AL Server and click **Security** > **System Roles**.
- 2. Select the Evaluation User system role and click Edit.
- 3. Change the following properties of the system role:
 - Name
 - Description
 - Permissions
- 4. Click **OK**.
- 5. Click Close.

Evaluation User item roles

For the Evaluation User item role the following Permissions are set initially:

- List
- Read

- Modify
- Manage
- Full Control

Changing properties of the Evaluation User item role

Procedure

- 1. Right-click a Performance AL Server and click **Manage** > **Security** > **Item Roles**.
- 2. Click the **Evaluation User** item role.
- 3. Change the following properties of the item role:
 - Name
 - Description
 - Permissions
- 4. Click Update.

Viewing the system policy Evaluation User

The policy **Evaluation User** has been added to **System Policies**. You can add this system policy to an item.

Procedure

- 1. Open a Performance AL Server.
- 2. Right-click an item and click **Properties**.

Results

In the **Policies** section, the **Account Evaluation User** is shown.

Active Sessions

If you have the system permission to manage sessions then you can view and terminate active sessions of Performance AL on a Performance AL Server.

Viewing Active Sessions

To view active sessions and the last used session of Performance AL on a Performance AL Server.

- 1. Right-click a Performance AL Server and click **Active Sessions**. In the **Active Sessions** table, the active sessions of Performance AL are listed with the following details:
 - User
 - Host address
 - Creation time
 - Last used. Last used is updated when a user performs an action on Performance AL Server.

- Description
- 2. You can sort the table of **Active Sessions** by clicking on a detail you want to sort on.

Terminating Active Sessions

You cannot terminate your own session within Performance AL Explorer. You can only terminate other sessions.

Procedure

- 1. Right-click a Performance AL Server and click Active Sessions.
- 2. In the **Active Sessions** table, select the active session you want to terminate and click **Terminate**.
- 3. Click Yes.

Server Log

The Performance AL Server log contains the following entries:

Log entry	Explanation
Category	Shows the category of the log. For example General, or Security.
Component	Shows the component that logged the log entry. For example the Security Provider or the Catalog Provider.
Level	Shows the log level.
Message	Contains the actual log message.
Process ID	Contains the ID of the Performance AL Server Process.
Thread ID	Contains the ID of the thread in the Process.
Session ID	Contains the ID of the Session.
Date-Time	Contains the date and time.

Showing and browsing the Log entries

- 1. Right-click a Performance AL Server and click View Log.
- 2. If you have process distribution enabled with master and slave servers, you can specify the server for which you want to view the log entries.
- 3. You can browse the **Log entries** by clicking the following buttons:
 - First
 - Prev
 - Next
 - Last

Setting a filter on the Log entries

You can set a filter if you do not want to see all Log entries.

- 1. Right-click a Performance AL Server and click **View Log**.
- 2. Click **Filter**. The following table lists the available filter options.

Filter	Explanation
Thread ID	Specify the Thread ID to view the log entries for, or "*" for all.
Session ID	Specify the Session ID to view the log entries for, or "*" for all.
Process ID	Specify the Process ID to view the log entries for, or "*" for all.
Level	Severe The less detailed level.
	Only severe errors are logged. These are errors that may cause a situation where Performance AL Server is unusable.
	Error All errors are logged. These are situations where Performance AL Server can run but a provider cannot be started.
	Warning Warnings are logged, for example when a provider is not correctly configured.
	Info Information is logged, for example the start and stop of Performance Analytics.
	Verbose More detailed information is logged, for example the loading of the catalog items.
	Trace The same information as in Verbose is logged, only more detailed.
	Debug The most detailed level. All possible information is

	logged.
	Note: The levels Severe, Error and Warnings give you information about (possible) errors that occur in Performance AL Server. The levels Warning, Info and Verbose contain information about the status or activities of Performance AL Server. The levels Trace and Debug are recommended in case you experience problems with Performance AL Server and you want to see all detailed information.
Sort order	Ascending or Descending
Components	For more information, see <i>"Components used by Performance Analytics"</i> . The possible Components are: Server The Log providers are:
	LogProviders.Event LogProviders.File LogProviders.Mail LogProviders.Oracle LogProviders.SQLServer LogProviders.XML
Components	The Catalog providers are: CatalogProviders.Oracle CatalogProviders.SQLServer
Components	The Categories are: Configuration General InternalError ParameterValidation Security ServerProtocol Session UnsupportedType WorkerProcessProtocol
Begin Date-Time	The start date for the filter.

Search paths

Performance AL Server has a search logic for resolving items that are referenced. Some item types link to another item. For example a view item can link to a database or an image, or a shortcut can link to any other item type.

The search order to find these linked items is:

- 1. The search **Pre paths**.
- 2. Search in the current folder and its ancestor folders from the specified item to the root folder.
- 3. The search **Post paths**.

For the item types data source, database and image, the search **Pre paths** and the search **Post paths** can be set. By default, the search **Pre paths** is empty and the search **Post paths** is the first sub folder in the **System** folder with the item type name. For example for item type images this is **/System/Images**.

Setting the search paths

Procedure

- 1. Right-click a Performance AL Server and click **Properties** > **Search Paths**.
- 2. For the item types **Data Source**, **Database** and **Image** you can set the search paths in the **Pre path** and **Post path** fields. You can define multiple search paths on new lines. Press the Enter key to create a new line.
- 3. Click Update.

Monitoring

You can monitor the present users and the number of users who have connected to a Performance AL Server over a period of time using Monitoring.

Note: Only users of Performance AL Client are registered. Users of Performance AL Explorer and Performance AL Desktop Explorer are not registered.

Viewing named users

The **Named Users** table shows the individual users of Performance AL Client that have connected to the system at any time. For each user the following data is shown:

User Name

The name of the user

- Security Namespace The security provider that is used by the user.
- First Connected The date on which the user first connected.
- Last Connected The date on which the user last connected.

1. Right-click a Performance AL Server and click Named Users.

Viewing concurrent users

The Concurrency counters table shows the maximum number of simultaneous connections to Performance AL Server per day. The following data is shown:

• Date

The date for the concurrency counters

• Timestamp

The time of the day when the maximum of concurrent users was attained for the first time. Note that this value is only populated since the 8.7.0 release and is set to 00:00:00 for all prior entries.

Concurrent Users

Represents the maximum number of users that access the system simultaneously on this date.

• Maximum concurrent users The maximum number of concurrent users that are registered on any day.

Note: If no user does log on or off on a particular day, that day will not be shown in the list of concurrent users.

Procedure

1. Right-click a Performance AL Server and click **Concurrency Counters**.

Comments

When comments shall be used, ensure that the following configuration has been applied correctly.

Database and Data Source settings

The database must be configured to allow comments. There are two options available to achieve that.

- 1. Navigate to the Data Source item which is shall be allowed
- 2. Select an Allow Comments option
 - \circ Never

Disables comments for all **Database** items which use this Data Source, regardless of their **Allow Comments** checkbox state.

• Always

Enables comments for all **Database** items which use this Data Source, regardless of their **Allow Comments** checkbox state.

Database Specific

Allows to configure the **Allow Comments** setting per **Database** item individually. The checkbox of the **Database** item applies now.

System roles

The logged in user has to be allowed to Use Comments in general.

- 1. Right click on a Performance AL server and select Manage
- 2. Click on System Roles
- 3. Select the role, which shall be allowed to use comments
- 4. Ensure, the Use Comments checkbox is checked
- 5. Click OK

System policies

Also ensure, that the user which shall use comments, owns a System Role which is allowed respectively.

- 1. Right click on a Performance AL server and select Manage
- 2. Click on System Policies
- 3. Ensure the users, which shall be allowed to use comments, have the correct **System Roles** assigned

Item roles

Define, which item role has which comment permission. An user can be allowed to read, write or manage comments. For a more detailed description see available permissions.

- 1. Right click on a Performance AL server and select Manage
- 2. Click on Item Roles
- 3. Select the role, which shall be configured for certain comment permissions
- 4. Check or uncheck the corresponding checkboxes depending on the required user permissions

Item policies

The detailed user permissions for Read, Write and Manage Comments have to be set for each Database item individually.

- 1. Navigate to the **Database** item for which the user permissions shall be configured
- 2. Click on Properties
- 3. Update policy settings for this item by adding or removing user and role combinations correspondingly

General Settings

- 1. Right click on a Performance AL server and select Manage
- 2. In the section Comments click on General Settings

The following settings can be made:

- Maximum comment length (characters) The number of characters which a comment can have at most.
- Maximum attachment size (MB)

The maximum size of one attachment

• Maximum total attachment size per entry (MB)

On one comment several attachments can be added. The cumulative size of all these attachments can't be higher than this number.

• Allowed attachment file types

This is a white list of all allowed file types (endings) that are allowed as attachments. Each file type needs to be added in a new row.

• History length

Defines the number of comments that should be shown in the comment panel. If there are more comments available a button **Show all comments** will be under the last comment. Clicking this button will load the rest of the comments.

Orphaned Items

- 1. Right click on a Performance AL server and select Manage
- 2. In the section Comments click on Orphaned Items

A comment is identified by a coordinate (unique combination of **Dimension / Member** values.

If a member of a dimension (or a whole dimension) gets deleted in the structure of the cube, the coordinate of the comment does not match any more and the comment is not assigned to a certain item in this state.

Also if a new dimension was added to the structure, the coordinates are not unique any more and need to be adjusted.

Therefore the **Orphaned Items** panel gives the following features.

After selecting the cube in the **Database** box the following functions can be applied to the comments:

• Remove invalid dimensions from all orphaned members

Clicking this link will delete all **Dimension / Member** pairs that don't match to the current cube structure. This is useful when a dimension was removed from the structure of a cube.

- Add a new dimension to all orphaned members
- Clicking this link will open a panel where a **New dimension name** and a **New member name** can be added. This is useful when a dimension was added to structure of a cube.
- Map Member

Clicking this link will open a panel where the **Old dimension name** and **Old member name** are shown. By entering values in the fields **New dimension name** and **New member name** the comment coordinates can be updated.

Delete Comments

Clicking this link will delete the comments that match on a certain coordinate.

9. Performance AL Desktop

Performance AL Desktop basically is a desktop application wrapper around the Performance AL Client allowing you to access Performance AL without using Microsoft Internet Explorer.

The application can be started by either calling the installation URL (see <u>Installing</u> <u>Performance AL Desktop</u>) or by using the desktop shortcut, which will be created during the installation.

Performance AL Desktop URL parameters

Performance AL Desktop supports the following URL parameters, which can be appended to the installation URL (see Installing Performance AL Desktop)

• Item

With the *Item* parameter you can pass a view path, which is opened directly after starting the application.

Example: http://<yourservername>/EVServer/DesktopApp?Item=/MyView

Culture

The *Culture* parameter sets the language of the application, independent of the server settings.

Example: http://<yourservername>/EVServer/DesktopApp?Culture=fr-FR

SessionID

With the SessionID parameter you can pass a valid session to the application.

Example: http://<yourservername>/EVServer/DesktopApp? SessionID=MySessionID

• EnableLogging

You can log the startup process of the Desktop application for debugging purpose. To enable the logging mode you have to set this parameter to "True". Once the application has finished loading you can see the logfile path in the window header. Alternatively, use the shortcut "CTRL + L", which copies the file path into the clipboard. This shortcut is only available until you clicked anything in the application window.

Example: http://<yourservername>/EVServer/DesktopApp?EnableLogging=True

Note: The shortcut created during the installation points to the URL (including the

parameter) which was called. Before you use any of this parameters you should install the application via the installation URL without any parameters.

10. Performance AL Anywhere

The Performance AL *Anywhere* client is a web based client that communicates with Performance AL Server through a restful Web API. The REST server providing the Web API runs self-hosted inside the Performance AL Server process.

The following section describes how to configure the web application, REST server and clients for Performance AL*Anywhere*.

Configuring the web application

The web application for Performance AL *Anywhere* is hosted in IIS. The application serves a static web page (index.html) to the client. All further communication will take place between the client and the Performance AL REST server. Thus the web application does not need to require authentication.

In order to configure the web application, open the "EVServer.exe.config" file.It can by default be found in the folder "C:\Program Files\cubus\Performance Analytics\Server".

The following parameters can be configured:

• EVDesktop_Culture

The language the client is using. Valid values are *da*, *de*, *en*, *es*, *fr*, *nl*. By default the browser language is used.

<add key="EVDesktop_Culture" value="en" />

ActivatePreviewFeatures

Determines whether the client is allowed to use the pre implemented features. <add key="ActivatePreviewFeatures" value="true" />

Note: If the first configuration of security provider is Windows, then the user is able to create an Impersonated Session. When an Impersonated Session is created, the user does not have to enter credentials when logging on to Performance AL Server regardless any other security provider configured after that.

Configuring the REST server

The following section describes how to configure the REST server which is hosted inside the Performance ALServer process.

Configuration parameters

The following configuration parameters can be configured in EVServer.exe.config and are described in chapter <a href="mailto:searchapter-s

- RestApiPortNumber
- RestApiProtocol
- RestApiCorsOrigins

Configuration for SSL

In order to use HTTPS for the communication between the Performance AL Anywhere and the Performance AL REST Server the following steps:

- 1. In Performance AL Server configuration file EVServer.exe.config set the parameter <add key="RestApiProtocol" value="https" />
- 2. In Performance AL Server configuration file EVServer.exe.config set the parameter for the port to e.g.

<add key="RestApiPortNumber" value="443" />

Configuring the mobile device

After the application has been set up and configured in the web server, it can be opened using the following URL in your browser.

http(s)://hostname/EVAnywhere

Hint: If the mobile device you're using is an iOS or Android device, it's recommended to add the application to your home screen.

Windows Integrated Authentication

In order to use Windows Integrated authentication (WIA) and Kerberos authentication the browsers need to be configured as follows:

Chrome

Add the host name of the REST server to the following registry key list:

• Computer\HKEY_LOCAL_MACHINE\SOFTWARE\Policies\Google\Chrome \AuthNegotiateDelegateWhiteList

Firefox

Add the host name of the REST server to the following parameter list (navigate to *about:config*):

- network.negotiate-auth.delegation-uris
- network.negotiate-auth.trusted-uris

If you are not using a full qualified domain name, set the following parameter to *true*:

network.negotiate-auth.allow-non-fqdn

Edge

Ensure that the host name of the REST server is in the **Intranet** or **Trusted sites** list of your browser.

Note: Users will be prompted to enter the credentials for the first time for every new instance of Microsoft Edge.

Functionality

The Anywhere version contains limited functionality that will be enhanced in the future.

It has been designed and implemented to run on multiple devices, such as, desktops, laptops, tablets and smart phones.

The following functionality is available:

- Backstage
 - List Recent and Favorite Views
 - $\circ\,$ List and search Shared Views
 - $\circ\,$ List and search My Views
 - \circ Save
 - \circ Save As
 - \circ Close all
- General menu
 - \circ Undo
 - \circ Redo
 - \circ Reload view
 - \circ Fullscreen mode
- Tables
 - o Select Offspread elements
 - Select Inspread elements
 - Swap dimensions (Offspread and Inspread)
 - \circ Stack Inspread dimensions
 - Sparklines (Display and Create/Edit)
 - o Databars (Display and Create/Edit)
 - Display Grid comments
 - o Display additional member information in tables
- Member Selection
 - Display member name and alias
 - o Search by member name or alias
 - Make asymetrical selections
 - Selection methods
 - Lowest from
 - All lowest
 - Select all
 - Deselect all
 - Expand all
 - Collapse all
 - \circ Change selection order
 - including Predefined orders like the outline order
 - Change chart selection

- $\circ\,$ Quick Navigation via Context Menu
 - Keep Only
 - Remove
 - Drillup/down
 - Include/HideChildren
 - Databar
 - Edit sparkline
- Data Options
 - \circ Suppress rows by null, missing or no access
 - \circ Suppress columns by null, missing or no access
 - \circ Data window
- Layout Options
 - $\,\circ\,$ Display table, chart or both
 - \circ Show or hide title
 - $\circ\,$ Show or hide offspread
- Format Options
 - $\circ\,$ Basic Functionality like "Show Data in Thousands"
- Chart Options
 - $\circ\,$ Most Options are supported
- Client API
 - \circ Refer to the client api documentation for the functionality of the client api (see windows startmenu shortcuts)
- Url API
 - \circ Refer to the url api documentation for the functionality of the url api (see windows startmenu shortcuts)

PowerBI Visual

The Anywhere Client is also provided as a Custom Visual for PowerBI. The PowerBI Visual is available as a download from the Performance AL server under the following url:

http(s)://hostname/ev/PowerBI/ALVisual.pbiviz

Opening the url in a browser allows you to download the file. Downloading the file in Internet Explorer is not supported.

It is recommended to add the Visual to the store of your organization, refer to the Power BI documentation for further details.

Configuration

Custom PowerBI Visuals are designed to run in Sandboxed Iframes. Thus, the Visual does not have an origin and the Performance AL server has to be configured to support the

access from the Visual by setting the RestApiCorsOrigins to a "*".

Limitations

- The Custom Visual offers almost the same functionality as the Anywhere client. However, it doesn't support OAuth2.0 Authentication.
- The Visual is a "private" visual and not certified by the PowerBI AppSource validation team. That certifications requires the Visual not to access any additional resources hence it wouldn't be possible to load additional data from the OLAP database/ Performance AL server. As the Visual is not certified, the *Export to PDF* Functionality is not supported. If you want your PowerBI report printed as a pdf, we recommend to print the report using the *print* functionality and a pdf printer.

Updates

When you upgrade your version of Performance AL, you also need to upgrade the version of the Visual. Most likely, Visuals in older versions will not be compatible to new versions of Performance AL. If you uploaded the Visual to the store of your organization, all you need to do is to upload the new version of the Visual and all existing reports will be updated automatically.

11. Appendix: dataSourceSettings

The **dataSourceSettings** section in the "EVServer.exe.config" file contains specific settings related to the several data source types. You only need to add these settings to the dataSourceSettings section if you want to specify a value other than the default value.

The "EVServer.exe.config" file can by default be found in the folder "C:\Program Files \cubus\Performance Analytics\Server".

For more information see "Editing the configuration file".

The following examples show the elements that can be edited.

TM1

```
<tm1>
 <authenticateUsingWIA>false</authenticateUsingWIA>
 <authenticateUsingWIAExceptions>
   <server name="tmlserver1|sdata" />
   <server name="tmlserver2|planning sample" />
 </authenticateUsingWIAExceptions>
 <allowWIA>false</allowWIA>
 <allowOIDC>false</allowOIDC>
 <isWriteEnabled>true</isWriteEnabled>
 <mdx>
   <compliant>true</compliant>
   <msExtensions>true</msExtensions>
    <evCalculations>true</evCalculations>
   <solveOrderBase>1000</solveOrderBase>
  </mdx>
</tml>
```

MSAS

```
<msas>
  <redirectUriNative>https://login.microsoftonline.com/common/oauth2/
nativeclient</redirectUriNative>
 <ptsTimeOut>30</ptsTimeOut>
  <provider>MSOLAP</provider>
  <allowWIA>true</allowWIA>
  <dimensionsFromOtherPerspectives>true
dimensionsFromOtherPerspectives>
  \langle mdx \rangle
    <compliant>true</compliant>
    <msExtensions>true</msExtensions>
    <evCalculations>true</evCalculations>
    <solveOrderBase>1000</solveOrderBase>
  </mdx>
  <amo>
    <active>true</active>
    <autoReloadCache>true</autoReloadCache>
    <reloadAllOutlinesAfterDimensionProcess>true
      </reloadAllOutlinesAfterDimensionProcess>
    <reloadRoleOutlinesAfterRoleChange>true
reloadRoleOutlinesAfterRoleChange>
```

```
<ttl>5</ttl>
    <servers>
      <server name="servername1.company.com">
        <active>true</active>
        <ttl>5</ttl>
      </server>
      <server name="servername2.company.com">
        <active>true</active>
        <ttl>5</ttl>
      </server>
    </servers>
 </amo>
 <dso>
    <active>true</active>
    <autoReloadCache>true</autoReloadCache>
    <ttl>5</ttl>
    <servers>
      <server name="servername1.company.com">
        <active>true</active>
        <ttl>5</ttl>
      </server>
      <server name="servername2.company.com">
        <active>true</active>
        <ttl>1</ttl>
      </server>
    </servers>
 </dso>
</msas>
```

Essbase

```
<essbase>
  <unicode>true</unicode>
   <nonUnicodeCodePage>1250</nonUnicodeCodePage>
</essbase>
```

mdx

```
<dataSourceSettings>
<mdx>
<useSumForMultiSelect>true</useSumForMultiSelect>
</mdx>
</dataSourceSettings>
```

Data source type TM1

Element <tm1>

This is the parent tag for the TM1 data source related settings. You can use these settings to configure none default behaviour for all, or specific, TM1 data sources.

Filter	Possible values	Default value
<datasourcesettings></datasourcesettings>	n/a	n/a

Element <adminHosts>

If the admin host for configured TM1 servers is running on another URL than http:// [servername]:5895 (which is the default), the connection parameters can be specified using the adminHost> tag. This connection is used to look up the connection information for the configured TM1 servers.

Filter	Possible values	Default value
<tm1></tm1>	n/a	n/a

Example:

```
<adminHosts>
<adminHost name="servername1">
<port>5897</port>
<useSSL>false</useSSL>
</adminHost>
<adminHost name="servername2">
<port>5898</port>
<useSSL>true</useSSL>
</adminHost>
</adminHost>
```

Element <authenticateUsingWIA>

The value set for the <authenticateUsingWIA> tag specifies if Performance Analytics Server uses Windows integrated authentication (WIA) to logon to your TM1 servers. If this tag is set to "true" then WIA will be used for authentication on your TM1 servers. You can specify exceptions with the 'authenticateUsingWIAExceptions' tag.

Filter	Possible values	Default value
<tm1></tm1>	true, false	false

Example:

<authenticateUsingWIA>true</authenticateUsingWIA>

Element <authenticateUsingWIAExceptions>

You can use this tag to specify TM1 servers that are exceptions to the configured authenticateUsingWIA behavior. For example if you have set the value for the <authenticateUsingWIA> tag to "true", you can use the <authenticateUsingWIAExceptions> tag to specify the TM1 servers that Performance AL should not use Windows integrated authentication for. You can specify a server by using the <server>-tag.

Filter Possible values Default value

<tm1></tm1>	n/a	n/a
-------------	-----	-----

Example:

```
<authenticateUsingWIAExceptions>
  <server name="tmladminhost|planning sample" />
</authenticateUsingWIAExceptions>
```

Element <server>

Tag to specify a specific server. The value of this server is specified in the

name-attribute. You can only specify one server in this tag. If you want to specify more than one server you need to add additional server-tags.

Filter	Possible values	Default value
<authenticateusingwia Exceptions></authenticateusingwia 	The value is specified in the name-attribute.	n/a

Name attribute:

The name of the server. The name needs to be specified according the following syntax: <TM1 Admin Host>|<TM1 Server>

<TM1 Admin Host> is the name of the Admin Host for the TM1 Server <TM1 Server> is the name of the TM1 Server

Example:

```
<authenticateUsingWIAExceptions>
  <server name="tmladminhost|sdata" />
  <server name="tmladminhost|planning sample" />
  </authenticateUsingWIAExceptions>
```

Element <allowWIA>

When Performance AL Client has authenticated itself against Performance AL Server using WIA (Windows Integrated Authenticated) or OIDC security provider, then the value set for the <allowWIA> tag specifies if Performance AL Server is allowed to pass the identity of the authenticated client to the TM1 data source server.

Filter	Possible values	Default value
<tm1></tm1>	true,false	false

If set to "true" and if the TM1 data source server is configured for WIA, then Performance AL Server passes the identity of the authenticated client to the TM1 data source server.

If set to "false" and if the TM1 data source server is configured for WIA, then credentials are required to connect to the TM1 data source server. If Performance AL Server is not configured for single sign on, then the user will be asked for credentials.

Example:

<allowWIA>true</allowWIA>

Element <allowOIDC>

This parameter is deprecated and will be ignored.

When Performance AL Client has authenticated itself against Performance AL Server using OIDC security provider, then it is impossible to authenticate user on TM1 level using OIDC Token. The value of the <allowOIDC> tag specifies if Performance AL Server is allowed to create connection using technical credentials and impersonation on TM1 level.

Filter	Possible values	Default value
<tm1></tm1>	true,false	false

If set to "true" and if the TM1 data source server is configured for Basic authentication, then Performance AL Server creates connection using technical credentials and TM1 impersonation.

If set to "false" and if the TM1 data source server is configured for Basic authentication, then credentials are required to connect to the TM1 data source server. The user will be asked for credentials.

Example:

<allowOIDC>true</allowOIDC>

Element <mdx>

This tag is the parent tag for all tags that are related to the MDX settings. These settings determine the way Performance AL creates the MDX-queries.

Filter	Possible values	Default value
<tm1></tm1>	n/a	n/a

Example:

<mdx>

```
<compliant>false</compliant>
<msExtensions>false</msExtensions>
<evCalculations>true</evCalculations>
<solveOrderBase>500</solveOrderBase>
```

</mdx>

Element <compliant>

The <compliant> tag defines if Performance AL uses advanced MDX queries with functions or basic MDX queries without any functions. If the value is set to true then Performance AL uses the advanced MDX queries. If the value is set to false then all the other tags defined within the <mdx> tags do not apply anymore.

Parent tag	Possible values	Default value
<mdx></mdx>	true,false	true

Example:

```
<mdx>
<compliant>false</compliant>
</mdx>
```

Element <msExtensions>

This tag specifies if Performance AL uses the Microsoft specific way to use specific MDX functions.

Parent tag	Possible values	Default value
<mdx></mdx>	true,false	true

Example:

```
<mdx>
```

```
<compliant>true</compliant>
<msExtensions>false</msExtensions>
</mdx>
```

Element <evCalculations>

This tag specifies whether calculations are performed by Performance AL ("false") or by the OLAP server ("true").

Parent tag	Possible values	Default value
<mdx></mdx>	true,false	false

```
<mdx>
<compliant>true</compliant>
<evCalculations>false</evCalculations>
</mdx>
```

Element <solveOrderBase>

The <solveOrderBase> tag specifies the solve order value for the first calculation that is created in a Performance AL view. If the <evCalculations> tag is set to false then the value set to this tag does not apply anymore.

Parent tag	Possible values	Default value
<mdx></mdx>	Any number.	1000

Example:

```
<mdx>
<compliant>true</compliant>
<solveOrderBase>500</solveOrderBase>
</mdx>
```

Element <usePersonalizedDimension>

The <usePersonalizedDimension> tag specifies if members with no-access are added to the member structure or not. If the <usePersonalizedDimension> tag is set to false then all members independent of the access rights are added. The toplevel dimension member is always added..

Filter	Possible values	Default value
<tm1></tm1>	true,false	false

Example:

<usePersonalizedDimension>true</usePersonalizedDimension>

Data source type MSAS

Element <msas>

Tag to specify the dataSourceSettings for your Analysis Services data sources. This tag is required when you want to specify dataSourceSettings for Analysis Services data sources.

Parent tag	Possible values	Default value
<datasourcesettings></datasourcesettings>	n/a	n/a

Element <ptsTimeOut>

The value set for this tag specifies the time-out for the PivotTable service connection to the Analysis Server. If the connection is idle for the number of seconds defined in the value of this tag, then the PTS-connection will be closed.

Parent tag	Possible values	Default value
<msas></msas>	0 - 14400	30

Example:

<ptsTimeOut>**30**</ptsTimeOut>

Element <redirectUriNative>

The redirectUriNative tag defines the redirect URI for mobile and desktop applications to an OAuth 2.0 system, when a non OAuth 2.0 security provider is used (e.g. Essbase).

If an OAuth 2.0 security provider is used this URI is implicitly defined in the security provider and is not required in the <msas> datasource section.

Parent tag	Possible values	Default value
<redirecturinative></redirecturinative>	Any valid native client redirect URI	n/a

Example:

<redirectUriNative>https://login.microsoftonline.com/common/oauth2/ nativeclient</redirectUriNative>

Element <provider>

The <provider> tag can be used to specify the provider for the connection string to the data source.

Parent tag	Possible values	Default value
<msas></msas>	MSOLAP, MSOLAP.6, MSOLAP.7, MSOLAP.8	MSOLAP

- MSOLAP.6 SQL Server 2014
- MSOLAP.7 SQL Server 2016
- MSOLAP.8 SQL Server 2017, 2019

Example:

<provider>MSOLAP</provider>

Element <allowWIA>

The value set for the <allowWIA> tag specifies if Performance AL Server is allowed to pass the identity of the authenticated client to the MSAS data source server.

Parent tag	Possible values	Default value
<msas></msas>	true,false	true

If set to "true", then Performance AL Server passes the identity of the authenticated client to the MSAS data source server.

If set to "false", then credentials are required to connect to the MSAS data source server. If Performance AL Server is not configured for single sign on, then the user will be asked for credentials.

Example:

<allowWIA>true</allowWIA>

Element <allowOIDC>

This parameter is deprecated and will be ignored.

The value set for the <allowOIDC> tag specifies if Performance AL Server is allowed to pass the windows identity of the authenticated client to the MSAS data source server.

Parent tag	Possible values	Default value
<msas></msas>	true,false	true

If set to "true", then Performance AL Server passes the windows identity of the authenticated client to the MSAS data source server.

If set to "false", then credentials are required to connect to the MSAS data source server. The user will be asked for credentials.

Example:

<allowOIDC>true</allowOIDC>

Element < dimensionsFromOtherPerspectives>

The value set for the <dimensionsFromOtherPerspectives> tag specifies if Performance AL Server is allowed to use already loaded in the cache hierarchy members for other perspectives in a catalog. This option works for both multidimensional and tabular mode.

Parent tag	Possible values	Default value
<msas></msas>	true,false	false

If set to "true", then Performance AL Server will not load the whole hierarchy members from MSAS and will reuse already loaded information from other perspectives from the same catalog. It will improve performance when loading a database structure should several perspective be used.

If set to "false", then Performance AL Server will load hierarchy members directly from MSAS for every perspective.

Example:

```
<dimensionsFromOtherPerspectives>true</
dimensionsFromOtherPerspectives>
```

Element <mdx>

This tag is the parent-tag for all tags related to the MDX-settings. These settings determine the way Performance AL creates the MDX-queries.

Parent tag	Possible values	Default value
<msas></msas>	n/a	n/a

Example:

```
<mdx>
<compliant>false</compliant>
<msExtensions>false</msExtensions>
<evCalculations>true</evCalculations>
<solveOrderBase>500</solveOrderBase>
</mdx>
```

Element <compliant>

The <compliant> tag defines if Performance AL uses basic MDX queries without any functions or more advanced MDX queries with functions. If the value is set to true then Performance AL uses the advanced MDX-queries. If the value is set to false then all the other tags defined within the <mdx> tags do not apply anymore.

Parent tag	Possible values	Default value
<mdx></mdx>	true,false	true

```
<mdx>
<compliant>false</compliant>
</mdx>
```

Element <msExtensions>

This tag specifies if Performance AL will use the Microsoft-specific way to use specific MDX functions.

Parent tag	Possible values	Default value
<mdx></mdx>	true,false	true

Example:

```
<mdx>
<compliant>true</compliant>
<msExtensions>false</msExtensions>
</mdx>
```

Element <evCalculations>

This tag specifies whether calculations are performed by Performance AL ("false") or by the OLAP server ("true").

Parent tag	Possible values	Default value
<mdx></mdx>	true,false	true

Example:

```
<mdx>
```

```
<compliant>true</compliant>
  <evCalculations>false</evCalculations>
</mdx>
```

Element <solveOrderBase>

The <solveOrderBase> tag specifies the solve order-value for the first calculation created in a Performance AL view.

Parent tag	Possible values	Default value
<mdx></mdx>	Any number	1000

If the <evCalculations> tag is set to false then the value set to this tag does not apply anymore.

```
<mdx>
<compliant>true</compliant>
<solveOrderBase>500</solveOrderBase>
</mdx>
```

Element <amo>

This tag is the parent-tag for all tags related to the Analysis Management Objects (AMO) settings. These settings determine the way Performance AL handles the AMO-data and caching. The <amo>tag only applies to Microsoft SQL Server 2012 Analysis Services and is the equivalent of the <dso>tag.

Parent tag	Possible values	Default value
<msas></msas>	n/a	n/a

Example:

```
<amo>
  <active>true</active>
  <ttl>5</ttl>
  <autoReloadCache>true</autoReloadCache>
  <servers>
        <server name="server1.company.com">
            <active>true
            <active>true
            <active>true
            <active>true
            <active>true
            <active>(active>
            <ttl>0</ttl>
            </active></active>
            </server>
            </servers>
            </servers>
            </servers>
            </active></active>
            </active></active>
            </servers>
            </ser
```

Element <dso>

This tag is the parent-tag for all tags related to the Decision Supported Objects (DSO) settings. These settings determine the way Performance AL handles the DSO-data and caching.

Parent tag	Possible values	Default value
<msas></msas>	n/a	n/a

The <dso> tag only applies to Microsoft SQL Server Analysis Services 2000 and is the equivalent of the <amo> tag.

```
<dso>
<active>true</active>
<ttl>5</ttl>
<autoReloadCache>true</autoReloadCache>
<servers>
<server name="server1.company.com">
<active>true</active>
<ttl>0</ttl>
</server>
</server>
```

</dso>

Element <servers>

The <servers> tag is the parent tag for all server-specific settings for the AMO or DSO settings. Within this tag you can specify the AMO or DSO settings for specific servers. These settings will override the general settings.

Parent tag	Possible values	Default value
<amo></amo>	n/a	n/a

Example:

```
<amo>
<active>true</active>
<ttl>5</ttl>
<autoReloadCache>true</autoReloadCache>
<servers>
<server name="server1.company.com">
<active>false</active>
</servers>
</servers>
</amo>
```

Element <server>

Tag to specify a specific server. The value of this server is specified in the name attribute.

Parent tag	Possible values	Default value
<servers></servers>	The value is specified in the name-attribute.	n/a

You can only specify one server in this tag. If you want to specify more than one server you need to add additional server tags. The tags specified within this <server> tag only apply to this server and do override the general settings.

Element <active>

The <active> tag specifies if Performance AL will retrieve AMO or DSO-data from the Analysis Server.

Parent tag	Possible values	Default value
<amo>,<dso><server></server></dso></amo>	true,false	true

When this value is set to false, Performance AL will not share memory images of the cube structure between users and loads the cube structure in memory for each user. Therefore it is not recommended to set this value to false.

If the <active> tag is specified within the <server> tag it will only apply to the server defined in this tag, when it is defined within the <amo> or <dso> tag, then it will apply to all servers not defined within the <servers> tag (general setting).

Example:

```
<amo>
<active>true</active>
<ttl>5</ttl>
<autoReloadCache>true</autoReloadCache>
<servers>
<server name="server1.company.com">
<active>true</active>
<ttl>0</ttl>
</server>
</servers>
</servers>
```

Element <ttl>

This tag specifies the duration (time to live) for the cached AMO or DSO data.

Parent tag	Possible values	Default value
<amo>,<dso><server></server></dso></amo>	0 - infinite	5

The value is specified in minutes. When the ttl expires the AMO or DSO data is flagged dirty and needs to be reloaded before any data can be retrieved from Performance AL.

If the value is set to 0, then the cache will never be refreshed.

If the <ttl> tag is specified within the <server> tag it will only apply to the server defined in this tag. When it is defined within the <amo> or <dso>tag, it will apply to all servers not defined within the <servers> tag (general setting).

Example:

Element <autoReloadCache>

The <autoReloadCache> tag specifies if Performance AL will refresh the cached AMO or DSO data at the moment its ttl is expired or at the moment a user requests data. If the value is set to true it will immediately reload the cache after its ttl is expired.

Parent tag	Possible values	Default value
<amo>,<dso></dso></amo>	true,false	false

You cannot specify this setting for a specific server.

Example:

```
<amo>
```

```
<active>true</active>
<ttl>5</ttl>
<autoReloadCache>true</autoReloadCache>
<servers>
<server name="server1.company.com">
<active>true</active>
<ttl>0</ttl>
</server>
</servers>
</amo>
```

Element <reloadAllOutlinesAfterDimensionProcess>

The <reloadAllOutlinesAfterDimensionProcess> tag specifies if Performance AL will refresh the cached outlines (the full outline as well as role specific outlines) after a cube dimension has been processed.

Parent tag	Possible values	Default value
<amo></amo>	true,false	true

After a dimension has been processed, Performance AL needs to refresh the AMO data to get the information about the last processed date. The point in time where the refresh of

the AMO data will happen depends on the <ttl> tag. After this refresh Performance AL will reload the outline at the time it is requested (e.g. when a user opens a view).

This functionality is only available if the <active> tag is true.

You cannot specify this setting for a specific server.

Example:

```
<amo>
<active>true</active>
<reloadAllOutlinesAfterDimensionProcess>true</
reloadAllOutlinesAfterDimensionProcess>
</amo>
```

Element <reloadRoleOutlinesAfterRoleChange>

The <reloadRoleOutlinesAfterRoleChange> tag specifies if Performance AL will refresh a cached role specific outline after this role has been changed.

Parent tag	Possible values	Default value
<amo></amo>	true,false	true

After a role has been changed, Performance AL needs to refresh the AMO data to get the information about the changed role. The point in time where the refresh of the AMO data will happen depends on the <ttl> tag. After this refresh Performance AL will reload the role specific outline at the time it is requested (e.g. when a user opens a view).

This functionality is only available if the <active> tag is true.

You cannot specify this setting for a specific server.

Example:

```
<amo>
<active>true</active>
<reloadRoleOutlinesAfterRoleChange>true</
reloadRoleOutlinesAfterRoleChange>
</amo>
```

Data source type Essbase

<essbase>

Tag to specify the dataSourceSettings for your Essbase Data Sources. This tag is required when you want to specify dataSourceSettings for Essbase Data Sources.

Parent tag	Possible values	Default value
<datasourcesettings< td=""><td>n/a</td><td>n/a</td></datasourcesettings<>	n/a	n/a

<unicode>

This tag specifies if Performance Analytics does use the Unicode- or the non-Unicode mode to connect to Essbase.

Parent tag	Possible values	Default value
<essbase></essbase>	true,false	true

Example:

<unicode>true</unicode>

<nonUnicodeCodePage>

If Performance AL is configured to use the non-Unicode mode to connect to Essbase you need to specify the non-Unicode codepage. The codepage needs to correspond with the value of the ESSLANG-variable set on the Essbase Server. The table below shows the corresponding codepages for the available ESSLANG-values.

Parent tag	Possible values	Default value
<essbase></essbase>	See table below.	n/a

ESSLANG variable	Codepage
Arabic_SaudiArabia.ISO-8859-6@Default	1256
ESSLANG variable	Codepage
Arabic_SaudiArabia.ISO-8859-6@Default	1256
Arabic_SaudiArabia.MS1256@Default	1256
Croatian_Croatia.ISO-8859-2@Croatian	1252
Croatian_Croatia.MS1250@Croatian	1252
CyrillicSerbian_Yugoslavia.ISO-8859- 5@Default	1251
CyrillicSerbian_Yugoslavia.MS1251@Default	1251
Czech_CzechRepublic.ISO-8859-2@Czech	1250
Czech_CzechRepublic.MS1250@Czech	1250
Danish_Denmark.ISO-8859-15@Danish	1252
Danish_Denmark.IBM500@Danish	1252
Danish_Denmark.Latin1@Danish	1252
Danish_Denmark.MS1252@Danish	1252
Dutch_Netherlands.IBM037@Default	1252
Dutch_Netherlands.IBM500@Default	1252

Dutch_Netherlands.ISO-8859-15@Default	1252
Dutch_Netherlands.Latin1@Default	1252
Dutch_Netherlands.MS1252@Default	1252
English_UnitedStates.IBM037@Binary	1252
English_UnitedStates.IBM285@Binary	1252
English_UnitedStates.IBM500@Binary	1252
English_UnitedStates.Latin1@Binary	1252
English_UnitedStates.MS1252@Binary	1252
English_UnitedStates.US-ASCII@Binary	1252
Finnish_Finland.IBM500@Finnish	1252
Finnish_Finland.ISO-8859-15@Finnish	1252
Finnish_Finland.Latin1@Finnish	1252
Finnish_Finland.MS1252@Finnish	1252
French_France.IBM297@Default	1252
French_France.IBM500@Default	1252
French_France.ISO-8859-15@Default	1252
French_France.Latin1@Default	1252
French_France.MS1252@Default	1252
German_Germany.IBM273@Default	1252
German_Germany.IBM500@Default	1252
German_Germany.ISO-8859-15@Default	1252
German_Germany.Latin1@Default	1252
German_Germany.MS1252@Default	1252
Greek_Greece.ISO-8859-7@Default	1253
Greek_Greece.MS1253@Default	1253
Hebrew_Israel.ISO-8859-8@Default	1255
Hebrew_Israel.MS1255@Default	1255
Hungarian_Hungary.ISO-8859-2@Hungarian	1250
Hungarian_Hungary.MS1250@Hungarian	1250
Italian_Italy.IBM280@Default	1252
Italian_Italy.IBM500@Default	1252
Italian_Italy.ISO-8859-15@Default	1252
Italian_Italy.Latin1@Default	1252
Italian_Italy.MS1252@Default	1252
Japanese_Japan.IBM930@Binary	932

Japanese_Japan.JapanEUC@Binary	932
Japanese_Japan.MS932@Binary	932
Korean_Korea.MS1361@Binary	949
Korean_Korea.MS949@Binary	949
Norwegian_Norway.IBM500@Danish	1252
Norwegian_Norway.ISO-8859-10@Danish	1252
Norwegian_Norway.ISO-8859-15@Danish	1252
Norwegian_Norway.ISO-8859-4@Danish	1252
Norwegian_Norway.Latin1@Danish	1252
Norwegian_Norway.MS1252@Danish	1252
Polish_Poland.ISO-8859-2@Polish	1250
Polish_Poland.MS1250@Polish	1250
Portuguese_Portugal.IBM037@Default	1252
Portuguese_Portugal.IBM500@Default	1252
Portuguese_Portugal.ISO-8859-15@Default	1252
Portuguese_Portugal.Latin1@Default	1252
Portuguese_Portugal.MS1252@Default	1252
Romanian_Romania.ISO-8859-2@Romanian	1250
Romanian_Romania.MS1250@Romanian	1250
Russian_Russia. ISO-8859-5@Default	1251
Russian_Russia.MS1251@Default	1251
Serbian_Yugoslavia.ISO-8859-2@Default	1250
Serbian_Yugoslavia.MS1250@Default	1250
SimplifiedChinese_China.IBM935@Binary	936
SimplifiedChinese_China.MS936@Binary	936
SimplifiedChinese_China.UTF-8@Binary	936
Slovak_Slovakia.ISO-8859-2@Slovak	1250
Slovak_Slovakia.MS1250@Slovak	1250
Slovenian_Slovenia.ISO-8859-10@Slovenian	1250
Slovenian_Slovenia.ISO-8859-2@Slovenian	1250
Slovenian_Slovenia.ISO-8859-4@Slovenian	1250
Slovenian_Slovenia.MS1250@Slovenian	1250
Spanish_Spain.IBM500@Spanish	1252
Spanish_Spain.ISO-8859-15@Spanish	1252
Spanish_Spain.Latin1@Spanish	1252

Spanish_Spain.MS1252@Spanish	1252
Swedish_Sweden.IBM500@Swedish	1252
Swedish_Sweden.ISO-8859-15@Swedish	1252
Swedish_Sweden.Latin1@Swedish	1252
Swedish_Sweden.MS1252@Swedish	1252
Thai_Thailand.MS874@Thai	874
TraditionalChinese_Taiwan.EUC-TW@Binary	950
TraditionalChinese_Taiwan.IBM937@Binary	950
TraditionalChinese_Taiwan.MS950@Binary	950
Turkish_Turkey.ISO-8859-3@Turkish	1254
Turkish_Turkey.ISO-8859-9@Turkish	1254
Turkish_Turkey.MS1254@Turkish	1254
Ukrainian_Ukraine.ISO-8859-5@Ukrainian	1251
Ukrainian_Ukraine.MS1251@Ukrainian	1251

Setting type mdx

<mdx>

Tag to specify the dataSourceSettings for mdx specific settings. This tag is required when you want to specify dataSourceSettings for mdx.

Parent tag	Possible values	Default value
<datasourcesettings></datasourcesettings>	n/a	n/a

<useSumForMultiSelect>

This setting, when set to true uses 'Sum' instead of 'Aggregate' in the MDX queries sent to the data source for multi-select offspread members.

SUM() is used instead of AGGREGATE() when a member with a unary operator is defined. It has effect on SSAS and TM1 databases.

Parent tag	Possible values	Default value
<mdx></mdx>	true,false	false

```
<dataSourceSettings>
   <mdx>
        <useSumForMultiSelect>true</useSumForMultiSelect>
        </mdx>
```

</dataSourceSettings>

12. Appendix: Database Specific Configuration

There are different configuration options for the multidimensional databases.

These options can be configured in the Performance AL Explorer as well as in the Desktop Explorer and are described in the following chapter.

Essbase Data Source Settings

When an Essbase Data Source is added, it can be configured for the following items:

Preload Databases

This setting can be set for all Databases at once or for specific Databases. Here you can specify if Performance AL Server should load the Essbase Databases on this Essbase Server automatically at startup. By doing this, users can connect immediately to the database and access its outline and data instantly without delays caused by opening the database.

• Personalize Databases

This setting can be set for all Databases at once or for specific Databases. 'Personalize Databases' allows you to limit the outline of all users according to their access rights within Essbase. According to the filters defined for this user in Essbase, the outline will be stripped of those members to which the user has no read access. Using this feature allows you to hide sensitive information in the outline or to simplify outlines for certain users. It also makes it possible to easily create personal reports.

Remove One Member Dimensions

This setting can be set for all Databases at once or for specific Databases. With this option you can remove dimensions from the outline, when only one member with data remains when a database is personalized. For example, if the Essbase filter only allows a user to see 'New York', the 'Market' dimension will be completely hidden.

• Retain Structure Using Labels

This setting can be set for all Databases at once or for specific Databases. When only members on a lower level are accessible when a Database is personalized, members on a higher level disappear. This changes the structure of the outline. If this behavior is not desirable, use this option to have Executive Viewer Server insert those members again as a label. The user still has the original structure to work with, but does not see data from these members.

• Add Substitution Members

This setting can be set for all Databases at once or for specific Databases. An Essbase Substitution Variable is a global variable you can set that applies for the entire Database. These Substitution Variables can be treated as a member of the dimension for which they are defined. By enabling this option, the Substitution Variables will be added to the outline as Substitution Members.

• Enable drillthrough

This setting can be set for all Databases at once or for specific Databases. If it is enabled an XML Outline is generated for the database that is used to provide the context for drillthrough. Note that Preloading needs to be enabled to allow drillthrough.

• REST API Endpoint

This setting can only be set for all Databases at once and is only valid for Datasources using Oracle Essbase 21.3 or higher. It defines the endpoint that is used to connect to the Essbase REST API. One example would be: https://essbase-server.local:9001.

Essbase Database Settings

For each Essbase Database Item it is possible to set the one of the following options:

- Preload
- Personalize
- Personalized Dimensions
- Remove One Member Dimensions
- Retain Structure Using Labels
- Add Substitution Members

See the previous section for an explanation of these options. The option 'Personalized Dimensions' is explained in this section.

Personalized Dimensions

It is possible to specify dimensions that should not be personalized if the 'Personalize' option is checked, or specify the Dimensions that should be personalized, if the 'Personalize' option is not checked.

When specifying dimensions in the 'Personalized Dimensions' field while the 'Personalize' option is not checked, only these dimensions will be limited to users according to their access rights within Essbase. The dimensions that are not specified will show without any restrictions applied. This means members that the user has no access to in these dimensions, will show as 'no access'. The dimension names can be entered in the 'Personalized Dimensions' field, separated by a semi-colon.

Example: Year; Product; Market

• Enable drillthrough

If drillthrough is enabled an XML Outline is generated for the database that is used to provide the context for drillthrough. Note that Preloading needs to be enabled to allow drillthrough.

TM1 Data Source Settings

When a Cognos TM1 Data Source is added, it can be configured for the following items:

• Preload Cubes

This setting can be set for all Databases at once or for specific Databases. Here you can specify if Performance AL Server should load the TM1 Databases on this TM1 Server automatically at startup. By doing this, users can connect immediately to the database and access its outline and data instantly without delays caused by opening the database.

• Provider Specific

This setting can be set for all Databases at once or for specific Databases. Click on 'Add' to add a Provider Specific setting. Specific OLE DB Properties can be set here. For a complete overview of the Properties available, consult the TM1 Documentation about OLE DB Properties. By default, no Properties are added here. It is recommended when connecting to a TM1 Server to leave this field empty. We advise you to contact our support team if you want to add Properties.

• Preload Roles/Users

This setting can be set for all Databases at once or for specific Databases. This setting only applies to the cubes, that are preloaded. With this option you can preload the users defined for a cube. When, for example, the cube with the dimension 'Market' is preloaded and a user with a role for only dimension 'East' is defined, this outline will be loaded when the option 'Preload Roles/Users' is checked.

Note: For MSAS, roles can be preloaded. For TM1, users can be preloaded.

TM1 Database Settings

For each TM1 Database Item it is possible to set the one of the following options:

- Preload
- Default Hierarchies

See the previous section for an explanation of the Preload option.

• Preload Roles/Users exceptions

It is possible to specify for each Database the Users that should not be preloaded if the 'Preload Roles/Users' option is checked, or specify the Users that should be preloaded, if the 'Preload Roles/Users' option is not checked.

These Users names can be entered in the 'Preload Roles/Users exceptions' field, separated by a semi-colon.

Example: User1;User2

• Default Hierarchies

It is possible to specify for each Database the default hierarchy that Performance AL will use for initial selections while creating new views.

This is a case sensitive parameter and only dimensions and hierarchies with an exact match will be applied.

If the hierarchy does not exist, the database default hierarchy will be applied as the default hierarchy.

Default hierarchies can be entered into the 'Default Hierarchies field. Only one

dimension and hierarchy can be entered per line.

The unique dimension name and unique hierarchy name needs to be specified separated with an equals (=) character.

Example:

[UniqueDimensionName]=[UniqueDimensionName].[UniqueHierarchyName]

[Market]=[Market].[Population] [Product]=[Product].[Size]

MSAS Data Source Settings

When a MS Analysis Services server Data Source is added, this server can be configured for the

following items:

• OAuth 2.0

The OAuth 2.0 authentication scheme can be used for MSAS data sources. In order to use this type of authentication, the following configurations have to be set.

• Authorization Endpoint

This is the full HTTPS URL to the **OAuth 2.0 Authorization Endpoint (v2)**. It must exactly match the OAuth 2.0 Authorization Endpoint (v2) of the application which is registered in the portal. On the Microsoft Azure portal it can be found under the path **Home > Azure Active Directory > App registrations > Endpoints**

Example for Microsoft Azure: https://login.microsoftonline.com/<TentantId>/ oauth2/v2.0/authorize

• Token Endpoint

This is the full HTTPS URL to the **OAuth 2.0 Token Endpoint (v2)**. It must exactly match the OAuth 2.0 Token Endpoint (v2) of the application which is registered in the portal. On the Microsoft Azure portal it can be found under the path **Home > Azure Active Directory > App registrations > Endpoints**

Example for Microsoft Azure: <u>https://login.microsoftonline.com/<TentantId>/</u> oauth2/v2.0/token

• Logout Endpoint

This is the full HTTPS URL to the OAuth 2.0 Logout Endpoint (v2).

Example for Microsoft Azure: <u>https://login.microsoftonline.com/<TentantId>/</u> oauth2/v2.0/logout

• Server Name

The server name can be found in your portal inside the current Permissions (see parameter description below).

By opening the menu Home > All resources > YourAnalysisServicesResourceName > Overview the Server name can be found in a format asazure:// YourAzureServerLocation.asazure.windows.net/YourResourceName

Use that information to create an URI as follows: https:// yourAzureServerLocation.asazure.windows.net The YourAnalysisServicesResourceName is the name of your Analysis Services resource.

Example for Microsoft Azure: https://westeurope.asazure.windows.net

• Application ID

When defining the application in the **App registrations** section of the portal, an **Application (client) ID** is defined. This needs to be inserted here.

It can be found under **Home > Azure Active Directory > App registrations**.

• Permission

This is the the API permission of the service, that is used. In the Microsoft Azure portal it can be found in the API permissions section of the application.

It can be found under Home > Azure Active Directory > App registrations > yourApp > API permissions.

Example for Azure Analysis Services: Model.ReadWrite.All

Client secret

This is a secret string that the application uses to prove its identity when requesting a token.

Note: default **Integrated Security** value is **false.** All other values will be ignored if **Integrated Security** will be added explicitly in the **Provider Specific Properties** section in the data source configuration panel. When OAuth 2.0 is configured, **Integrated Security** does not require a definition. To find more read <u>Impersonation</u> chapter.

Further configuration steps are described in

- Preparing Microsoft Azure
- Specifying the security providers
- Configuring the OAuth2 Security Provider

• Preload Cubes

This setting can be set for all Databases at once or for specific Databases. You can specify if Performance AL Server should load the MS Analysis Services cubes automatically at startup. By doing this, users can connect immediately to the cube and access its outline and data instantly without delays caused by opening the cube.

• Provider Specific

- When adding a MS Analysis Services Data Source it is possible to specify PivotTable Service Properties in the 'Provider Specific' field, for example, the 'Client Cache Size Property'.

Note: For a complete overview of the Properties available, consult the Microsoft Documentation about 'PivotTable Service Properties'.

By default, no Properties are added here. It is recommended when connecting to a MS Analysis Server to leave this field empty. We advise you to contact our support team if you want to add items.

Performance AL Server uses several of the Properties available, such as the 'Roles' Property or the 'MDX Compatibility' Property. The Properties already in use by

Performance AL Server may not be specified here.

When specifying Properties, you have to use the Property Name, exactly as specified in the Microsoft documentation. Note that this is case-sensitive.

You can enter multiple Properties by clicking on 'Add'. Specify the name and the value and click on 'Update'.

A PivotTable Service Property is passed on to all connections from Executive Viewer Server to MS Analysis Services.

 If it is impossible to use Windows integrated authentication with MS Analysis Services Data Source, you should specify a 'integrated security' property and set it to 'false'. Consult the Microsoft Documentation about Integrated Security to connect to data sources that support it. Note that default value for 'integrated security' is 'sspi'.

• Interpret Roles

This setting can be set for all Databases at once or for specific Databases. If this option is checked, Performance AL Server checks which users and groups belong to a role. For the first user to log on, the outline is loaded. If other users connect who belong to the same role, the outline is reused. If this option is not checked, the outline gets loaded for each individual user.

• Preload Roles/Users

This setting can be set for all Databases at once or for specific Databases. This setting only applies to the cubes, that are preloaded, and to Roles which are interpreted. With this option you can preload the roles defined for a cube. When, for example, the cube with the dimension 'Market' is preloaded and a role for only dimension 'East' is defined, this outline will be loaded when the option 'Preload Roles/Users' is checked.

Note: For MSAS, roles can be preloaded. For TM1, users can be preloaded.

MSAS Database Settings

For each MS Analysis Services Database Item it is possible to set the one of the following options:

- Preload
- Interpret Roles
- Interpret Roles exceptions
- Preload Roles/Users
- Preload Roles/Users exceptions

See the previous section for an explanation of these options. The options 'Interpret Roles exceptions', 'Preload Roles exceptions' and 'Default Hierarchies' are explained in this section.

• Interpret Roles exceptions

It is possible to specify for each Database the Roles that should not be interpreted if the 'Interpret Roles' options is checked, or specify the Roles that should be interpreted, if the 'Interpret Roles' option is not checked.

These Roles names can be entered in the 'Interpret Roles exceptions' field, separated by a semi-colon.

Example: DemoRole;SampleRole

• Preload Roles/Users exceptions

It is possible to specify for each Database the Roles that should not be preloaded if the 'Preload Roles/Users' option is checked, or specify the Roles that should be preloaded, if the 'Preload Roles/Users' option is not checked.

These Roles names can be entered in the 'Preload Roles/Users exceptions' field, separated by a semi-colon.

Example: *DemoRole;SampleRole*

Note: If a user has multiple roles assigned in MSAS (e.g. Role1 and Role2), the outline for this user is not loaded when the 'Preload Roles' option is checked. In order to preload outlines for users with multiple roles, these role combinations have to be entered in the 'Preload Roles exceptions' field, separated by a comma, while the 'Preload Roles' option is unchecked.

Example: *DemoRole;SampleRole;Role1,Role2*

• Default Hierarchies

It is possible to specify for each Database the default hierarchy that Performance AL will use for initial selections while creating new views.

This is a case sensitive parameter and only dimensions and hierarchies with an exact match will be applied.

If the hierarchy does not exist, the database default hierarchy will be applied as the default hierarchy.

Default hierarchies can be entered into the 'Default Hierarchies field. Only one dimension and hierarchy can be entered per line.

The unique dimension name and unique hierarchy name needs to be specified separated with an equals (=) character.

Example:

[UniqueDimensionName]=[UniqueDimensionName].[UniqueHierarchyName]

[Market]=[Market].[Population] [Product]=[Product].[Size]

13. Appendix: Preloading

Preloading process can be used to reduce waiting time to open a view. If preloading is activated, the server will load outline (database structure) in cache automatically at startup. By doing this, users can connect immediately to the cube and access its outline and data instantly without delays caused by opening the cube.

Preloading process contains two parts: preloading full outline and preloading restricted outlines. It is possible to manage preloading using **Preload** and **Preload roles/users** in a datasource or database settings.

Preload activates preloading full outline without restrictions. **Preload roles/users** activates preloading restricted outlines for different users.

The preload process starts:

- 1. If preloading is activated right after the server start. The full outline will be loaded to the cache.
- 2. After an user logs in preloading starts according to the preloading settings. If the user is the first the user's outline will be loaded first then full outline.
- 3. An user with administrator rights can force a preload using <u>forcePreloading</u> if e.g. database structure has been changed.

If Preload roles/users is activated, Performance AL starts preloading restricted outlines after the full outline has been loaded. While preloading, each dimension will be checked if it has restriction. If not - the dimension will be reused from the full outline.

When user logs in the system will check first if his outline is in cache. Timestamps that show when the database structure was changed will be compared with the outline in the cache and with the database. The user will get his outline if it is already loaded and up to date. The preloading process will be triggered to find outdated outlines and update them according to the preloading settings.

Preloading may take some time until all the outlines where this option is enabled are loaded. If you have a lot of roles/user but not all of them use Performance AL every day it makes sense to activate preloading the full outline only. It can save time until the system will be ready. You can configure different preloading options to get the desired result, suitable for your environment. It is possible to manage preloading process using Parallel Preloading for databases and users. Check **ParallelPreload**, **RetryDatabasePreload** and **UseCurrentOutlineWhilePreloading** keys in <u>Configure_the service and the configuration file</u> chapter. Using parallelization can reduce the time for preloading, but it can increase the load on the processor. Also using **Preload Roles/Users exceptions** field to manage preloading process for specific users or roles can help to avoid unnecessary preloading for users who uses Performance AL on a case-by-case basis. The best way is to check and choose the option that is better for your case.

• MSAS

MSAS provides roles concept to define restrictions for different users. It means different users can have the same role and same restrictions. It make sence to activate **Interpret Roles** flag to save memory required for the cache and preloading time when different users with the same role can use the same outline.

If you use Dynamic security when the restrictions depend not only on the role but also on the user name you should not activate Interpret Roles otherwise user can get wrong restrictions. In this case user specific outlines will be loaded for each user. **Interpret Roles exceptions** field helps to combine classical roles and roles with dynamic security. Check <u>MSAS Data Source Settings</u> chapter to read about Interpret Roles.

Information about restrictions in a dimension will come directly from MSAMO. While preloading, each restricted dimension will be checked if it has been loaded already for another perspective for this role. If yes, the dimension will be reused. It can save additional time and memory.

• TM1

TM1 provides restrictions on a group level that means it is impossible to have personal users outline and outline will be loaded for all users from the same group (the same meaning as a role in MSAS).

Information about user restrictions in a dimension will be available by comparing number of available members for 'administrator' and 'user' connections.

• LOG


You can track the full preloading process in Performance AL log file with Debug log level. All entries related to the preloading have the category Preloading. The first message when preload starts is "Preloading database". The last is "Preloading Database succeeded." or "Preloading Database failed".

Preloading users/roles process has messages: "Loading user" or "Loading role", "Loading user succeeded" or "Loading role succeeded", "Loading user failed" or "Loading role failed".


If parallel preloading is used, it can be helpful to use a thread parameter to filter out the thread and check preloading for the certain user or role.

• Examples of preload schemes


1. This scheme describes process if preload and preload users/roles are activated, Interpret Roles flag is deactivated. Valid only for MSAS.



2. This example shows scenario with activated Interpret Roles for MSAS. Valid for MSAS and TM1.



3. The next scheme describes what hapens if preload users/roles is disabled. Interpret Roles is activated. Valid for MSAS and TM1.



14. Appendix: Impersonation

This part explains the impersonation mechanism in Performance Analytics.

Impersonation is a way to create user specific connections to the database. Impersonation allows to get all user's restrictions without using his password. It is can be used in case of preloading users or if some external security provider is used to authenticate users and Performance AL has no access to the real user's credentials. Such an authentication provider can be <u>OIDC security provider</u>. Performance AL has used impersonation on system level to impersonate a user with his windows identity before. Beginning with the version 9.1.0 impersonation is used on the database level for MSAS and TM1.

Impersonation workflow in Performance AL has been changed to realize or improve the following features:

- preload user outlines for MSAS;
- provide mapping between OIDC security provider and the database layer without using current Windows user;
- subscriptions with restrictions applied propperly if OIDC is used as security provider.
- MSAS

Integrated security parameter in connection string defines if the Windows identity of the caller is used to connect to Analysis Services. That means that connection user credentials defined in the datasource settings will be used to create a database connection. You don't need to set Integrated security explicitly for Azure databases in provider specific parameters. If you define another value for *Integrated security* with Azure databases it will be ignored.

Note: If the Impersonation does not work in your environment you may need to set Integrated Security = false explicitly in the provider specific settings of the Analysis services datasource.

Impersonation is activated by parameters **EffectiveUserName** or **Roles** in the connection string.

If you use Profiling to analyze connections to the database you will see that all connections to the database will be made using a connection user from the datasource settings.

Additional information can be found in the Session Initialize data. If impersonated connection was created this will be role name and EffectiveUserName or Roles attributes in the PropertyList for the connection.

If impersonated user does not exist or has no access to the database the connection can not be established. This eliminates the situation when a windows user cannot be impersonated for some reasons and gets full access to the database.

• TM1

TM1 supports 3 different ways to authenticate a user. These are Basic, Windows and CAM authentication mechanisms. TM1 uses REST API therefore TM1 Impersonation is possible during a database connection creation using TM1-Impersonate HTTP header

with the value:

- TM1 user name for Basic authentication (IntegratedSecurityMode = 1)
- Windows user name or corresponding to it TM1 user name for IntegratedSecurityMode = 3
- CAMID for IntegratedSecurityMode = 4

A connection to the TM1 database will be created using connection user from the datasource settings. If impersonated user does not exist or has no access to the database the connection can not be established.

• Essbase

Impersonation is not supported for Oracle Essbase. If an user can not be authenticated using the security provider he will get a database login dialog to enter credentials.

If OIDC is used as security provider the mapping of user names between OIDC server and the database should be correctly <u>configured</u>. The 'database_user' attribute has to be added in OIDC user settings. The value depends on what authentication mechanisms has been selected for the database.

- For **Basic** authentication **user name** has to be used as the value.
- For Windows authentication DOMAIN\USERNAME.
- For TM1 CAM security CAMNAMESPACE/USERNAME.

Pay attention to the correct use of \ and / symbols.

15. Appendix: Essbase Drill Through

This part describes Essbase Drill Through and its restrictions in Performance Analytics.

Drill Through report shows external data from one or more Essbase cell intersections and provides additional information not contained in the Essbase cube.

In order to turn on this functionality, "Enable drillthrough" setting needs to be switched on for Database and "REST API Endpoint" has to be specified. More about these settings can be found in the following chapters: <u>Essbase_Data_Source_Settings</u> and <u>Essbase_Database Settings</u>

Drill Through in Performance Analytics is supported for Datasources using Oracle Essbase 21.4 or greater.

When a Drill Through script is created, at least one Drillable Region should be defined. It consist of combination of members and/or calls of Essbase Member-Set functions. The functions, which are supported by Performance Analytics can be found below:

Supported Member-Set Functions
@LEVMBRS
@IANCESTORS
@ANCESTORS
@SIBLINGS
@LSIBLINGS
@RSIBLINGS
@DESCENDANTS
@IDESCENDANTS
@CHILDREN

Limitations:

- Calling a function from another function (e.g. @CHILDREN(@SIBLINGS(Jan))) is not supported
- For all members, which are defined in Drillable Regons, '(', ')' and ',' are not allowed to be part of the member's name.

16. Appendix: Tools

This chapter describes the tools that come with Performance Analytics.

EVCreateReport

The EVCreateReport tool can be used to generate PDF and Excel documents from Performance AL views.

It can be found in the <Install_Dir>/Server/Tools/EVCreateReport directory.

The tool creates a log file with the name: EVCreateReport_<DAY><MONTH><YEAR>.log

The following parameters are used:

Opt ion	Parameter	Requir ed	Description	Example
-S	EVSERVER	Yes	The host name of the machine where the Performance AL Server is running. It's also possible to include a port number in the host name.	
-u	USER	Yes (If WIA is not used)	The name of the identity that is used to open the report.	-u admin
-p	PASSWOR D	-	The password of the identity that is used to open the report. It can either be send in clear text or as an encrypted string. For encryption use the tool <install_dir>/Server/ Tools/EncryptConsole/ EncryptConsole.exe</install_dir>	-p password
-v	VIEWNAM E	Yes	The name of the view (starting with / and including the full path) for which the document is created. Multiple views can be passed.	
-f	OUTPUTFI LE	Yes	The name of the document that is created.	-f "c:\temp\My Report.pdf"
 the me	THEME	No	The name of the theme that will be used for the report. For valid values refer to the chapter Theme settings in the	theme Classic

			User Guide.	
 wia		No	Use Windows Integrated Authentication. No user and password is required. The identity of the user executing the program is used.	wia
-е	FILETYPE	Νο	The type of file with which the document is created. Valid values are: - PDF (default) - EXCEL	-e EXCEL
-t	TITLE	No	The titel of the frontpage in a PDF document. Parameter -I <i>Frontpage</i> must be passed in order to print the title on the frontpage.	-t "Sales Report Q1"
-0	OFFGRIDD IMENSION OFFGRIDM EMBER	No	The member of an offgrid dimension in the view can be selected.	-o Market Region01
-or	ORIENTATI ON	Νο	The orientation of the document paper. Valid values are: - Landscape (default) - Portrait	-or Portrait
-1	тос	No	Print the table of contents.	-I TOC
-1	Header	No	Print page headers and footers. (PDF only)	-l Header
-1	Frontpage	No	Print a frontpage in the document (PDF only). Titel can be defined with parameter -t <i>Title</i> .	-l Frontpage
-1	PrintRang e	No	Use the print range that is defined in the view. If parameter -pf <i><printrangefile></printrangefile></i> is used in addition, then the print range from the <i><</i> PRINTRANGEFILE> is used.	-l PrintRange
-pf	PRINTRAN GEFILE	No	Use the print range from the <printrangefile>. This needs to be an JSON file containing the name of the view and the</printrangefile>	

			<pre>corresponding PrintRange. Example: [{ "Name": "/View1", "PrintRange": { "Dimensions": [{ "Dimension": "Product", "Members": [{ "Name": "100" }, { "Name": "300" }</pre>	
			<pre>]}, { "Dimension": "Market", "Members": [{ "Name": "RegGrp01" }, { "Name": "RegGrp02" }]} }</pre>	
-tl	Table LineStyle	No	Define linestyle of the table of content. Valid values are: - none - dot (default) - dash - thin	-tl dash
-im	Image Name	No	Include an image on the frontpage. The image must locate inside the "Images" directory of the server. Note: If the image doesn't have a file extension in its name then it must not be added to the argument here.	
- imh	Horizontal Image Alignment	No	Define the horizontal alignment of the frontpage image. Valid values are: - left - center - right (default)	-imh center
- imv	Vertical Image Alignment	No	Define the vertical alignment of the frontpage image. Valid values are: - top (default) - center	-imv center

			- bottom	
-th	Horizontal Title Alignment	No	Define the horizontal alignment of the frontpage title. Valid values are: - left (default) - center - right	-th center
-tv	Vertical Title Alignment	No	Define the vertical alignment of the frontpage title. Valid values are: - top (default) - center - bottom	-tv center
-db	Database Info	No	Show/hide database connection info for excel export. Valid values are: - on (default) - off	-db on
- cha rtUr I	Chart URL	No	Set chart URL.	-chartUrl http(s):// <server>/EVServer/UI/ chart.html</server>

UserManagement

Users in Performance AL can be managed using the UserManagement console application. The UserManagement console can be found in the tools directory after the installation, for example:

<Install_Dir>/Server/Tools/UserManagement

The UserManagement console has the following parameters. Please note the parameters are passed using double hyphen (except -h and -?).

- --help/-h/-?
 Display help message (optional)
- --EVServer The Performance AL server name. (optional)
- --Authentication Security provider Windows, WindowsForms or Essbase (required)
- --EVUser The connection username that is used to create the user. (required)

- --EVPassword The connection password that is used to create the user. (required)
- --EssbaseServer The Essbase server. If Essbase is being used as a security provider, the user can also be created automatically in Essbase. (optional)

Only one of the following arguments can be passed:

- --Add <UserName> Adds a user to the specified server.
- --Delete <UserName> Deletes the user from the specified server.
- --Update Creates or updates a CubusEV user on essbase based on an existing user. If you use the --Update parameter, then the --EssbaseServer parameter must be also set.
 Note: The CubusEV user will be overwritten, including all access rights.
- --List

Lists all users configured for the specified server.

Creating Users

Users can be created in Performance AL by executing the UserManagement console in the following way.

UserManagement	EVServer ServerNameEVUser ConnectionUserName
	EVPassword PasswordAuthentication SecurityProvider
	Add NewUserName

To create the user on the Performance AL server and in Essbase.

UserManagement --EVServer ServerName --EVUser ConnectionUserName --EVPassword Password --Authentication SecurityProvider --Add NewUserName --EssbaseServer EssbaseServerName

Note: The user access rights still need to be set after the user has been created in Essbase. It may be that the user has no access to the required databases.

Deleting Users

Users can be deleted in Performance AL by executing the UserManagement console in the following way.

```
UserManagement --EVServer ServerName --EVUser ConnectionUserName
--EVPassword Password --Authentication SecurityProvider
--Delete DeleteUserName
```

To delete the user on the Performance AL server and in Essbase.

UserManagement -- EVServer ServerName -- EVUser ConnectionUserName

```
--EVPassword Password --Authentication SecurityProvider
--Delete DeleteUserName --EssbaseServer EssbaseServerName
```

Listing Users

All configured users can be displayed using the UserManagement console in the following way.

```
UserManagement --EVServer ServerName --EVUser ConnectionUserName
--EVPassword Password --Authentication SecurityProvider --List
```

EncryptConsole

The EncryptConsole tool is used to encrypt the password for <u>EVCreateReport</u>. It can be found in <Install_Dir>/Server/Tools/EncryptConsole directory.

Opt ion	Parameter	Requir ed	Description	Example
-h		No	Displays help messages.	-h
-t	TEXT	Yes (If -i is not used)	The text that should be encrypted.	-t test
-i	FILE	Yes (If -t is not used)	The file that should be encrypted.	-i C:\Temp\test.txt
-0	FILE	No	If this is enabled and set to a valid file path the encrypted output will be writted to the file.	-t test -o output.txt
-k	KEY	No	This setting allows the user to specify a different key for encryption. If it not set the default key for Performance will be used.	-t test -k test2

The following parameters are used:

17. Appendix: Migration

This chapter describes migration tasks that need to be manually run by the administrator.

Performance AL 9.0.2 to 9.1.0

Due to Deprecation of the **unique_name** User Attribute as user name when using Performance AL with Keycloak authentication the following tasks have to be done:

- 1. The **unique_name** Mapper in the **Mappers** tab of your Performance AL application should be removed.
- 2. The **unique_name** Attribute should be removed from all users where it was defined. This can be done under the **Attributes** tab while selecting a user in the Keycloak user administration.
- 3. The **database_user** Mapper needs to be added when using impersonation. See <u>Preparing Keycloak</u> for instructions.

Performance AL 9.1.0 to 9.2.0

Due to an added system permission ("Manage Subscriptions") which is added to prepare the management of subscriptions, the webservice definition changed.

If you have a custom implemention/external program working with the Performance AL SOAP webservice, you have to update your webservice reference to ensure everything works as expected.

Please refer to the Server API Reference for more details on the webservice.

18. Notices

This information was developed for products and services offered worldwide.

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law: cubus AG PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. cubus AG may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-cubus Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this cubus product and use of those Web sites is at your own risk.

cubus may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Any performance data contained herein was determined in a controlled environment. Therefore, the results obtained in other operating environments may vary significantly. Some measurements may have been made on development-level systems and there is no guarantee that these measurements will be the same on generally available systems. Furthermore, some measurements may have been estimated through extrapolation. Actual results may vary. Users of this document should verify the applicable data for their specific environment.

Information concerning non-cubus products was obtained from the suppliers of those products, their published announcements or other publicly available sources. cubus has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-cubus products. Questions on the capabilities of non-cubus products should be addressed to the suppliers of those products.

All statements regarding cubus's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

If you are viewing this information softcopy, the photographs and color illustrations may not appear.

19. Trademarks

IBM, the IBM logo, ibm.com, TM1, and Cognos are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the Web at "Copyright and trademark information" at www.ibm.com/legal/ copytrade.shtml.

The following terms are trademarks or registered trademarks of other companies:

- Adobe, the Adobe logo, PostScript, and the PostScript logo are either registered trademarks or trademarks of Adobe Systems Incorporated in the United States, and/ or other countries.
- Microsoft, Windows, Windows NT, and the Windows logo are trademarks of Microsoft Corporation in the United States, other countries, or both.
- Java and all Java-based trademarks and logos are trademarks or registered trademarks of Oracle and/or its affiliates.

20. Licenses

Performance AL incorporates the following third party software components whose licenses require us to publish copies of the licensing language and/or copyright notices. In compliance with those requirements, here are copies of the licenses.

CURL

COPYRIGHT AND PERMISSION NOTICE

Copyright (c) 1996 - 2014, Daniel Stenberg, <daniel@haxx.se>.

All rights reserved.

Permission to use, copy, modify, and distribute this software for any purpose with or without fee is hereby granted, provided that the above copyright notice and this permission notice appear in all copies.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT OF THIRD PARTY RIGHTS. IN

NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Except as contained in this notice, the name of a copyright holder shall not be used in advertising or otherwise to promote the sale, use or other dealings in this Software without prior written authorization of the copyright holder.

JsonCpp

The JsonCpp library's source code, including accompanying documentation, tests and demonstration applications, are licensed under the following conditions...

The author (Baptiste Lepilleur) explicitly disclaims copyright in all jurisdictions which recognize such a disclaimer. In such jurisdictions, this software is released into the Public Domain.

In jurisdictions which do not recognize Public Domain property (e.g. Germany as of 2010), this software is Copyright (c) 2007-2010 by Baptiste Lepilleur, and is

released under the terms of the MIT License (see below).

In jurisdictions which recognize Public Domain property, the user of this software may choose to accept it either as 1) Public Domain, 2) under the conditions of the MIT License (see below), or 3) under the terms of dual Public Domain/MIT License conditions described here, as they choose.

The MIT License is about as close to Public Domain as a license can get, and is described in clear, concise terms at:

http://en.wikipedia.org/wiki/MIT_License

The full text of the MIT License follows:

Copyright (c) 2007-2010 Baptiste Lepilleur

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

(END LICENSE TEXT)

The MIT license is compatible with both the GPL and commercial software, affording one all of the rights of Public Domain with the

minor nuisance of being required to keep the above copyright notice and license text in the source code. Note also that by accepting the Public Domain "license" you can re-license your copy using whatever license you like.

LibXL

END USER LICENSE AGREEMENT FOR LIBXL

This End-User License Agreement ("EULA") is a legal agreement between you and XLware for the LibXL product which may include associated software components, media, printed materials, and "online" electronic documentation ("SOFTWARE PRODUCT").

You agree to be bound by the terms of this EULA by using the SOFTWARE PRODUCT. If you do not agree, do not use it.

1. COPYRIGHT

All rights, title, inerests in and to copyrights in the SOFTWARE PRODUCT are owned exclusively (or licensed) by XLware. The SOFTWARE PRODUCT is protected by copyright laws and international copyright treaties, as well as other intellectual property laws and treaties. The SOFTWARE PRODUCT is licensed, not sold.

2. GRANT OF LICENSE

XLware grants Customer the following rights:

a. Customer is granted the non-transferable, non-exclusive, and perpetual right to integrate the SOFTWARE PRODUCT in their software products, to use these products in their own company and to distribute these products under their own trade name.

b. License fee is based on the number of developers that will use the Application Programming Interface provided by this library. The total number of development workplaces is taken into account, while the number of computers is irrelevant. A single developer or a number of developers in an organization, in accordance with the purchased license, may use the SOFTWARE PRODUCT in any software development process.

c. License fee can be fixed for Enterprise licenses. In this case, any developer within a company may use the SOFTWARE PRODUCT in any software development process inside company. The total number of development workplaces and number of computers inside an organization are irrelevant.

d. Apart from the per-developer or the fixed license fee, Customer is NOT required to pay any additional distribution, runtime, royalty, or per-end-user license fees.

e. Customer may make copies of the SOFTWARE PRODUCT as may be necessary for backup and archival purposes.

3. RESTRICTIONS

a. Customer may not disassemble, decomplile, reverse engineer the SOFTWARE PRODUCT.

b. Customer may not transfer, modify, sell, lease or sublicense the SOFTWARE PRODUCT.

4. TERMINATION

Without prejudice to any other rights, XLware may terminate this EULA if Customer fails to comply with the terms and conditions of this EULA. In such event, Customer must destroy all copies of the SOFTWARE PRODUCT in your possession.

5. NO WARRANTIES

XLware expressly disclaims any warranty for the SOFTWARE PRODUCT. LibXL is provided "As Is" without any express or implied warranty of any kind, including but not limited to any warranties of merchantability, noninfringement, or fitness of a particular purpose. XLware does not warrant or assume responsibility for the accuracy or completeness of any information, text, algorithms, graphics, links or other items contained within this software product. XLware will not be liable for data loss, damages, loss of profits or any other kind of loss while using or misusing this library.

google-sparsehash license

Copyright (c) 2005, Google Inc. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

* Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.

* Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

* Neither the name of Google Inc. nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

RSA Data Security, Inc., MD4 message-digest algorithm

Copyright (C) 1990-2, RSA Data Security, Inc. All rights reserved.

License to copy and use this software is granted provided that it is identified as the "RSA Data Security, Inc. MD4 Message-Digest Algorithm" in all material mentioning or referencing this software or this function.

License is also granted to make and use derivative works provided that such works are identified as "derived from the RSA Data Security, Inc. MD4 Message-Digest Algorithm" in all material mentioning or referencing the derived work.

RSA Data Security, Inc. makes no representations concerning either the merchantability of this software or the suitability of this software for any particular purpose. It is provided "as is" without express or implied warranty of any kind.

These notices must be retained in any copies of any part of this documentation and/or software.

RSA Data Security, Inc., MD5 message-digest algorithm

Copyright (C) 1991-2, RSA Data Security, Inc. Created 1991. All rights reserved.

License to copy and use this software is granted provided that it is identified as the "RSA Data Security, Inc. MD5 Message-Digest Algorithm" in all material mentioning or referencing this software or this function.

License is also granted to make and use derivative works provided that such works are identified as "derived from the RSA Data Security, Inc. MD5 Message-Digest Algorithm" in all material mentioning or referencing the derived work.

RSA Data Security, Inc. makes no representations concerning either the merchantability of this software or the suitability of this software for any particular purpose. It is provided "as is" without express or implied warranty of any kind.

These notices must be retained in any copies of any part of this documentation and/or software.

The ZipArchive Library Commercial License

The ZipArchive Library - creation, modification and decompression of "zip" format archives.

Copyright © 2000 - 2010 Artpol Software - Tadeusz Dracz

Commercial License for Use with Proprietary Software - http://www.artpol-software.com/ZipArchive/KB/eula.aspx

Codalogic LMX Commercial License

Copyright (c) 2003-2010 Codalogic Ltd.

LibXL contains THE SUPPORTING SOFTWARE of Codalogic's LMX W3C Schema to C++ code generator product.

THIS SOFTWARE CONTAINED HEREIN IS PROVIDED 'AS IS' AND COMES WITH NO WARRANTIES OF ANY KIND.

CODALOGIC LTD SHALL NOT BE LIABLE FOR ANY DAMAGES SUFFERED BY ANYONE OR ANYTHING DUE TO THE USE OF THIS FILE HOWEVER THEY MAY BE CAUSED.

For more information on the LMX compiler, go to http://www.xml2cpp.com

License agreement for LMX Software http://www.codalogic.com/Imx/Imx-license-1-5.html

PDFsharp & MigraDoc

MigraDoc Foundation is published under the MIT License.

Copyright (c) 2005-2014 empira Software GmbH, Troisdorf (Germany)

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

HTML Agility Pack

Microsoft Public License (Ms-PL)

This license governs use of the accompanying software. If you use the software, you accept this license. If you do not accept the license, do not use the software.

1. Definitions

The terms "reproduce," "reproduction," "derivative works," and "distribution" have the same meaning here as under U.S. copyright law.

A "contribution" is the original software, or any additions or changes to the software.

A "contributor" is any person that distributes its contribution under this license.

"Licensed patents" are a contributor's patent claims that read directly on its contribution.

2. Grant of Rights

(A) Copyright Grant- Subject to the terms of this license, including the license conditions and limitations in section 3, each contributor grants you a non-exclusive, worldwide, royalty-free copyright license to reproduce its contribution, prepare derivative works of its contribution, and distribute its contribution or any derivative works that you create.

(B) Patent Grant- Subject to the terms of this license, including the license conditions and limitations in section 3, each contributor grants you a non-exclusive, worldwide, royalty-free license under its licensed patents to make, have made, use, sell, offer for sale, import, and/or otherwise dispose of its contribution in the software or derivative works of the contribution in the software.

3. Conditions and Limitations

(A) No Trademark License- This license does not grant you rights to use any contributors' name, logo, or trademarks.

(B) If you bring a patent claim against any contributor over patents that you claim are infringed by the software, your patent license from such contributor to the software ends automatically.

(C) If you distribute any portion of the software, you must retain all copyright, patent, trademark, and attribution notices that are present in the software.

(D) If you distribute any portion of the software in source code form, you may do so only under this license by including a complete copy of this license with your distribution. If you distribute any portion of the software in compiled or object code form, you may only do so under a license that complies with this license.

(E) The software is licensed "as-is." You bear the risk of using it. The contributors give no express warranties, guarantees or conditions. You may have additional consumer rights under your local laws which this license cannot change. To the extent permitted under your local laws, the contributors exclude the implied warranties of merchantability, fitness for a particular purpose and non-infringement.

iTextSharp

Mozilla Public License Version 1.1

1. Definitions.

1.0.1. "Commercial Use" means distribution or otherwise making the Covered Code available to a third party. 1.1. "Contributor" means each entity that creates or contributes to the creation of Modifications. 1.2. "Contributor Version" means the combination of the Original Code, prior Modifications used by a Contributor, and the Modifications made by that particular Contributor. 1.3. "Covered Code" means the Original Code or Modifications or the combination of the Original Code and Modifications, in each case including portions thereof. 1.4. "Electronic Distribution Mechanism" means a mechanism generally accepted in the software development community for the electronic transfer of data. 1.5. "Executable" means the individual or entity identified as the Initial Developer in the Source Code notice required by Exhibit A. 1.7. "Larger Work" means a work which combines Covered Code or portions thereof with code not governed by the terms of this License" means this document. 1.8.1. "Licensable" means having the right to

grant, to the maximum extent possible, whether at the time of the initial grant or subsequently acquired, any and all of the rights conveyed herein. 1.9. "Modifications"

means any addition to or deletion from the substance or structure of either the Original Code or any previous Modifications. When Covered Code is released as a series of files, a Modification is:

a. Any addition to or deletion from the contents of a file containing Original Code or previous Modifications.

b.Any new file that contains any part of the Original Code or previous Modifications.

1.10. "Original Code" means Source Code of computer software code which is described in the Source Code notice required by Exhibit A as Original Code, and which, at the time of its release under this License is not already Covered Code governed by this License. 1.10.1. "Patent Claims" means any patent claim(s), now owned or hereafter acquired, including without limitation, method, process, and apparatus claims, in any patent Licensable by grantor. 1.11. "Source Code" means the preferred form of the Covered Code for making modifications to it, including all modules it contains, plus any associated interface definition files, scripts used to control compilation and installation of an Executable, or source code differential comparisons against either the Original Code or another well known, available Covered Code of the Contributor's choice. The Source Code can be in a compressed or archival form, provided the appropriate decompression or dearchiving software is widely available for no charge. 1.12. "You" (or "Your") means an individual or a legal entity exercising rights under, and complying with all of the terms of, this License or a future version of this License issued under Section 6.1. For legal entities, "You" includes any entity which controls, is controlled by, or is under common control with You. For purposes of this definition, "control" means (a) the power, direct or indirect, to cause the direction or management of such entity, whether by contract or otherwise, or (b) ownership of more than fifty percent (50%) of the outstanding shares or beneficial ownership of such entity.

2. Source Code License.

2.1. The Initial Developer Grant.

The Initial Developer hereby grants You a world-wide, royalty-free, non-exclusive license, subject to third party intellectual property claims:

a.under intellectual property rights (other than patent or trademark) Licensable by Initial Developer to use, reproduce, modify, display, perform, sublicense and distribute the Original Code (or portions thereof) with or without Modifications, and/or as part of a Larger Work; and

b.under Patents Claims infringed by the making, using or selling of Original Code, to make, have made, use, practice, sell, and offer for sale, and/or otherwise dispose of the Original Code (or portions thereof).

c.the licenses granted in this Section 2.1 (a) and (b) are effective on the date Initial Developer first distributes Original Code under the terms of this License.

d.Notwithstanding Section 2.1 (b) above, no patent license is granted: 1) for code that You delete from the Original Code; 2) separate from the Original Code; or 3) for infringements caused by: i) the modification of the Original Code or ii) the combination of the Original Code with other software or devices.

2.2. Contributor Grant.

Subject to third party intellectual property claims, each Contributor hereby grants You a world-wide, royalty-free, non-exclusive license

a.under intellectual property rights (other than patent or trademark) Licensable by Contributor, to use, reproduce, modify, display, perform, sublicense and distribute the Modifications created by such Contributor (or portions thereof) either on an unmodified basis, with other Modifications, as Covered Code and/or as part of a Larger Work; and

b.under Patent Claims infringed by the making, using, or selling of Modifications made by that Contributor either alone and/or in combination with its Contributor Version (or portions of such combination), to make, use, sell, offer for sale, have made, and/or otherwise dispose of: 1) Modifications made by that Contributor (or portions thereof); and 2) the combination of Modifications made by that Contributor with its Contributor Version (or portions of such combination).

c.the licenses granted in Sections 2.2 (a) and 2.2 (b) are effective on the date Contributor first makes Commercial Use of the Covered Code.

d.Notwithstanding Section 2.2 (b) above, no patent license is granted: 1) for any code that Contributor has deleted from the Contributor Version; 2) separate from the Contributor Version; 3) for infringements caused by: i) third party modifications of Contributor Version or ii) the combination of Modifications made by that Contributor with other software (except as part of the Contributor Version) or other devices; or 4) under Patent Claims infringed by Covered Code in the absence of Modifications made by that Contributor.

3. Distribution Obligations.

3.1. Application of License.

The Modifications which You create or to which You contribute are governed by the terms of this License, including without limitation Section 2.2. The Source Code version of Covered Code may be distributed only under the terms of this License or a future version of this License released under Section 6.1, and You must include a copy of this License with every copy of the Source Code You distribute. You may not offer or impose any terms on any Source Code version that alters or restricts the applicable version of this License or the recipients' rights hereunder. However, You may include an additional document offering the additional rights described in Section 3.5.

3.2. Availability of Source Code.

Any Modification which You create or to which You contribute must be made available in Source Code form under the terms of this License either on the same media as an Executable version or via an accepted Electronic Distribution Mechanism to anyone to whom you made an Executable version available; and if made available via Electronic Distribution Mechanism, must remain available for at least twelve (12) months after the date it initially became available, or at least six (6) months after a subsequent version of that particular Modification has been made available to such recipients. You are responsible for ensuring that the Source Code version remains available even if the Electronic Distribution Mechanism is maintained by a third party.

3.3. Description of Modifications.

You must cause all Covered Code to which You contribute to contain a file documenting the changes You made to create that Covered Code and the date of any change. You must include a prominent statement that the Modification is derived, directly or indirectly, from Original Code provided by the Initial Developer and including the name of the Initial Developer in (a) the Source Code, and (b) in any notice in an Executable version or related documentation in which You describe the origin or ownership of the Covered Code.

3.4. Intellectual Property Matters

(a) Third Party Claims

If Contributor has knowledge that a license under a third party's intellectual property rights is required to exercise the rights granted by such Contributor under Sections 2.1 or 2.2, Contributor must include a text file with the Source Code distribution titled "LEGAL" which describes the claim and the party making the claim in sufficient detail that a recipient will know whom to contact. If Contributor obtains such knowledge after the Modification is made available as described in Section 3.2, Contributor shall promptly modify the LEGAL file in all copies Contributor makes available thereafter and shall take other steps (such as notifying appropriate mailing lists or newsgroups) reasonably calculated to inform those who received the Covered Code that new knowledge has been obtained.

(b) Contributor APIs

If Contributor's Modifications include an application programming interface and Contributor has knowledge of patent licenses which are reasonably necessary to implement that API, Contributor must also include this information in the legal file.

(c) Representations.

Contributor represents that, except as disclosed pursuant to Section 3.4 (a) above, Contributor believes that Contributor's Modifications are Contributor's original creation(s) and/or Contributor has sufficient rights to grant the rights conveyed by this License.

3.5. Required Notices.

You must duplicate the notice in Exhibit A in each file of the Source Code. If it is not possible to put such notice in a particular Source Code file due to its structure, then You must include such notice in a location (such as a relevant directory) where a user would be likely to look for such a notice. If You created one or more Modification(s) You may add your name as a Contributor to the notice described in Exhibit A. You must also duplicate this License in any documentation for the Source Code where You describe recipients' rights or ownership rights relating to Covered Code. You may choose to offer, and to charge a fee for, warranty, support, indemnity or liability obligations to one or more recipients of Covered Code. However, You may do so only on Your own behalf, and not on behalf of the Initial Developer or any Contributor. You must make it absolutely clear than any such warranty, support, indemnity or liability obligation is offered by You alone, and You hereby agree to indemnify the Initial Developer and every Contributor for any liability incurred by the Initial Developer or such Contributor as a result of warranty, support, indemnity or liability or liability or a result of warranty, support, indemnify the Initial Developer and every Contributor for any liability incurred by the Initial Developer or such Contributor as a result of warranty, support, indemnity or liability contributor as a result of warranty, support, indemnity or liability terms You offer.

3.6. Distribution of Executable Versions.

You may distribute Covered Code in Executable form only if the requirements of Sections 3.1, 3.2, 3.3, 3.4 and 3.5 have been met for that Covered Code, and if You include a notice stating that the Source Code version of the Covered Code is available under the terms of this License, including a description of how and where You have fulfilled the obligations of Section 3.2. The notice must be conspicuously included in any notice in an Executable version, related documentation or collateral in which You describe recipients' rights relating to the Covered Code. You may distribute the Executable version of Covered Code or ownership rights under a license of Your choice, which may contain terms different from this License, provided that You are in compliance with the terms of this License and that the license for the Executable version does not attempt to limit or alter the recipient's rights in the Source Code version from the rights set forth in this License. If You distribute the Executable version under a different license You must make it absolutely clear that any terms which differ from this License are offered by You alone, not by the Initial Developer or any Contributor. You hereby agree to indemnify the Initial Developer and every Contributor for any liability incurred by the Initial Developer or such Contributor as a result of any such terms You offer.

3.7. Larger Works.

You may create a Larger Work by combining Covered Code with other code not governed by the terms of this License and distribute the Larger Work as a single product. In such a case, You must make sure the requirements of this License are fulfilled for the Covered Code.

4. Inability to Comply Due to Statute or Regulation.

If it is impossible for You to comply with any of the terms of this License with respect to some or all of the Covered Code due to statute, judicial order, or regulation then You must: (a) comply with the terms of this License to the maximum extent possible; and (b) describe the limitations and the code they affect. Such description must be included in the legal file described in Section 3.4 and must be included with all distributions of the Source Code. Except to the extent prohibited by statute or regulation, such description must be sufficiently detailed for a recipient of ordinary skill to be able to understand it.

5. Application of this License.

This License applies to code to which the Initial Developer has attached the notice in Exhibit A and to related Covered Code.

6. Versions of the License.

6.1. New Versions

Netscape Communications Corporation ("Netscape") may publish revised and/or new versions of the License from time to time. Each version will be given a distinguishing version number.

6.2. Effect of New Versions

Once Covered Code has been published under a particular version of the License, You may always continue to use it under the terms of that version. You may also choose to use such Covered Code under the terms of any subsequent version of the License published

by Netscape. No one other than Netscape has the right to modify the terms applicable to Covered Code created under this License.

6.3. Derivative Works

If You create or use a modified version of this License (which you may only do in order to apply it to code which is not already Covered Code governed by this License), You must (a) rename Your license so that the phrases "Mozilla", "MOZILLAPL", "MOZPL", "Netscape", "MPL", "NPL" or any confusingly similar phrase do not appear in your license (except to note that your license differs from this License) and (b) otherwise make it clear that Your version of the license contains terms which differ from the Mozilla Public License and Netscape Public License. (Filling in the name of the Initial Developer, Original Code or Contributor in the notice described in Exhibit A shall not of themselves be deemed to be modifications of this License.)

7. Disclaimer of warranty

Covered code is provided under this license on an "as is" basis, without warranty of any kind, either expressed or implied, including, without limitation, warranties that the covered code is free of defects, merchantable, fit for a particular purpose or non-infringing. The entire risk as to the quality and performance of the covered code is with you. Should any covered code prove defective in any respect, you (not the initial developer or any other contributor) assume the cost of any necessary servicing, repair or correction. This disclaimer of warranty constitutes an essential part of this license. No use of any covered code is authorized hereunder except under this disclaimer.

8. Termination

8.1. This License and the rights granted hereunder will terminate automatically if You fail to comply with terms herein and fail to cure such breach within 30 days of becoming aware of the breach. All sublicenses to the Covered Code which are properly granted shall survive any termination of this License. Provisions which, by their nature, must remain in effect beyond the termination of this License shall survive.

8.2. If You initiate litigation by asserting a patent infringement claim (excluding declatory judgment actions) against Initial Developer or a Contributor (the Initial Developer or Contributor against whom You file such action is referred to as "Participant") alleging that:

a.such Participant's Contributor Version directly or indirectly infringes any patent, then any and all rights granted by such Participant to You under Sections 2.1 and/or 2.2 of this License shall, upon 60 days notice from Participant terminate prospectively, unless if within 60 days after receipt of notice You either: (i) agree in writing to pay Participant a mutually agreeable reasonable royalty for Your past and future use of Modifications made by such Participant, or (ii) withdraw Your litigation claim with respect to the Contributor Version against such Participant. If within 60 days of notice, a reasonable royalty and payment arrangement are not mutually agreed upon in writing by the parties or the litigation claim is not withdrawn, the rights granted by Participant to You under Sections 2.1 and/or 2.2 automatically terminate at the expiration of the 60 day notice period specified above.

b.any software, hardware, or device, other than such Participant's Contributor Version, directly or indirectly infringes any patent, then any rights granted to You by such

Participant under Sections 2.1(b) and 2.2(b) are revoked effective as of the date You first made, used, sold, distributed, or had made, Modifications made by that Participant.

8.3. If You assert a patent infringement claim against Participant alleging that such Participant's Contributor Version directly or indirectly infringes any patent where such claim is resolved (such as by license or settlement) prior to the initiation of patent infringement litigation, then the reasonable value of the licenses granted by such Participant under Sections 2.1 or 2.2 shall be taken into account in determining the amount or value of any payment or license.

8.4. In the event of termination under Sections 8.1 or 8.2 above, all end user license agreements (excluding distributors and resellers) which have been validly granted by You or any distributor hereunder prior to termination shall survive termination.

9. Limitation of liability

Under no circumstances and under no legal theory, whether tort (including negligence), contract, or otherwise, shall you, the initial developer, any other contributor, or any distributor of covered code, or any supplier of any of such parties, be liable to any person for any indirect, special, incidental, or consequential damages of any character including, without limitation, damages for loss of goodwill, work stoppage, computer failure or malfunction, or any and all other commercial damages or losses, even if such party shall have been informed of the possibility of such damages. This limitation of liability shall not apply to liability for death or personal injury resulting from such party's negligence to the extent applicable law prohibits such limitation. Some jurisdictions do not allow the exclusion or limitation of incidental or consequential damages, so this exclusion and limitation may not apply to you.

10. U.S. government end users

The Covered Code is a "commercial item," as that term is defined in 48 C.F.R. 2.101 (Oct. 1995), consisting of "commercial computer software" and "commercial computer software documentation," as such terms are used in 48 C.F.R. 12.212 (Sept. 1995). Consistent with 48 C.F.R. 12.212 and 48 C.F.R. 227.7202-1 through 227.7202-4 (June 1995), all U.S. Government End Users acquire Covered Code with only those rights set forth herein.

11. Miscellaneous

This License represents the complete agreement concerning subject matter hereof. If any provision of this License is held to be unenforceable, such provision shall be reformed only to the extent necessary to make it enforceable. This License shall be governed by California law provisions (except to the extent applicable law, if any, provides otherwise), excluding its conflict-of-law provisions. With respect to disputes in which at least one party is a citizen of, or an entity chartered or registered to do business in the United States of America, any litigation relating to this License shall be subject to the jurisdiction of the Federal Courts of the Northern District of California, with venue lying in Santa Clara County, California, with the losing party responsible for costs, including without limitation, court costs and reasonable attorneys' fees and expenses. The application of the United Nations Convention on Contracts for the International Sale of Goods is expressly excluded. Any law or regulation which provides that the language of a contract shall be construed against the drafter shall not apply to this License.

12. Responsibility for claims

As between Initial Developer and the Contributors, each party is responsible for claims and damages arising, directly or indirectly, out of its utilization of rights under this License and You agree to work with Initial Developer and Contributors to distribute such responsibility on an equitable basis. Nothing herein is intended or shall be deemed to constitute any admission of liability.

13. Multiple-licensed code

Initial Developer may designate portions of the Covered Code as "Multiple-Licensed". "Multiple-Licensed" means that the Initial Developer permits you to utilize portions of the Covered Code under Your choice of the MPL or the alternative licenses, if any, specified by the Initial Developer in the file described in Exhibit A.

Exhibit A - Mozilla Public License.

"The contents of this file are subject to the Mozilla Public License Version 1.1 (the "License"); you may not use this file except in compliance with the License. You may obtain a copy of the License at https://www.mozilla.org/MPL/

Software distributed under the License is distributed on an "AS IS" basis, WITHOUT WARRANTY OF ANY KIND, either express or implied. See the License for the specific language governing rights and limitations under the License.

The Original Code is ______.

The Initial Developer of the Original Code is ______.
Portions created by ______ are Copyright (C) ______.
All Rights Reserved.

Contributor(s):

Alternatively, the contents of this file may be used under the terms of the _____ license (the "[___] License"), in which case the provisions of [_____] License are applicable instead of those above. If you wish to allow use of your version of this file only under the terms of the [___] License and not to allow others to use your version of this file under the MPL, indicate your decision by deleting the provisions above and replace them with the notice and other provisions required by the [__] License. If you do not delete the provisions above, a recipient may use your version of this file under either the MPL or the [__] License." NOTE: The text of this Exhibit A may differ slightly from the text of the notices in the Source Code files of the Original Code. You should use the text of this Exhibit A rather than the text found in the Original Code Source Code for Your Modifications.

GNU Lesser General Public License Version 2.1, February 1999

Copyright (C) 1991, 1999 Free Software Foundation, Inc. 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

[This is the first released version of the Lesser GPL. It also counts as the successor of the GNU Library Public License, version 2, hence the version number 2.1.]

Preamble

The licenses for most software are designed to take away your freedom to share and change it. By contrast, the GNU General Public Licenses are intended to guarantee your freedom to share and change free software--to make sure the software is free for all its users.

This license, the Lesser General Public License, applies to some specially designated software packages--typically libraries--of the Free Software Foundation and other authors who decide to use it. You can use it too, but we suggest you first think carefully about whether this license or the ordinary General Public License is the better strategy to use in any particular case, based on the explanations below.

When we speak of free software, we are referring to freedom of use, not price. Our General Public Licenses are designed to make sure that you have the freedom to distribute copies of free software (and charge for this service if you wish); that you receive source code or can get it if you want it; that you can change the software and use pieces of it in new free programs; and that you are informed that you can do these things.

To protect your rights, we need to make restrictions that forbid distributors to deny you these rights or to ask you to surrender these rights. These restrictions translate to certain responsibilities for you if you distribute copies of the library or if you modify it.

For example, if you distribute copies of the library, whether gratis or for a fee, you must give the recipients all the rights that we gave you. You must make sure that they, too, receive or can get the source code. If you link other code with the library, you must provide complete object files to the recipients, so that they can relink them with the library after making changes to the library and recompiling it. And you must show them these terms so they know their rights.

We protect your rights with a two-step method: (1) we copyright the library, and (2) we offer you this license, which gives you legal permission to copy, distribute and/or modify the library.

To protect each distributor, we want to make it very clear that there is no warranty for the free library. Also, if the library is modified by someone else and passed on, the recipients should know that what they have is not the original version, so that the original author's reputation will not be affected by problems that might be introduced by others.

Finally, software patents pose a constant threat to the existence of any free program. We wish to make sure that a company cannot effectively restrict the users of a free program by obtaining a restrictive license from a patent holder. Therefore, we insist that any patent license obtained for a version of the library must be consistent with the full freedom of use specified in this license.

Most GNU software, including some libraries, is covered by the ordinary GNU General Public License. This license, the GNU Lesser General Public License, applies to certain designated libraries, and is quite different from the ordinary General Public License. We use this license for certain libraries in order to permit linking those libraries into non-free programs.

When a program is linked with a library, whether statically or using a shared library, the combination of the two is legally speaking a combined work, a derivative of the original library. The ordinary General Public License therefore permits such linking only if the entire combination fits its criteria of freedom. The Lesser General Public License permits more lax criteria for linking other code with the library.

We call this license the "Lesser" General Public License because it does Less to protect the user's freedom than the ordinary General Public License. It also provides other free software developers Less of an advantage over competing non-free programs. These disadvantages are the reason we use the ordinary General Public License for many libraries. However, the Lesser license provides advantages in certain special circumstances.

For example, on rare occasions, there may be a special need to encourage the widest possible use of a certain library, so that it becomes a de-facto standard. To achieve this, non-free programs must be allowed to use the library. A more frequent case is that a free library does the same job as widely used non-free libraries. In this case, there is little to gain by limiting the free library to free software only, so we use the Lesser General Public License.

In other cases, permission to use a particular library in non-free programs enables a greater number of people to use a large body of free software. For example, permission to use the GNU C Library in non-free programs enables many more people to use the whole GNU operating system, as well as its variant, the GNU/Linux operating system.

Although the Lesser General Public License is Less protective of the users' freedom, it

does ensure that the user of a program that is linked with the Library has the freedom and the wherewithal to run that program using a modified version of the Library.

The precise terms and conditions for copying, distribution and modification follow. Pay close attention to the difference between a "work based on the library" and a "work that uses the library". The former contains code derived from the library, whereas the latter must be combined with the library in order to run.

TERMS AND CONDITIONS FOR COPYING, DISTRIBUTION AND MODIFICATION

0. This License Agreement applies to any software library or other program which contains a notice placed by the copyright holder or other authorized party saying it may be distributed under the terms of this Lesser General Public License (also called "this License"). Each licensee is addressed as "you".

A "library" means a collection of software functions and/or data prepared so as to be conveniently linked with application programs (which use some of those functions and data) to form executables.

The "Library", below, refers to any such software library or work which has been distributed under these terms. A "work based on the Library" means either the Library or any derivative work under copyright law: that is to say, a work containing the Library or a portion of it, either verbatim or with modifications and/or translated straightforwardly into another language. (Hereinafter, translation is included without limitation in the term "modification".)

"Source code" for a work means the preferred form of the work for making modifications to it. For a library, complete source code means all the source code for all modules it contains, plus any associated interface definition files, plus the scripts used to control compilation and installation of the library.

Activities other than copying, distribution and modification are not covered by this License; they are outside its scope. The act of running a program using the Library is not restricted, and output from such a program is covered only if its contents constitute a work based on the Library (independent of the use of the Library in a tool for writing it). Whether that is true depends on what the Library does and what the program that uses the Library does.

1. You may copy and distribute verbatim copies of the Library's complete source code as you receive it, in any medium, provided that you conspicuously and appropriately publish on each copy an appropriate copyright notice and disclaimer of warranty; keep intact all the notices that refer to this License and to the absence of any warranty; and distribute a copy of this License along with the Library.

You may charge a fee for the physical act of transferring a copy, and you may at your option offer warranty protection in exchange for a fee.

2. You may modify your copy or copies of the Library or any portion of it, thus forming a work based on the Library, and copy and distribute such modifications or work under the terms of Section 1 above, provided that you also meet all of these conditions:

a) The modified work must itself be a software library.

b) You must cause the files modified to carry prominent notices stating that you changed the files and the date of any change.

c) You must cause the whole of the work to be licensed at no charge to all third parties under the terms of this License.

d) If a facility in the modified Library refers to a function or a table of data to be supplied by an application program that uses the facility, other than as an argument passed when the facility is invoked, then you must make a good faith effort to ensure that, in the event an application does not supply such function or table, the facility still operates, and performs whatever part of its purpose remains meaningful.

(For example, a function in a library to compute square roots has a purpose that is entirely well-defined independent of the application. Therefore, Subsection 2d requires that any application-supplied function or table used by this function must be optional: if the application does not supply it, the square root function must still compute square roots.)

These requirements apply to the modified work as a whole. If identifiable sections of that work are not derived from the Library, and can be reasonably considered independent and separate works in themselves, then this License, and its terms, do not apply to those sections when you distribute them as separate works. But when you distribute the same sections as part of a whole which is a work based on the Library, the distribution of the whole must be on the terms of this License, whose permissions for other licensees extend to the entire whole, and thus to each and every part regardless of who wrote it.

Thus, it is not the intent of this section to claim rights or contest your rights to work written entirely by you; rather, the intent is to exercise the right to control the distribution of derivative or collective works based on the Library.

In addition, mere aggregation of another work not based on the Library with the Library (or with a work based on the Library) on a volume of a storage or distribution medium does not bring the other work under the scope of this License.

3. You may opt to apply the terms of the ordinary GNU General Public License instead of this License to a given copy of the Library. To do this, you must alter all the notices that refer to this License, so that they refer to the ordinary GNU General Public License, version 2, instead of to this License. (If a newer version than version 2 of the ordinary GNU General Public License has appeared, then you can specify that version instead if you wish.) Do not make any other change in these notices.

Once this change is made in a given copy, it is irreversible for that copy, so the ordinary GNU General Public License applies to all subsequent copies and derivative works made from that copy.

This option is useful when you wish to copy part of the code of the Library into a program that is not a library.

4. You may copy and distribute the Library (or a portion or derivative of it, under Section 2) in object code or executable form under the terms of Sections 1 and 2 above provided that you accompany it with the complete corresponding machine-readable source code, which must be distributed under the terms of Sections 1 and 2 above on a medium customarily used for software interchange.

If distribution of object code is made by offering access to copy from a designated place, then offering equivalent access to copy the source code from the same place satisfies the requirement to distribute the source code, even though third parties are not compelled to copy the source along with the object code.

5. A program that contains no derivative of any portion of the Library, but is designed to work with the Library by being compiled or linked with it, is called a "work that uses the Library". Such a work, in isolation, is not a derivative work of the Library, and therefore falls outside the scope of this License.

However, linking a "work that uses the Library" with the Library creates an executable that is a derivative of the Library (because it contains portions of the Library), rather than a "work that uses the library". The executable is therefore covered by this License. Section 6 states terms for distribution of such executables.

When a "work that uses the Library" uses material from a header file that is part of the Library, the object code for the work may be a derivative work of the Library even though the source code is not. Whether this is true is especially significant if the work can be linked without the Library, or if the work is itself a library. The threshold for this to be true is not precisely defined by law.

If such an object file uses only numerical parameters, data structure layouts and accessors, and small macros and small inline functions (ten lines or less in length), then the use of the object file is unrestricted, regardless of whether it is legally a derivative work. (Executables containing this object code plus portions of the Library will still fall under Section 6.)

Otherwise, if the work is a derivative of the Library, you may distribute the object code for the work under the terms of Section 6. Any executables containing that work also fall under Section 6, whether or not they are linked directly with the Library itself.

6. As an exception to the Sections above, you may also combine or link a "work that uses the Library" with the Library to produce a work containing portions of the Library, and distribute that work under terms of your choice, provided that the terms permit modification of the work for the customer's own use and reverse engineering for debugging such modifications. You must give prominent notice with each copy of the work that the Library is used in it and that the Library and its use are covered by this License. You must supply a copy of this License. If the work during execution displays copyright notices, you must include the copyright notice for the Library among them, as well as a reference directing the user to the copy of this License. Also, you must do one of these things:

a) Accompany the work with the complete corresponding machine-readable source code for the Library including whatever changes were used in the work (which must be distributed under Sections 1 and 2 above); and, if the work is an executable linked with the Library, with the complete machine-readable "work that uses the Library", as object code and/or source code, so that the user can modify the Library and then relink to produce a modified executable containing the modified Library. (It is understood that the user who changes the contents of definitions files in the Library will not necessarily be able to recompile the application to use the modified definitions.)

b) Use a suitable shared library mechanism for linking with the Library. A suitable mechanism is one that (1) uses at run time a copy of the library already present on the user's computer system, rather than copying library functions into the executable, and (2) will operate properly with a modified version of the library, if the user installs one, as long as the modified version is interface-compatible with the version that the work was made with.

c) Accompany the work with a written offer, valid for at least three years, to give the same user the materials specified in Subsection 6a, above, for a charge no more than the cost of performing this distribution.

d) If distribution of the work is made by offering access to copy from a designated place, offer equivalent access to copy the above specified materials from the same place.

e) Verify that the user has already received a copy of these materials or that you have already sent this user a copy.

For an executable, the required form of the "work that uses the Library" must include any data and utility programs needed for reproducing the executable from it. However, as a special exception, the materials to be distributed need not include anything that is normally distributed (in either source or binary form) with the major components (compiler, kernel, and so on) of the operating system on which the executable runs, unless that component itself accompanies the executable.

It may happen that this requirement contradicts the license restrictions of other proprietary libraries that do not normally accompany the operating system. Such a contradiction means you cannot use both them and the Library together in an executable that you distribute.

7. You may place library facilities that are a work based on the Library side-by-side in a single library together with other library facilities not covered by this License, and distribute such a combined library, provided that the separate distribution of the work based on the Library and of the other library facilities is otherwise permitted, and provided that you do these two things:

a) Accompany the combined library with a copy of the same work based on the Library,

uncombined with any other library facilities. This must be distributed under the terms of the Sections above.

b) Give prominent notice with the combined library of the fact that part of it is a work based on the Library, and explaining where to find the accompanying uncombined form of the same work.

8. You may not copy, modify, sublicense, link with, or distribute the Library except as expressly provided under this License. Any attempt otherwise to copy, modify, sublicense, link with, or distribute the Library is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.

9. You are not required to accept this License, since you have not signed it. However, nothing else grants you permission to modify or distribute the Library or its derivative works. These actions are prohibited by law if you do not accept this License. Therefore, by modifying or distributing the Library (or any work based on the Library), you indicate your acceptance of this License to do so, and all its terms and conditions for copying, distributing or modifying the Library or works based on it.

10. Each time you redistribute the Library (or any work based on the Library), the recipient automatically receives a license from the original licensor to copy, distribute, link with or modify the Library subject to these terms and conditions. You may not impose any further restrictions on the recipients' exercise of the rights granted herein. You are not responsible for enforcing compliance by third parties with this License.

11. If, as a consequence of a court judgment or allegation of patent infringement or for any other reason (not limited to patent issues), conditions are imposed on you (whether by court order, agreement or otherwise) that contradict the conditions of this License, they do not excuse you from the conditions of this License. If you cannot distribute so as to satisfy simultaneously your obligations under this License and any other pertinent obligations, then as a consequence you may not distribute the Library at all. For example, if a patent license would not permit royalty-free redistribution of the Library by all those who receive copies directly or indirectly through you, then the only way you could satisfy both it and this License would be to refrain entirely from distribution of the Library.

If any portion of this section is held invalid or unenforceable under any particular circumstance, the balance of the section is intended to apply, and the section as a whole is intended to apply in other circumstances.

It is not the purpose of this section to induce you to infringe any patents or other property right claims or to contest validity of any such claims; this section has the sole purpose of protecting the integrity of the free software distribution system which is implemented by public license practices. Many people have made generous contributions to the wide range of software distributed through that system in reliance on consistent application of that system; it is up to the author/donor to decide if he or she is willing to distribute software through any other system and a licensee cannot impose that choice.

This section is intended to make thoroughly clear what is believed to be a consequence of the rest of this License.

12. If the distribution and/or use of the Library is restricted in certain countries either by patents or by copyrighted interfaces, the original copyright holder who places the Library under this License may add an explicit geographical distribution limitation excluding those countries, so that distribution is permitted only in or among countries not thus excluded. In such case, this License incorporates the limitation as if written in the body of this License.

13. The Free Software Foundation may publish revised and/or new versions of the Lesser General Public License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns.

Each version is given a distinguishing version number. If the Library specifies a version number of this License which applies to it and "any later version", you have the option of following the terms and conditions either of that version or of any later version published by the Free Software Foundation. If the Library does not specify a license version number, you may choose any version ever published by the Free Software Foundation.

14. If you wish to incorporate parts of the Library into other free programs whose distribution conditions are incompatible with these, write to the author to ask for permission. For software which is copyrighted by the Free Software Foundation, write to the Free Software Foundation; we sometimes make exceptions for this. Our decision will be guided by the two goals of preserving the free status of all derivatives of our free software and of promoting the sharing and reuse of software generally.

NO WARRANTY

15. BECAUSE THE LIBRARY IS LICENSED FREE OF CHARGE, THERE IS NO WARRANTY FOR THE LIBRARY, TO THE EXTENT PERMITTED BY APPLICABLE LAW. EXCEPT WHEN OTHERWISE STATED IN WRITING THE COPYRIGHT HOLDERS AND/OR OTHER PARTIES PROVIDE THE LIBRARY "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. THE ENTIRE RISK AS TO THE QUALITY AND PERFORMANCE OF THE LIBRARY IS WITH YOU. SHOULD THE LIBRARY PROVE DEFECTIVE, YOU ASSUME THE COST OF ALL NECESSARY SERVICING, REPAIR OR CORRECTION.

16. IN NO EVENT UNLESS REQUIRED BY APPLICABLE LAW OR AGREED TO IN WRITING WILL ANY COPYRIGHT HOLDER, OR ANY OTHER PARTY WHO MAY MODIFY AND/OR REDISTRIBUTE THE LIBRARY AS PERMITTED ABOVE, BE LIABLE TO YOU FOR DAMAGES, INCLUDING ANY GENERAL, SPECIAL, INCIDENTAL OR CONSEQUENTIAL DAMAGES ARISING OUT OF THE USE OR INABILITY TO USE THE LIBRARY (INCLUDING BUT NOT LIMITED TO LOSS OF DATA OR DATA BEING RENDERED INACCURATE OR LOSSES SUSTAINED BY YOU OR THIRD PARTIES OR A FAILURE OF THE LIBRARY TO OPERATE WITH ANY OTHER SOFTWARE), EVEN IF SUCH HOLDER OR OTHER PARTY HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

SvgRenderer

Microsoft Public License (Ms-PL)

This license governs use of the accompanying software. If you use the software, you accept this license. If you do not accept the license, do not use the software.

1. Definitions

The terms "reproduce," "reproduction," "derivative works," and "distribution" have the same meaning here as under U.S. copyright law.

A "contribution" is the original software, or any additions or changes to the software.

A "contributor" is any person that distributes its contribution under this license.

"Licensed patents" are a contributor's patent claims that read directly on its contribution.

2. Grant of Rights

(A) Copyright Grant- Subject to the terms of this license, including the license conditions and limitations in section 3, each contributor grants you a non-exclusive, worldwide, royalty-free copyright license to reproduce its contribution, prepare derivative works of its contribution, and distribute its contribution or any derivative works that you create.

(B) Patent Grant- Subject to the terms of this license, including the license conditions and limitations in section 3, each contributor grants you a non-exclusive, worldwide, royalty-free license under its licensed patents to make, have made, use, sell, offer for sale, import, and/or otherwise dispose of its contribution in the software or derivative works of the contribution in the software.

3. Conditions and Limitations

(A) No Trademark License- This license does not grant you rights to use any contributors' name, logo, or trademarks.

(B) If you bring a patent claim against any contributor over patents that you claim are infringed by the software, your patent license from such contributor to the software ends automatically.

(C) If you distribute any portion of the software, you must retain all copyright, patent, trademark, and attribution notices that are present in the software.

(D) If you distribute any portion of the software in source code form, you may do so only under this license by including a complete copy of this license with your distribution. If you distribute any portion of the software in compiled or object code form, you may only do so under a license that complies with this license.

(E) The software is licensed "as-is." You bear the risk of using it. The contributors give no express warranties, guarantees or conditions. You may have additional consumer rights under your local laws which this license cannot change. To the extent permitted under your local laws, the contributors exclude the implied warranties of merchantability, fitness for a particular purpose and non-infringement.

DotNetZip

Microsoft Public License (Ms-PL)

This license governs use of the accompanying software, the DotNetZip library ("the software"). If you use the software, you accept this license. If you do not accept the license, do not use the software.

1. Definitions

The terms "reproduce," "reproduction," "derivative works," and "distribution" have the same meaning here as under U.S. copyright law.

A "contribution" is the original software, or any additions or changes to the software.

A "contributor" is any person that distributes its contribution under this license.

"Licensed patents" are a contributor's patent claims that read directly on its contribution.

2. Grant of Rights

(A) Copyright Grant- Subject to the terms of this license, including the license conditions and limitations in section 3, each contributor grants you a non-exclusive, worldwide, royalty-free copyright license to reproduce its contribution, prepare derivative works of its contribution, and distribute its contribution or any derivative works that you create.

(B) Patent Grant- Subject to the terms of this license, including the license conditions and limitations in section 3, each contributor grants you a non-exclusive, worldwide, royalty-free license under its licensed patents to make, have made, use, sell, offer for sale, import, and/or otherwise dispose of its contribution in the software or derivative works of the contribution in the software.

3. Conditions and Limitations

(A) No Trademark License- This license does not grant you rights to use any contributors' name, logo, or trademarks.

(B) If you bring a patent claim against any contributor over patents that you claim are infringed by the software, your patent license from such contributor to the software ends automatically.

(C) If you distribute any portion of the software, you must retain all copyright, patent,

trademark, and attribution notices that are present in the software.

(D) If you distribute any portion of the software in source code form, you may do so only under this license by including a complete copy of this license with your distribution. If you distribute any portion of the software in compiled or object code form, you may only do so under a license that complies with this license.

(E) The software is licensed "as-is." You bear the risk of using it. The contributors give no express warranties, guarantees or conditions. You may have additional consumer rights under your local laws which this license cannot change. To the extent permitted under your local laws, the contributors exclude the implied warranties of merchantability, fitness for a particular purpose and non-infringement.

The following licenses govern use of the accompanying software, the DotNetZip library ("the software"). If you use the software, you accept these licenses. If you do not accept the license, do not use the software.

The managed ZLIB code included in Ionic.Zlib.dll and Ionic.Zip.dll is modified code, based on jzlib.

The following notice applies to jzlib:

Copyright (c) 2000,2001,2002,2003 ymnk, JCraft, Inc. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

 Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
 Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
 The names of the authors may not be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED ``AS IS'' AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL JCRAFT, INC. OR ANY CONTRIBUTORS TO THIS SOFTWARE BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

jzlib is based on zlib-1.1.3.

The following notice applies to zlib:

Copyright (C) 1995-2004 Jean-loup Gailly and Mark Adler

The ZLIB software is provided 'as-is', without any express or implied warranty. In no event will the authors be held liable for any damages arising from the use of this software.

Permission is granted to anyone to use this software for any purpose, including commercial applications, and to alter it and redistribute it freely, subject to the following restrictions:

- 1. The origin of this software must not be misrepresented; you must not claim that you wrote the original software. If you use this software in a product, an acknowledgment in the product documentation would be appreciated but is not required.
- 2. Altered source versions must be plainly marked as such, and must not be misrepresented as being the original software.
- 3. This notice may not be removed or altered from any source distribution.

Jean-loup Gailly jloup@gzip.org Mark Adler madler@alumni.caltech.edu

The managed BZIP2 code included in Ionic.BZip2.dll and Ionic.Zip.dll is modified code, based on the bzip2 code in the Apache commons compress library.

The original BZip2 was created by Julian Seward, and is licensed under the BSD license.

The following license applies to the Apache code:

/*

- * Licensed to the Apache Software Foundation (ASF) under one
- * or more contributor license agreements. See the NOTICE file
- * distributed with this work for additional information
- * regarding copyright ownership. The ASF licenses this file
- * to you under the Apache License, Version 2.0 (the
- * "License"); you may not use this file except in compliance
- * with the License. You may obtain a copy of the License at
- *

*

- * http://www.apache.org/licenses/LICENSE-2.0
- * Unless required by applicable law or agreed to in writing,
- * software distributed under the License is distributed on an
- * "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY
- * KIND, either express or implied. See the License for the
- * specific language governing permissions and limitations
- * under the License.
- */

Performance AL Anywhere Licenses

The Performance AL Anywhere client uses web components based on the React Javascript Library from Meta.

Components are licensed under the following licenses:

Component	License	Copyright
adobe/css-tools	МІТ	Copyright (c) 2022 Jean-Philippe Zolesio
ampproject/remapping	Apache-2.0	Copyright 2019 Google LLC
babel/code-frame	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/compat-data	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/core	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/generator	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/helper-annotate-as-pure	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/helper-builder-binary- assignment-operator-visitor	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors

Component	License	Copyright
babel/helper-compilation- targets	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/helper-create-class- features-plugin	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/helper-create-regexp- features-plugin	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/helper-define-polyfill- provider	МІТ	Copyright (c) 2014-present Nicolo Ribaudo and other contributors
babel/helper-environment- visitor	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/helper-explode- assignable-expression	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/helper-function-name	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/helper-hoist-variables	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/helper-member- expression-to-functions	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/helper-module-imports	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/helper-module- transforms	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/helper-optimise-call- expression	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/helper-plugin-utils	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/helper-remap-async-to- generator	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/helper-replace-supers	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/helper-simple-access	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/helper-skip-transparent- expression-wrappers	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/helper-split-export- declaration	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors

Component	License	Copyright
babel/helper-string-parser	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/helper-validator- identifier	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/helper-validator-option	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/helper-wrap-function	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/helpers	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/highlight	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/parser	МІТ	Copyright (c) 2012-2014 by various contributors
babel/plugin-bugfix-safari-id- destructuring-collision-in- function-expression	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-bugfix-v8-spread- parameters-in-optional- chaining	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-proposal-async- generator-functions	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-proposal-class- properties	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-proposal-class- static-block	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-proposal- dynamic-import	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-proposal-export- namespace-from	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-proposal-json- strings	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-proposal-logical- assignment-operators	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-proposal-nullish- coalescing-operator	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-proposal-numeric- separator	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-proposal-object-	міт	Copyright (c) 2014-present

Component	License	Copyright
rest-spread		Sebastian McKenzie and other contributors
babel/plugin-proposal- optional-catch-binding	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-proposal- optional-chaining	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-proposal-private- methods	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-proposal-private- property-in-object	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-proposal-unicode- property-regex	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-syntax-async- generators	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-syntax-bigint	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-syntax-class- properties	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-syntax-class- static-block	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-syntax-dynamic- import	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-syntax-export- namespace-from	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-syntax-import- assertions	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-syntax-import- meta	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-syntax-json- strings	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-syntax-jsx	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-syntax-logical- assignment-operators	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-syntax-nullish- coalescing-operator	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-syntax-numeric-	МІТ	Copyright (c) 2014-present

Component	License	Copyright
separator		Sebastian McKenzie and other contributors
babel/plugin-syntax-object-rest- spread	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-syntax-optional- catch-binding	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-syntax-optional- chaining	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-syntax-private- property-in-object	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-syntax-top-level- await	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-syntax-typescript	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform-arrow- functions	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform-async- to-generator	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform-block- scoped-functions	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform-block- scoping	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform-classes	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform- computed-properties	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform- destructuring	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform-dotall- regex	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform- duplicate-keys	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform- exponentiation-operator	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform-for-of	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform-	МІТ	Copyright (c) 2014-present

Component	License	Copyright
function-name		Sebastian McKenzie and other contributors
babel/plugin-transform-literals	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform- member-expression-literals	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform- modules-amd	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform- modules-commonjs	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform- modules-systemjs	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform- modules-umd	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform-named- capturing-groups-regex	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform-new- target	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform-object- super	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform- parameters	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform- property-literals	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform-react- display-name	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform-react- jsx	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform-react- jsx-development	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform-react- pure-annotations	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform- regenerator	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform- reserved-words	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform-	міт	Copyright (c) 2014-present

Component	License	Copyright
shorthand-properties		Sebastian McKenzie and other contributors
babel/plugin-transform-spread	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform-sticky- regex	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform- template-literals	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform-typeof- symbol	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform- typescript	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform- unicode-escapes	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform- unicode-regex	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/preset-env	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/preset-modules	MIT	Copyright (c) 2020 Babel
babel/preset-react	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/preset-typescript	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/runtime	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/template	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/traverse	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/types	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
bcoe/v8-coverage	MIT	The copyright for this library is unknown
bcoe/v8-coverage/dist/lib	МІТ	The copyright for this library is unknown
csstools/selector-specificity	CC0-1.0	The copyright for this library is unknown
date-io/core	МІТ	Copyright (c) 2017 Dmitriy Kovalenko
date-io/moment	МІТ	Copyright (c) 2017 Dmitriy

Component	License	Copyright
		Kovalenko
egjs/hammerjs	МІТ	The copyright for this library is unknown
emotion/hash	МІТ	Copyright (c) Emotion team and other contributors
enykeev/react-virtualized	MIT	Copyright (c) 2015 Brian Vaughn
esbuild/win32-x64	МІТ	The copyright for this library is unknown
eslint/eslintrc	МІТ	Copyright OpenJS Foundation and other contributors,
humanwhocodes/config-array	Apache-2.0	The copyright for this library is unknown
humanwhocodes/module- importer	Apache-2.0	The copyright for this library is unknown
humanwhocodes/object-schema	BSD-3-Clause	Copyright (c) 2019, Human Who Codes
icons/material	МІТ	The copyright for this library is unknown
istanbuljs/load-nyc-config	ISC	Copyright (c) 2019, Contributors
istanbuljs/schema	МІТ	Copyright (c) 2019 CFWare, LLC
jest/console	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jest/core	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jest/environment	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jest/expect	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jest/expect-utils	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jest/fake-timers	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jest/globals	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jest/reporters	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jest/schemas	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jest/source-map	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jest/test-result	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jest/test-sequencer	міт	Copyright (c) Facebook, Inc. and its affiliates
jest/transform	міт	Copyright (c) Facebook, Inc. and its affiliates
jest/types	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jridgewell/gen-mapping	MIT	Copyright 2022 Justin Ridgewell
jridgewell/resolve-uri	MIT	Copyright 2019 Justin Ridgewell
jridgewell/set-array	МІТ	Copyright 2022 Justin Ridgewell

Component	License	Copyright
jridgewell/sourcemap-codec	MIT	Copyright (c) 2015 Rich Harris
jridgewell/trace-mapping	MIT	Copyright 2022 Justin Ridgewell
material-ui/core	MIT	Copyright (c) 2014 Call-Em-All
material-ui/icons	MIT	Copyright (c) 2014 Call-Em-All
· · · · ·		The copyright for this library is
material-ui/pickers	МІТ	unknown
material-ui/styles	MIT	Copyright (c) 2014 Call-Em-All
material-ui/system	MIT	Copyright (c) 2014 Call-Em-All
material-ui/types	МІТ	The copyright for this library is unknown
material-ui/utils	МІТ	Copyright (c) 2014 Call-Em-All
mdi/js	Apache-2.0	The copyright for this library is unknown
nodelib/fs.scandir	MIT	Copyright (c) Denis Malinochkin
nodelib/fs.stat	MIT	Copyright (c) Denis Malinochkin
nodelib/fs.walk	MIT	Copyright (c) Denis Malinochkin
progress/kendo-ui		Copyright 2020 Progress Software Corporation and/or one of its subsidiaries or affiliates
react-dnd/asap	МІТ	The copyright for this library is unknown
react-dnd/invariant	МІТ	Copyright (c) 2013-present, Facebook, Inc.
react-dnd/shallowequal	MIT	Copyright (c) 2017 Alberto Leal
reduxjs/toolkit	MIT	Copyright (c) 2018 Mark Erikson
reduxjs/toolkit/query	МІТ	The copyright for this library is unknown
reduxjs/toolkit/query/react	МІТ	The copyright for this library is unknown
rollup/plugin-typescript	MIT	The copyright for this library is unknown
rollup/pluginutils	MIT	The copyright for this library is unknown
sinclair/typebox	МІТ	Copyright (c) 2022 Haydn Paterson
sinonjs/commons	BSD-3-Clause	Copyright (c) 2018, Sinon.JS
sinonjs/fake-timers	BSD-3-Clause	Copyright (c) 2010-2014, Christian Johansen, christian@cjohansen.no
storybook/csf	міт	The copyright for this library is unknown
testing-library/dom	MIT	Copyright (c) 2017 Kent C. Dodds
testing-library/jest-dom	MIT	Copyright (c) 2017 Kent C. Dodds
testing-library/react	MIT	Copyright (c) 2017 Kent C. Dodds
tootalInate/once	міт	Copyright (c) 2020 Nathan Rajlich
types/aria-query	MIT	Copyright (c) Microsoft Corporation
types/babelcore	МІТ	Copyright (c) Microsoft Corporation

Component	License	Copyright
types/babelgenerator	МІТ	Copyright (c) Microsoft Corporation
types/babeltemplate	МІТ	Copyright (c) Microsoft Corporation
types/babeltraverse	МІТ	Copyright (c) Microsoft Corporation
types/detect-it	МІТ	Copyright (c) Microsoft Corporation
types/draft-js	МІТ	Copyright (c) Microsoft Corporation
types/estree	МІТ	Copyright (c) Microsoft Corporation
types/graceful-fs	МІТ	Copyright (c) Microsoft Corporation
types/hammerjs	МІТ	Copyright (c) Microsoft Corporation
types/hoist-non-react-statics	МІТ	Copyright (c) Microsoft Corporation
types/istanbul-lib-coverage	МІТ	Copyright (c) Microsoft Corporation
types/istanbul-lib-report	МІТ	Copyright (c) Microsoft Corporation
types/istanbul-reports	МІТ	Copyright (c) Microsoft Corporation
types/jest	МІТ	Copyright (c) Microsoft Corporation
types/jquery	МІТ	Copyright (c) Microsoft Corporation
types/jsdom	МІТ	Copyright (c) Microsoft Corporation
types/json-schema	МІТ	Copyright (c) Microsoft Corporation
types/json5	МІТ	The copyright for this library is unknown
types/lodash	МІТ	Copyright (c) Microsoft Corporation
types/lodash.clonedeep	МІТ	Copyright (c) Microsoft Corporation
types/lodash.debounce	МІТ	Copyright (c) Microsoft Corporation
types/lodash.memoize	МІТ	Copyright (c) Microsoft Corporation
types/lodash.merge	МІТ	Copyright (c) Microsoft Corporation
types/lodash.uniq	МІТ	Copyright (c) Microsoft Corporation
types/lodash.uniqwith	МІТ	Copyright (c) Microsoft Corporation
types/minimist	МІТ	Copyright (c) Microsoft Corporation
types/node	МІТ	Copyright (c) Microsoft Corporation

Component	License	Copyright
types/normalize-package-data	МІТ	Copyright (c) Microsoft Corporation
types/parse-json	MIT	Copyright (c) Microsoft Corporation
types/prettier	МІТ	Copyright (c) Microsoft Corporation
types/prop-types	MIT	Copyright (c) Microsoft Corporation
types/react	МІТ	Copyright (c) Microsoft Corporation
types/react-color	MIT	Copyright (c) Microsoft Corporation
types/react-dom	MIT	Copyright (c) Microsoft Corporation
types/react-hammerjs	MIT	Copyright (c) Microsoft Corporation
types/react-measure	МІТ	Copyright (c) Microsoft Corporation
types/react-transition-group	МІТ	Copyright (c) Microsoft Corporation
types/react-virtualized	МІТ	Copyright (c) Microsoft Corporation
types/reactcss	МІТ	Copyright (c) Microsoft Corporation
types/redux-mock-store	МІТ	Copyright (c) Microsoft Corporation
types/scheduler	МІТ	Copyright (c) Microsoft Corporation
types/semver	МІТ	Copyright (c) Microsoft Corporation
types/sizzle	МІТ	Copyright (c) Microsoft Corporation
types/stack-utils	МІТ	Copyright (c) Microsoft Corporation
types/styled-jsx	МІТ	Copyright (c) Microsoft Corporation
types/testing-library_jest-dom	МІТ	Copyright (c) Microsoft Corporation
types/tough-cookie	МІТ	Copyright (c) Microsoft Corporation
types/use-sync-external-store	МІТ	Copyright (c) Microsoft Corporation
types/uuid	МІТ	Copyright (c) Microsoft Corporation
types/yargs	МІТ	Copyright (c) Microsoft Corporation
types/yargs-parser	МІТ	Copyright (c) Microsoft Corporation
typescript-eslint/eslint-plugin	MIT	Copyright (c) 2019 TypeScript ESLint and other contributors
typescript-eslint/parser	BSD-2-Clause	Copyright JS Foundation and other contributors, https://

Component	License	Copyright
		js.foundation
typescript-eslint/scope- manager	міт	Copyright (c) 2019 TypeScript ESLint and other contributors
typescript-eslint/type-utils	міт	Copyright (c) 2021 typescript- eslint and other contributors
typescript-eslint/types	МІТ	Copyright (c) 2019 TypeScript ESLint and other contributors
typescript-eslint/typescript- estree	BSD-2-Clause	Copyright JS Foundation and other contributors, https://js.foundation
typescript-eslint/utils	МІТ	Copyright (c) 2019 typescript- eslint and other contributors
typescript-eslint/visitor-keys	МІТ	Copyright (c) 2019 TypeScript ESLint and other contributors
vitejs/plugin-react	MIT	Copyright (c) 2019-present, Yuxi
abab	BSD-3-Clause	The copyright for this library is unknown
acorn	МІТ	Copyright (c) 2012-2018 by various contributors
acorn-globals	МІТ	Copyright (c) 2014 Forbes Lindesay
acorn-jsx	МІТ	Copyright (c) 2012-2017 by Ingvar Stepanyan
acorn-walk	МІТ	Copyright (c) 2012-2018 by various contributors
agent-base	МІТ	The copyright for this library is unknown
ajv	МІТ	Copyright (c) 2015-2017 Evgeny Poberezkin
ansi-escapes	МІТ	Copyright (c) Sindre Sorhus (https://sindresorhus.com)
ansi-regex	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
ansi-styles	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
antlr4	BSD-3-Clause	The copyright for this library is unknown
anymatch	ISC	Copyright (c) 2014 Elan Shanker
argparse	МІТ	Copyright (c) 2012 by Vitaly Puzrin
aria-query	Apache-2.0	Copyright 2020 A11yance
array-includes	МІТ	Copyright (c) 2015 Jordan Harband
array-union	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
array.prototype.flat	МІТ	Copyright (c) 2017 ECMAScript Shims
array.prototype.flatmap	МІТ	Copyright (c) 2017 ECMAScript Shims
array.prototype.tosorted	МІТ	Copyright (c) 2021 ECMAScript Shims
arrify	MIT	Copyright (c) Sindre Sorhus

Component	License	Copyright
		(sindresorhus.com)
asap	МІТ	The copyright for this library is unknown
ast-types-flow	ISC	The copyright for this library is unknown
astral-regex	МІТ	Copyright (c) Kevin Martensson
asynckit	МІТ	Copyright (c) 2016 Alex Indigo
available-typed-arrays	МІТ	Copyright (c) 2020 Inspect JS
axe-core	MPL-2.0	The copyright for this library is unknown
axobject-query	Apache-2.0	Copyright 2020 A11yance
babel-jest	міт	Copyright (c) Facebook, Inc. and its affiliates
babel-plugin-istanbul	BSD-3-Clause	Copyright (c) 2016, Istanbul Code Coverage
babel-plugin-jest-hoist	МІТ	Copyright (c) Facebook, Inc. and its affiliates
babel-plugin-polyfill-corejs2	MIT	Copyright (c) 2014-present Nicolo Ribaudo and other contributors
babel-plugin-polyfill-corejs3	МІТ	Copyright (c) 2014-present Nicolo Ribaudo and other contributors
babel-plugin-polyfill- regenerator	МІТ	Copyright (c) 2014-present Nicolo Ribaudo and other contributors
babel-plugin-transform-import- meta	BSD-3-Clause	Copyright (c) 2019 javiertury Code derived from a previous work of The Polymer Authors
babel-preset-current-node- syntax	МІТ	Copyright (c) 2020 Nicolo Ribaudo and other contributors
babel-preset-jest	МІТ	Copyright (c) Facebook, Inc. and its affiliates
balanced-match	МІТ	The copyright for this library is unknown
binary-extensions	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
brace-expansion	МІТ	Copyright (c) 2013 Julian Gruber
braces	МІТ	Copyright (c) 2014-2018, Jon Schlinkert
browserslist	МІТ	Copyright 2014 Andrey Sitnik and other contributors
bser	Apache-2.0	The copyright for this library is unknown
buffer-from	МІТ	Copyright (c) 2016, 2018 Linus Unneback
call-bind	МІТ	Copyright (c) 2020 Jordan Harband
call-me-maybe	МІТ	Copyright (c) 2015 Eric McCarthy
callsites	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)

Component	License	Copyright
camelcase	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
camel case-keys	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
caniuse-lite	CC-BY-4.0	The copyright for this library is unknown
chalk	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
char-regex	МІТ	Copyright (c) 2019 Richie Bendall
chokidar	МІТ	Copyright (c) 2012-2019 Paul Miller (https://paulmillr.com), Elan Shanker
ci-info	МІТ	Copyright (c) 2016-2018 Thomas Watson Steen
cjs-module-lexer	МІТ	Copyright (c) 2018-2020 Guy Bedford
cliui	ISC	The copyright for this library is unknown
clsx	МІТ	Copyright (c) Luke Edwards (lukeed.com)
со	МІТ	Copyright (c) 2014 TJ Holowaychuk
collect-v8-coverage	МІТ	Copyright (c) 2019 Simen Bekkhus
color-convert	МІТ	Copyright (c) 2011-2016 Heather Arthur
color-name	МІТ	Copyright (c) 2015 Dmitry Ivanov
colord	МІТ	The copyright for this library is unknown
combined-stream	МІТ	Copyright (c) 2011 Debuggable Limited
commander	МІТ	Copyright (c) 2011 TJ Holowaychuk
concat-map	МІТ	The copyright for this library is unknown
confusing-browser-globals	міт	Copyright (c) 2013-present, Facebook, Inc.
convert-source-map	MIT	Copyright 2013 Thorsten Lorenz
core-js	МІТ	Copyright (c) 2014-2021 Denis Pushkarev
core-js-compat	МІТ	Copyright (c) 2014-2020 Denis Pushkarev
core-util-is	MIT	Copyright Node.js contributors
cosmiconfig	MIT	Copyright (c) 2015 David Clark
cross-env	MIT	Copyright (c) 2017 Kent C. Dodds
cross-fetch	МІТ	Copyright (c) 2017 Leonardo Quixada
cross-fetch/polyfill	МІТ	The copyright for this library is unknown
cross-spawn	MIT	Copyright (c) 2018 Made With

Component	License	Copyright
-		MOXY Lda
css-functions-list	МІТ	The copyright for this library is unknown
css-vendor	МІТ	Copyright (c) 2014-present Oleg Slobodskoi
css.escape	МІТ	The copyright for this library is unknown
cssesc	МІТ	The copyright for this library is unknown
cssom	МІТ	The copyright for this library is unknown
cssstyle	МІТ	Copyright (c) Chad Walker
csstype	МІТ	Copyright (c) 2017-2018 Fredrik Nicol
da mera u-levenshtein	BSD-2-Clause	Copyright (c) 2018, Tadeusz Lazurski
data-urls	МІТ	The copyright for this library is unknown
debug	МІТ	Copyright (c) 2014 TJ Holowaychuk
decamelize	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
decamelize-keys	МІТ	Copyright (c) Sindre Sorhus
decimal.js	МІТ	The copyright for this library is unknown
dedent	MIT	Copyright (c) 2015 Desmond Brand (dmnd@desmondbrand.com)
deep-equal	MIT	Copyright (c) 2012, 2013, 2014 James Halliday , 2009 Thomas Robinson <280north.com>
deep-is	МІТ	Copyright (c) 2009 Thomas Robinson <280north.com>
deepfreeze	МІТ	Copyright (c) 2016 Alexander Praetorius
deepmerge	МІТ	The copyright for this library is unknown
define-properties	МІТ	Copyright (c) 2015 Jordan Harband
delayed-stream	МІТ	Copyright (c) 2011 Debuggable Limited
detect-it	МІТ	Copyright (c) 2016 Rafael Pedicini
detect-newline	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
diff-sequences	МІТ	Copyright (c) Facebook, Inc. and its affiliates
dir-glob	MIT	Copyright (c) Kevin Martensson
dnd-core	MIT	Copyright (c) 2015 Dan Abramov
doctrine	Apache-2.0	The copyright for this library is unknown
dom-accessibility-api	МІТ	The copyright for this library is

Component	License	Copyright
		unknown
dom-helpers	міт	Copyright (c) 2015 Jason Quense
domexception	МІТ	The copyright for this library is unknown
draft-js	MIT	Copyright (c) Facebook, Inc. and its affiliates
electron-to-chromium	ISC	Copyright 2018 Kilian Valkhof
emittery	МІТ	Copyright (c) Sindre Sorhus (https://sindresorhus.com)
emoji-regex	міт	The copyright for this library is unknown
enhanced-resolve	міт	Copyright JS Foundation and other contributors
entities	BSD-2-Clause	Copyright (c) Felix Bohm
errno	міт	The copyright for this library is unknown
error-ex	MIT	Copyright (c) 2015 JD Ballard
es-abstract	міт	Copyright (c) 2015 Jordan Harband
es-get-iterator	міт	Copyright (c) 2019 Jordan Harband
es-set-tostringtag	міт	Copyright (c) 2022 ECMAScript Shims
es-shim-unscopables	міт	Copyright (c) 2022 Jordan Harband
es-to-primitive	МІТ	Copyright (c) 2015 Jordan Harband
es6-promise	МІТ	Copyright (c) 2014 Yehuda Katz, Tom Dale, Stefan Penner and contributors
esbuild	МІТ	The copyright for this library is unknown
escalade	міт	Copyright (c) Luke Edwards (lukeed.com)
escape-string-regexp	міт	Copyright (c) Sindre Sorhus (sindresorhus.com)
escodegen	BSD-3-Clause AND BSD-2-Clause	The copyright for this library is unknown
eslint	міт	Copyright JS Foundation and other contributors, https:// js.foundation
eslint-config-airbnb	МІТ	The copyright for this library is unknown
eslint-config-airbnb-base	МІТ	The copyright for this library is unknown
eslint-config-airbnb-typescript	МІТ	Copyright (c) Matt Turnbull
eslint-config-prettier	МІТ	Copyright (c) 2017, 2018, 2019, 2020, 2021 Simon Lydell and contributors
eslint-import-resolver-node	МІТ	Copyright (c) 2015 Ben Mosher
eslint-module-utils	МІТ	Copyright (c) 2015 Ben Mosher
eslint-plugin-es	MIT	Copyright (c) 2018 Toru

Component	License	Copyright
		Nagashima
eslint-plugin-import	MIT	Copyright (c) 2015 Ben Mosher
eslint-plugin-import/memo- parser	MIT	Copyright (c) 2015 Ben Mosher
eslint-plugin-jest	МІТ	Copyright (c) 2018 Jonathan Kim
eslint-plugin-jsx-a11y	MIT	The copyright for this library is unknown
eslint-plugin-node	МІТ	Copyright (c) 2015 Toru Nagashima
eslint-plugin-prettier	МІТ	The copyright for this library is unknown
eslint-plugin-promise	ISC	The copyright for this library is unknown
eslint-plugin-react	МІТ	Copyright (c) 2014 Yannick Croissant
eslint-plugin-react-hooks	МІТ	Copyright (c) Facebook, Inc. and its affiliates
eslint-plugin-storybook	МІТ	Copyright (c) 2022 Storybook
eslint-scope	BSD-2-Clause	Copyright (c) 2012-2013 Yusuke Suzuki (twitter Constellation) and other contributors
eslint-utils	MIT	Copyright (c) 2018 Toru Nagashima
eslint-visitor-keys	Apache-2.0	The copyright for this library is unknown
espree	BSD-2-Clause	Copyright JS Foundation and other contributors, https:// js.foundation
esprima	BSD-2-Clause	The copyright for this library is unknown
esquery	BSD-3-Clause	The copyright for this library is unknown
esrecurse	BSD-2-Clause	The copyright for this library is unknown
estraverse	BSD-2-Clause	The copyright for this library is unknown
estree-walker	МІТ	Copyright (c) 2015-20 these people (https://github.com/Rich- Harris/estree-walker/graphs/ contributors)
esutils	BSD-3-Clause AND BSD-2-Clause	The copyright for this library is unknown
execa	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
exit	міт	The copyright for this library is unknown
expect	міт	Copyright (c) Facebook, Inc. and its affiliates
fast-deep-equal	міт	Copyright (c) 2017 Evgeny Poberezkin
fast-diff	Apache-2.0	The copyright for this library is unknown

Component	License	Copyright
fast-glob	MIT	Copyright (c) Denis Malinochkin
fast-json-stable-stringify	МІТ	Copyright (c) 2013 James Halliday
fast-levenshtein	МІТ	The copyright for this library is unknown
fastest-levenshtein	МІТ	The copyright for this library is unknown
fastq	ISC	Copyright (c) 2015-2020, Matteo Collina
fb-watchman	Apache-2.0	The copyright for this library is unknown
fbjs	міт	Copyright (c) 2013-present, Facebook, Inc.
fbjs-css-vars	МІТ	Copyright (c) 2013-present, Facebook, Inc.
file-entry-cache	MIT	Copyright (c) 2015 Roy Riojas
fill-range	МІТ	Copyright (c) 2014-present, Jon Schlinkert
find-up	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
flat-cache	MIT	Copyright (c) 2015 Roy Riojas
flatted	ISC	(c) 2018, Andrea Giammarchi, (ISC)
for-each	MIT	Copyright (c) 2012 Raynos
form-data	МІТ	Copyright (c) 2012 Felix Geisendorfer (felix@debuggable.com) and contributors
fs-extra	MIT	Copyright (c) 2011-2017 JP Richardson
fs.realpath	ISC AND MIT	Copyright Joyent, Inc. and other Node contributors
function-bind	MIT	Copyright (c) 2013 Raynos
function.prototype.name	MIT	Copyright (c) 2016 Jordan Harband
functions-have-names	МІТ	Copyright (c) 2019 Jordan Harband
gensync	MIT	Copyright 2018 Logan Smyth
get-caller-file	ISC	The copyright for this library is unknown
get-intrinsic	MIT	Copyright (c) 2020 Jordan Harband
get-node-dimensions	МІТ	Copyright (c) 2015 get-node- dimensions authors
get-package-type	МІТ	Copyright (c) 2020 CFWare, LLC
get-stream	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
get-symbol-description	МІТ	Copyright (c) 2021 Inspect JS
glob	ISC	Copyright (c) Isaac Z. Schlueter and Contributors
glob-parent	ISC	Copyright (c) 2015, 2019 Elan Shanker

Component	License	Copyright
glob-to-regexp	BSD-3-Clause	The copyright for this library is unknown
global-modules	МІТ	Copyright (c) 2015-present, Jon Schlinkert
global-prefix	МІТ	Copyright (c) 2015-present, Jon Schlinkert
globals	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
globalthis	MIT	Copyright (c) 2016 Jordan Harband
globby	MIT	Copyright (c) Sindre Sorhus (sindresorhus.com)
globjoin	MIT	Copyright (c) 2016 amobiz
gopd	MIT	Copyright (c) 2022 Jordan Harband
graceful-fs	ISC	Copyright (c) Isaac Z. Schlueter, Ben Noordhuis, and Contributors
grapheme-splitter	МІТ	Copyright (c) 2015 Orlin Georgiev
hard-rejection	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
has	МІТ	The copyright for this library is unknown
has-bigints	МІТ	Copyright (c) 2019 Jordan Harband
has-flag	MIT	Copyright (c) Sindre Sorhus (sindresorhus.com)
has-property-descriptors	MIT	Copyright (c) 2022 Inspect JS
has-proto	MIT	Copyright (c) 2022 Inspect JS
has-symbols	MIT	Copyright (c) 2016 Jordan Harband
has-tostringtag	MIT	Copyright (c) 2021 Inspect JS
hoist-non-react-statics	BSD-3-Clause	The copyright for this library is unknown
hosted-git-info	ISC	Copyright (c) 2015, Rebecca Turner
html-encoding-sniffer	MIT	The copyright for this library is unknown
html-escaper	MIT	The copyright for this library is unknown
html-parse-stringify	МІТ	The copyright for this library is unknown
html-tags	MIT	Copyright (c) Sindre Sorhus (https://sindresorhus.com)
http-proxy-agent	МІТ	The copyright for this library is unknown
https-proxy-agent	MIT	The copyright for this library is unknown
human-signals	Apache-2.0	Copyright 2019 ehmicky
hyphenate-style-name	BSD-3-Clause	Copyright (c) 2015, Espen Hovlandsdal

Component	License	Copyright
i18next	MIT	Copyright (c) 2017 i18next
i18next-browser- languagedetector	МІТ	Copyright (c) 2015 i18next
i18next-xhr-backend	MIT	Copyright (c) 2015 i18next
iconv-lite	МІТ	Copyright (c) 2011 Alexander Shtuchkin
ignore	МІТ	The copyright for this library is unknown
immer	МІТ	Copyright (c) 2017 Michel Weststrate
immutable	BSD-3-Clause	Copyright (c) 2014-2015, Facebook, Inc.
import-fresh	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
import-lazy	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
import-local	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
imurmurhash	МІТ	The copyright for this library is unknown
indent-string	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
inflight	ISC	Copyright (c) Isaac Z. Schlueter
inherits	ISC	Copyright (c) Isaac Z. Schlueter
ini	ISC	Copyright (c) Isaac Z. Schlueter and Contributors
internal-slot	МІТ	Copyright (c) 2019 Jordan Harband
is-absolute	МІТ	Copyright (c) 2009-2014, TJ Holowaychuk
is-arguments	МІТ	Copyright (c) 2014 Jordan Harband
is-array-buffer	МІТ	Copyright (c) 2015 Chen Gengyuan, Inspect JS
is-arrayish	MIT	Copyright (c) 2015 JD Ballard
is-bigint	МІТ	Copyright (c) 2018 Jordan Harband
is-binary-path	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
is-boolean-object	МІТ	Copyright (c) 2015 Jordan Harband
is-callable	МІТ	Copyright (c) 2015 Jordan Harband
is-core-module	MIT	Copyright (c) 2014 Dave Justice
is-date-object	МІТ	Copyright (c) 2015 Jordan Harband
is-extglob	МІТ	Copyright (c) 2014-2015, Jon Schlinkert
is-fullwidth-code-point	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
is-generator-fn	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)

Component	License	Copyright
is-glob	МІТ	Copyright (c) 2014-2017, Jon Schlinkert
is-in-browser	МІТ	The copyright for this library is unknown
is-map	MIT	Copyright (c) 2019 Inspect JS
is-negative-zero	МІТ	Copyright (c) 2014 Jordan Harband
is-number	МІТ	Copyright (c) 2014-2016, Jon Schlinkert
is-number-object	МІТ	Copyright (c) 2015 Jordan Harband
is-path-inside	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
is-plain-obj	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
is-plain-object	МІТ	Copyright (c) 2014-2017, Jon Schlinkert
is-potential-custom-element- name	МІТ	The copyright for this library is unknown
is-regex	МІТ	Copyright (c) 2014 Jordan Harband
is-relative	МІТ	Copyright (c) 2014-2017, Jon Schlinkert
is-set	MIT	Copyright (c) 2019 Inspect JS
is-shared-array-buffer	MIT	Copyright (c) 2021 Inspect JS
is-stream	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
is-string	МІТ	Copyright (c) 2015 Jordan Harband
is-symbol	МІТ	Copyright (c) 2015 Jordan Harband
is-typed-array	МІТ	Copyright (c) 2015 Jordan Harband
is-unc-path	МІТ	Copyright (c) 2015-2017, Jon Schlinkert
is-weakmap	MIT	Copyright (c) 2019 Inspect JS
is-weakref	MIT	Copyright (c) 2020 Inspect JS
is-weakset	MIT	Copyright (c) 2019 Inspect JS
is-windows	МІТ	Copyright (c) 2015-2018, Jon Schlinkert
isarray	MIT	Copyright (c) 2013 Julian Gruber
isexe	ISC	Copyright (c) Isaac Z. Schlueter and Contributors
istanbul-lib-coverage	BSD-3-Clause	Copyright 2012-2015 Yahoo! Inc.
istanbul-lib-instrument	BSD-3-Clause	Copyright 2012-2015 Yahoo! Inc.
istanbul-lib-report	BSD-3-Clause	Copyright 2012-2015 Yahoo! Inc.
istanbul-lib-source-maps	BSD-3-Clause	Copyright 2015 Yahoo! Inc.
istanbul-reports	BSD-3-Clause	Copyright 2012-2015 Yahoo!

Component	License	Copyright
		Inc.
jest	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jest-changed-files	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jest-circus	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jest-cli	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jest-config	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jest-diff	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jest-docblock	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jest-each	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jest-environment-jsdom	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jest-environment-node	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jest-get-type	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jest-haste-map	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jest-leak-detector	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jest-matcher-utils	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jest-message-util	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jest-mock	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jest-pnp-resolver	МІТ	The copyright for this library is unknown
jest-regex-util	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jest-resolve	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jest-resolve-dependencies	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jest-runner	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jest-runtime	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jest-snapshot	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jest-util	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jest-validate	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jest-watcher	МІТ	Copyright (c) Facebook, Inc. and

Component	License	Copyright
		its affiliates
jest-worker	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jquery	МІТ	The copyright for this library is unknown
js-sdsl	MIT	Copyright (c) 2021 Zilong Yao
js-tokens	МІТ	Copyright (c) 2014, 2015, 2016, 2017, 2018 Simon Lydell
js-yaml	МІТ	Copyright (c) 2011-2015 by Vitaly Puzrin
jsdom	МІТ	The copyright for this library is unknown
jsesc	МІТ	The copyright for this library is unknown
json-parse-even-better-errors	МІТ	The copyright for this library is unknown
json-schema-traverse	МІТ	Copyright (c) 2017 Evgeny Poberezkin
json-stable-stringify-without- jsonify	МІТ	The copyright for this library is unknown
json5	МІТ	The copyright for this library is unknown
jsonfile	МІТ	Copyright (c) 2012-2015, JP Richardson
jss	МІТ	Copyright (c) 2014-present Oleg Isonen (Slobodskoi) & contributors
jss-plugin-camel-case	MIT	Copyright (c) 2014-present Oleg Isonen (Slobodskoi) & contributors
jss-plugin-default-unit	MIT	Copyright (c) 2014-present Oleg Isonen (Slobodskoi) & contributors
jss-plugin-global	MIT	Copyright (c) 2014-present Oleg Isonen (Slobodskoi) & contributors
jss-plugin-nested	МІТ	Copyright (c) 2014-present Oleg Isonen (Slobodskoi) & contributors
jss-plugin-props-sort	МІТ	Copyright (c) 2014-present Oleg Isonen (Slobodskoi) & contributors
jss-plugin-rule-value-function	МІТ	Copyright (c) 2014-present Oleg Isonen (Slobodskoi) & contributors
jss-plugin-vendor-prefixer	МІТ	Copyright (c) 2014-present Oleg Isonen (Slobodskoi) & contributors
jsx-ast-utils	МІТ	The copyright for this library is unknown
kind-of	MIT	Copyright (c) 2014-2017, Jon Schlinkert
kleur	MIT	Copyright (c) Luke Edwards

Component	License	Copyright
		(lukeed.com)
known-css-properties	MIT	Copyright (c) 2017 Mavrix Technologies
language-subtag-registry	CC0-1.0	The copyright for this library is unknown
language-tags	МІТ	The copyright for this library is unknown
leven	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
levn	МІТ	Copyright (c) George Zahariev
lines-and-columns	міт	Copyright (c) 2015 Brian Donovan
locate-path	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
lodash	MIT AND CC0-1.0	copyright Jeremy Ashkenas, DocumentCloud and Investigative Reporters & Editors
lodash-es	MIT AND CC0-1.0	copyright Jeremy Ashkenas, DocumentCloud and Investigative Reporters & Editors
lodash.clonedeep	MIT AND CC0-1.0	copyright Jeremy Ashkenas, DocumentCloud and Investigative Reporters & Editors
lodash.debounce	MIT AND CC0-1.0	copyright Jeremy Ashkenas, DocumentCloud and Investigative Reporters & Editors
lodash.isplainobject	MIT AND CC0-1.0	copyright Jeremy Ashkenas, DocumentCloud and Investigative Reporters & Editors
lodash.memoize	MIT AND CC0-1.0	copyright Jeremy Ashkenas, DocumentCloud and Investigative Reporters & Editors
lodash.merge	MIT AND CC0-1.0	copyright Jeremy Ashkenas, DocumentCloud and Investigative Reporters & Editors
lodash.truncate	MIT AND CC0-1.0	copyright Jeremy Ashkenas, DocumentCloud and Investigative Reporters & Editors
lodash.uniq	MIT AND CC0-1.0	copyright Jeremy Ashkenas, DocumentCloud and Investigative Reporters & Editors
lodash.uniqwith	MIT AND CC0-1.0	copyright Jeremy Ashkenas, DocumentCloud and Investigative Reporters & Editors

Component	License	Copyright
loose-envify	МІТ	Copyright (c) 2015 Andres Suarez
lru-cache	ISC	Copyright (c) Isaac Z. Schlueter and Contributors
lz-string	WTFPL	The copyright for this library is unknown
magic-string	MIT	Copyright 2018 Rich Harris
make-dir	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
makeerror	BSD-3-Clause	Copyright (c) 2014, Naitik Shah
map-obj	міт	Copyright (c) Sindre Sorhus (sindresorhus.com)
material-colors	ISC	Copyright 2014 Shuhei Kagawa
mathml-tag-names	MIT	Copyright (c) 2016 Titus Wormer
memory-fs	міт	Copyright JS Foundation and other contributors
meow	міт	Copyright (c) Sindre Sorhus (https://sindresorhus.com)
merge-stream	міт	Copyright (c) Stephen Sugden (stephensugden.com)
merge2	міт	Copyright (c) 2014-2020 Teambition
micromatch	МІТ	Copyright (c) 2014-2018, Jon Schlinkert
mi me-db	МІТ	Copyright (c) 2014 Jonathan Ong me@jongleberry.com
mi me-types	МІТ	Copyright (c) 2015 Douglas Christopher Wilson
mimic-fn	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
min-indent	MIT	Copyright (c) Sindre Sorhus
minimatch	ISC	Copyright (c) Isaac Z. Schlueter and Contributors
minimist	МІТ	The copyright for this library is unknown
minimist-options	МІТ	Copyright (c) Vadim Demedes (vadimdemedes.com)
moment	МІТ	Copyright (c) JS Foundation and other contributors
ms	МІТ	The copyright for this library is unknown
nanoid	МІТ	Copyright 2017 Andrey Sitnik
natural-compare	МІТ	The copyright for this library is unknown
natural-compare-lite	МІТ	The copyright for this library is unknown
node-fetch	МІТ	The copyright for this library is unknown
node-int64	MIT	Copyright (c) 2014 Robert Kieffer
node-releases	МІТ	Copyright (c) 2017 Sergey Rubanov (https://github.com/ chicoxyzzy)

Component	License	Copyright
normalize-package-data	BSD-2-Clause	Copyright (c) Meryn Stol 'Author
normalize-path	МІТ	Copyright (c) 2014-2018, Jon Schlinkert
npm-run-path	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
nwsapi	МІТ	Copyright (c) 2007-2019 Diego Perini (http://www.iport.it/)
object-assign	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
object-inspect	МІТ	Copyright (c) 2013 James Halliday
object-is	МІТ	Copyright (c) 2014 Jordan Harband
object-keys	МІТ	Copyright (c) 2013 Jordan Harband
object.assign	МІТ	Copyright (c) 2014 Jordan Harband
object.entries	МІТ	Copyright (c) 2015 Jordan Harband
object.fromentries	МІТ	Copyright (c) 2018 Jordan Harband
object.hasown	МІТ	Copyright (c) 2016 Glen Mailer, Jordan Harband, and contributors
object.values	МІТ	Copyright (c) 2015 Jordan Harband
once	ISC	Copyright (c) Isaac Z. Schlueter and Contributors
onetime	МІТ	Copyright (c) Sindre Sorhus (https://sindresorhus.com)
optionator	MIT	Copyright (c) George Zahariev
p-limit	міт	Copyright (c) Sindre Sorhus (sindresorhus.com)
p-locate	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
p-try	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
parent-module	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
parse-json	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
parse5	МІТ	Copyright (c) 2013-2019 Ivan Nikulin (ifaaan@gmail.com, https://github.com/inikulin)
path-exists	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
path-is-absolute	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
path-key	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
path-parse	МІТ	Copyright (c) 2015 Javier Blanco
path-type	МІТ	Copyright (c) Sindre Sorhus

Component	License	Copyright
		(sindresorhus.com)
picocolors	ISC	Copyright (c) 2021 Alexey Raspopov, Kostiantyn Denysov, Anton Verinov
picomatch	МІТ	Copyright (c) 2017-present, Jon Schlinkert
pirates	МІТ	Copyright (c) 2016-2018 Ari Porad
pkg-dir	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
polly-js	МІТ	Copyright (c) 2015 Maurice de Beijer
popper.js	МІТ	The copyright for this library is unknown
postcss	MIT	Copyright 2013 Andrey Sitnik
postcss-media-query-parser	МІТ	The copyright for this library is unknown
postcss-resolve-nested-selector	МІТ	Copyright (c) 2016 David Clark
postcss-safe-parser	МІТ	Copyright 2013 Andrey Sitnik
postcss-scss	МІТ	Copyright 2013 Andrey Sitnik
postcss-selector-parser	міт	The copyright for this library is unknown
postcss-value-parser	MIT	Copyright (c) Bogdan Chadkin
prelude-Is	МІТ	Copyright (c) George Zahariev
prettier	міт	Copyright (c) James Long and contributors
prettier-linter-helpers	МІТ	The copyright for this library is unknown
pretty-format	МІТ	Copyright (c) Facebook, Inc. and its affiliates
process-nextick-args	МІТ	The copyright for this library is unknown
promise	МІТ	Copyright (c) 2014 Forbes Lindesay
prompts	МІТ	Copyright (c) 2018 Terkel Gjervig Nielsen
prop-types	МІТ	Copyright (c) 2013-present, Facebook, Inc.
prr	МІТ	The copyright for this library is unknown
psl	МІТ	Copyright (c) 2017 Lupo Montero Iupomontero@gmail.com
punycode	МІТ	The copyright for this library is unknown
querystringify	МІТ	Copyright (c) 2015 Unshift.io, Arnout Kazemier
queue-microtask	МІТ	Copyright (c) Feross Aboukhadijeh
quick-Iru	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
react	МІТ	Copyright (c) Facebook, Inc. and

Component	License	Copyright
		its affiliates
react-color	МІТ	Copyright (c) 2015 Case Sandberg
react-dnd	MIT	Copyright (c) 2016 Dan Abramov
react-dnd-touch-backend	MIT	Copyright (c) 2015 Dan Abramov
react-dom	міт	Copyright (c) Facebook, Inc. and its affiliates
react-extras	міт	Copyright (c) Sindre Sorhus (sindresorhus.com)
react-i18next	МІТ	Copyright (c) 2021 i18next
react-is	міт	Copyright (c) Facebook, Inc. and its affiliates
react-lifecycles-compat	міт	The copyright for this library is unknown
react-measure	МІТ	Copyright (c) 2018 React Measure
react-redux	МІТ	The copyright for this library is unknown
react-refresh	МІТ	Copyright (c) Facebook, Inc. and its affiliates
react-split-pane	MIT	Copyright (c) 2015 tomkp
react-style-proptype	МІТ	Copyright 2016 Frankie Bagnardi
react-transition-group	BSD-3-Clause	Copyright 2013-present, Facebook, Inc.
reactcss	МІТ	Copyright (c) 2015 Case Sandberg
read-pkg	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
read-pkg-up	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
readable-stream	МІТ	Copyright Joyent, Inc. and other Node contributors
readdir-enhanced	МІТ	Copyright (c) 2016 James Messinger
readdirp	МІТ	Copyright (c) 2012-2015 Thorsten Lorenz
redent	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
redux	МІТ	The copyright for this library is unknown
redux-mock-store	МІТ	The copyright for this library is unknown
redux-thunk	МІТ	The copyright for this library is unknown
regenerate	МІТ	The copyright for this library is unknown
regenerate-unicode-properties	МІТ	The copyright for this library is unknown
regenerator-runtime	МІТ	Copyright (c) 2014-present, Facebook, Inc.
regenerator-transform	MIT	Copyright (c) 2014-present,

Component	License	Copyright
		Facebook, Inc.
regexp.prototype.flags	МІТ	Copyright (c) 2014 Jordan Harband
regexpp	МІТ	Copyright (c) 2018 Toru Nagashima
regexpu-core	МІТ	The copyright for this library is unknown
regjsgen	МІТ	The copyright for this library is unknown
regjsparser	BSD-2-Clause AND BSD-3-Clause	The copyright for this library is unknown
require-directory	МІТ	Copyright (c) 2011 Troy Goode
require-from-string	МІТ	Copyright (c) Vsevolod Strukchinsky
requireindex	МІТ	The copyright for this library is unknown
requires-port	МІТ	Copyright (c) 2015 Unshift.io, Arnout Kazemier
reselect	МІТ	Copyright (c) 2015-2018 Reselect
resize-observer-polyfill	МІТ	Copyright (c) 2016 Denis Rul
resolve	МІТ	Copyright (c) 2012 James Halliday
resolve/test/resolver/multirepo	МІТ	The copyright for this library is unknown
resolve/test/resolver/ multirepo/packages/package-a	MIT	The copyright for this library is unknown
resolve/test/resolver/ multirepo/packages/package-b	MIT	The copyright for this library is unknown
resolve/test/resolver/ nested_symlinks/mylib	ISC	The copyright for this library is unknown
resolve-cwd	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
resolve-from	MIT	Copyright (c) Sindre Sorhus (sindresorhus.com)
resolve.exports	МІТ	Copyright (c) Luke Edwards (lukeed.com)
reusify	МІТ	Copyright (c) 2015 Matteo Collina
rifm	МІТ	The copyright for this library is unknown
rimraf	ISC	Copyright (c) Isaac Z. Schlueter and Contributors
rollup	МІТ	The copyright for this library is unknown
run-parallel	MIT	Copyright (c) Feross Aboukhadijeh
run-script-os	MIT	Copyright (c) 2017 Charlie Guse
safe-buffer	МІТ	Copyright (c) Feross Aboukhadijeh
safe-regex-test	МІТ	Copyright (c) 2022 Jordan Harband

Component	License	Copyright
safer-buffer	МІТ	Copyright (c) 2018 Nikita Skovoroda
saxes	ISC	The copyright for this library is unknown
scheduler	МІТ	Copyright (c) Facebook, Inc. and its affiliates
semver	ISC	Copyright (c) Isaac Z. Schlueter and Contributors
setimmediate	МІТ	The copyright for this library is unknown
shebang-command	MIT	Copyright (c) Kevin Martensson
shebang-regex	MIT	Copyright (c) Sindre Sorhus (sindresorhus.com)
side-channel	МІТ	Copyright (c) 2019 Jordan Harband
signal-exit	ISC	The copyright for this library is unknown
sisteransi	МІТ	Copyright (c) 2018 Terkel Gjervig Nielsen
slash	MIT	Copyright (c) Sindre Sorhus (sindresorhus.com)
slice-ansi	MIT	Copyright (c) DC
source-map	BSD-3-Clause	Copyright (c) 2009-2011, Mozilla Foundation and contributors
source-map-js	BSD-3-Clause	Copyright (c) 2009-2011, Mozilla Foundation and contributors
source-map-support	MIT	The copyright for this library is unknown
sourcemap-codec	MIT	Copyright (c) 2015 Rich Harris
spdx-correct	Apache-2.0	The copyright for this library is unknown
spdx-exceptions	СС-ВҮ-3.0	The copyright for this library is unknown
spdx-expression-parse	MIT	Copyright (c) 2015 Kyle E. Mitchell
spdx-license-ids	CC0-1.0	The copyright for this library is unknown
sprintf-js	BSD-3-Clause	Copyright (c) 2007-2014, Alexandru Marasteanu
stack-utils	MIT	Copyright (c) Isaac Z. Schlueter , James Talmage (github.com/ jamestalmage), and Contributors
string-length	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
string-width	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
string.prototype.matchall	МІТ	Copyright (c) 2015 Jordan Harband
string.prototype.trimend	МІТ	Copyright (c) 2017 Khaled Al- Ansari

Component	License	Copyright
string.prototype.trimstart	МІТ	Copyright (c) 2017 Khaled Al- Ansari
string_decoder	міт	Copyright Joyent, Inc. and other Node contributors
strip-ansi	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
strip-bom	міт	Copyright (c) Sindre Sorhus (sindresorhus.com)
strip-final-newline	міт	Copyright (c) Sindre Sorhus (sindresorhus.com)
strip-indent	міт	Copyright (c) Sindre Sorhus (sindresorhus.com)
strip-json-comments	міт	Copyright (c) Sindre Sorhus (https://sindresorhus.com)
style-search	ISC	Copyright (c) 2016, David Clark
stylelint	MIT	Copyright (c) 2015 - present Maxime Thirouin, David Clark & Richard Hallows
stylelint-config-prettier	MIT	Copyright (c) 2017 Simon Lydell
stylelint-config-prettier-scss	МІТ	Copyright (c) 2017 Simon Lydell
stylelint-config-recommended	MIT	Copyright (c) 2018 - present stylelint
stylelint-config-recommended- scss	МІТ	Copyright (c) 2016 Krister Kari
stylelint-config-standard	МІТ	Copyright (c) 2015 - present stylelint
stylelint-config-standard-scss	МІТ	Copyright (c) 2021 Present stylelint-scss authors
stylelint-css-modules	МІТ	The copyright for this library is unknown
stylelint-scss	MIT	Copyright (c) 2016 Krister Kari
supports-color	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
supports-hyperlinks	MIT	Copyright (c) James Talmage
supports-preserve-symlinks-flag	MIT	Copyright (c) 2022 Inspect JS
svg-tags	МІТ	Copyright (c) 2014 Athan Reines
symbol-tree	MIT	Copyright (c) 2015 Joris van der Wel
sync-directory	ISC	The copyright for this library is unknown
table	BSD-3-Clause	Copyright (c) 2018, Gajus Kuizinas (http://gajus.com/)
tapable	МІТ	Copyright (c) Tobias Koppers
test-exclude	ISC	The copyright for this library is unknown
text-table	MIT	The copyright for this library is unknown
tiny-warning	МІТ	Copyright (c) 2019 Alexander Reardon
tinycolor2	МІТ	Copyright (c), Brian Grinstead, http://briangrinstead.com

Component	License	Copyright
tmpl	BSD-3-Clause	Copyright (c) 2014, Naitik Shah
to-fast-properties	міт	Copyright (c) 2014 Petka Antonov 2015 Sindre Sorhus
to-regex-range	міт	Copyright (c) 2015-present, Jon Schlinkert
tough-cookie	BSD-3-Clause	Copyright (c) 2015, Salesforce.com, Inc.
tr46	міт	The copyright for this library is unknown
trim-newlines	міт	Copyright (c) Sindre Sorhus (sindresorhus.com)
ts-dedent	міт	Copyright (c) 2018 Tamino Martinius
tsconfig-paths	МІТ	Copyright (c) 2016 Jonas Kello
tslib	OBSD	The copyright for this library is unknown
tsutils	міт	Copyright (c) 2017 Klaus Meinhardt
type-check	МІТ	Copyright (c) George Zahariev
type-detect	міт	Copyright (c) 2013 Jake Luer (http://alogicalparadox.com)
type-fest	міт	Copyright (c) Sindre Sorhus (sindresorhus.com)
typed-array-length	МІТ	Copyright (c) 2020 Inspect JS
typescript	Apache-2.0	The copyright for this library is unknown
ua-parser-js	міт	The copyright for this library is unknown
unbox-primitive	міт	Copyright (c) 2019 Jordan Harband
unc-path-regex	міт	Copyright (c) 2015, Jon Schlinkert
unicode-canonical-property- names-ecmascript	міт	The copyright for this library is unknown
unicode-match-property- ecmascript	міт	The copyright for this library is unknown
unicode-match-property-value- ecmascript	міт	The copyright for this library is unknown
unicode-property-aliases- ecmascript	міт	The copyright for this library is unknown
universalify	міт	Copyright (c) 2017, Ryan Zimmerman
update-browserslist-db	міт	Copyright 2022 Andrey Sitnik and other contributors
uri-js	BSD-2-Clause	Copyright 2011 Gary Court
url-parse	міт	Copyright (c) 2015 Unshift.io, Arnout Kazemier
use-sync-external-store	міт	Copyright (c) Facebook, Inc. and its affiliates
util-deprecate	міт	Copyright (c) 2014 Nathan Rajlich
uuid	МІТ	The copyright for this library is

Component	License	Copyright
		unknown
v8-compile-cache	МІТ	Copyright (c) 2019 Andres Suarez
v8-to-istanbul	ISC	The copyright for this library is unknown
validate-npm-package-license	Apache-2.0	The copyright for this library is unknown
vite	МІТ	The copyright for this library is unknown
void-elements	MIT	Copyright (c) 2014 hemanth
w3c-xmlserializer	МІТ	The copyright for this library is unknown
walker	Apache-2.0	Copyright 2013 Naitik Shah
webidl-conversions	BSD-2-Clause	The copyright for this library is unknown
whatwg-encoding	МІТ	The copyright for this library is unknown
whatwg-mimetype	МІТ	The copyright for this library is unknown
whatwg-url	МІТ	The copyright for this library is unknown
which	ISC	Copyright (c) Isaac Z. Schlueter and Contributors
which-boxed-primitive	МІТ	Copyright (c) 2019 Jordan Harband
which-collection	MIT	Copyright (c) 2019 Inspect JS
which-typed-array	МІТ	Copyright (c) 2015 Jordan Harband
word-wrap	МІТ	Copyright (c) 2014-2017, Jon Schlinkert
wrap-ansi	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
wrappy	ISC	Copyright (c) Isaac Z. Schlueter and Contributors
write-file-atomic	ISC	Copyright (c) 2015, Rebecca Turner
ws	МІТ	Copyright (c) 2011 Einar Otto Stangvik
x-is-object	МІТ	The copyright for this library is unknown
xml-name-validator	Apache-2.0	The copyright for this library is unknown
xmlchars	MIT	Copyright Louis-Dominique Dubeau and contributors
y18n	ISC	Copyright (c) 2015, Contributors
yallist	ISC	Copyright (c) Isaac Z. Schlueter and Contributors
yaml	ISC	Copyright 2018 Eemeli Aro
yargs	МІТ	Copyright 2014 Contributors (ben@npmjs.com)
yargs-parser	ISC	The copyright for this library is unknown

Component	License	Copyright
yocto-queue	МІТ	Copyright (c) Sindre Sorhus (https://sindresorhus.com)
babel/helper-builder-react-jsx	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/helper-builder-react-jsx- experimental	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/helper-define-map	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/helper-get-function-arity	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/helper-regex	MIT	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform-react- constant-elements	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform-react- jsx-self	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/plugin-transform-react- jsx-source	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
babel/runtime-corejs3	МІТ	Copyright (c) 2014-present Sebastian McKenzie and other contributors
cnakazawa/watch	Apache-2.0	The copyright for this library is unknown
csstools/convert-colors	CC0-1.0	The copyright for this library is unknown
csstools/normalize.css	CC0-1.0	The copyright for this library is unknown
hapi/address	BSD-3-Clause	The copyright for this library is unknown
hapi/bourne	BSD-3-Clause	The copyright for this library is unknown
hapi/hoek	BSD-3-Clause	The copyright for this library is unknown
hapi/joi	BSD-3-Clause	The copyright for this library is unknown
hapi/topo	BSD-3-Clause	The copyright for this library is unknown
mrmlnc/readdir-enhanced	міт	Copyright (c) 2016 James Messinger
svgr/babel-plugin-add-jsx- attribute	міт	Copyright 2017 Smooth
svgr/babel-plugin-remove-jsx- attribute	міт	Copyright 2017 Smooth
svgr/babel-plugin-remove-jsx- empty-expression	MIT	Copyright 2017 Smooth

Component	License	Copyright
svgr/babel-plugin-replace-jsx- attribute-value	МІТ	Copyright 2017 Smooth
svgr/babel-plugin-svg-dynamic- title	МІТ	Copyright 2017 Smooth
svgr/babel-plugin-svg-em- dimensions	МІТ	Copyright 2017 Smooth
svgr/babel-plugin-transform- react-native-svg	МІТ	Copyright 2017 Smooth
svgr/babel-plugin-transform- svg-component	МІТ	Copyright 2017 Smooth
svgr/babel-preset	МІТ	Copyright 2017 Smooth
svgr/cli	МІТ	Copyright 2017 Smooth
svgr/core	МІТ	Copyright 2017 Smooth
svgr/hast-util-to-babel-ast	MIT	Copyright 2017 Smooth
svgr/plugin-jsx	MIT	Copyright 2017 Smooth
svgr/plugin-prettier	MIT	Copyright 2017 Smooth
svgr/plugin-svgo	MIT	Copyright 2017 Smooth
svgr/webpack	МІТ	Copyright 2017 Smooth
testing-library/user-event	МІТ	Copyright (c) 2020 Giorgio Polvara
types/color-name	МІТ	Copyright (c) Microsoft Corporation
types/detect-hover	МІТ	Copyright (c) Microsoft Corporation
types/detect-passive-events	МІТ	Copyright (c) Microsoft Corporation
types/detect-pointer	МІТ	Copyright (c) Microsoft Corporation
types/detect-touch-events	МІТ	Copyright (c) Microsoft Corporation
types/glob	МІТ	Copyright (c) Microsoft Corporation
types/minimatch	МІТ	Copyright (c) Microsoft Corporation
types/q	МІТ	Copyright (c) Microsoft Corporation
types/react-redux	МІТ	Copyright (c) Microsoft Corporation
typescript-eslint/experimental- utils	МІТ	Copyright (c) 2019 TypeScript ESLint and other contributors
webassemblyjs/ast	MIT	Copyright (c) 2018 Sven Sauleau
webassemblyjs/floating-point- hex-parser	міт	Copyright (c) 2017 Mauro Bringolf
webassemblyjs/helper-api-error	MIT	Copyright (c) 2018 Sven Sauleau
webassemblyjs/helper-buffer	МІТ	Copyright (c) 2018 Sven Sauleau
webassemblyjs/helper-code- frame	МІТ	Copyright (c) 2018 Sven Sauleau
webassemblyjs/helper-fsm	MIT	Copyright (c) 2018 Sven Sauleau
webassemblyjs/helper-module- context	міт	Copyright (c) 2018 Sven Sauleau
webassemblyjs/helper-wasm-	МІТ	Copyright (c) 2018 Sven Sauleau

Component	License	Copyright
bytecode		
webassemblyjs/helper-wasm- section	міт	Copyright (c) 2018 Sven Sauleau
webassemblyjs/ieee754	МІТ	Copyright (c) 2018 Sven Sauleau
webassemblyjs/leb128	міт	The copyright for this library is unknown
webassemblyjs/utf8	МІТ	Copyright (c) 2018 Sven Sauleau
webassemblyjs/wasm-edit	МІТ	Copyright (c) 2018 Sven Sauleau
webassemblyjs/wasm-gen	MIT	Copyright (c) 2018 Sven Sauleau
webassemblyjs/wasm-opt	MIT	Copyright (c) 2018 Sven Sauleau
webassemblyjs/wasm-parser	МІТ	Copyright (c) 2018 Sven Sauleau
webassemblyjs/wast-parser	МІТ	Copyright (c) 2018 Sven Sauleau
webassemblyjs/wast-printer	МІТ	Copyright (c) 2018 Sven Sauleau
webcomponents/ webcomponentsjs	BSD-3-Clause	The copyright for this library is unknown
xtuc/ieee754	BSD-3-Clause	Copyright (c) 2008, Fair Oaks Labs, Inc.
xtuc/long	Apache-2.0	The copyright for this library is unknown
accepts	міт	Copyright (c) 2015 Douglas Christopher Wilson
address	МІТ	The copyright for this library is unknown
adjust-sourcemap-loader	міт	The copyright for this library is unknown
aggregate-error	міт	Copyright (c) Sindre Sorhus (sindresorhus.com)
ajv-errors	міт	Copyright (c) 2017 Evgeny Poberezkin
ajv-keywords	міт	Copyright (c) 2016 Evgeny Poberezkin
alphanum-sort	МІТ	Copyright (c) Bogdan Chadkin
ansi-colors	міт	Copyright (c) 2015-present, Brian Woodward
ansi-html	Apache-2.0	The copyright for this library is unknown
antlr4ts	BSD-3-Clause	Copyright (c) 2016 The ANTLR Project
aproba	ISC	Copyright (c) 2015, Rebecca Turner
arity-n	МІТ	Copyright (c) 2015 Christoph Hermann
arr-diff	МІТ	Copyright (c) 2014-2017, Jon Schlinkert
arr-flatten	міт	Copyright (c) 2014-2017, Jon Schlinkert
arr-union	міт	Copyright (c) 2014-2016, Jon Schlinkert
array-equal	міт	Copyright (c) 2014 Jonathan Ong me@jongleberry.com
array-flatten	міт	Copyright (c) 2014 Blake Embrey

Component	License	Copyright
		(hello@blakeembrey.com)
array-from	МІТ	The copyright for this library is unknown
array-uniq	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
array-unique	МІТ	Copyright (c) 2014-2016, Jon Schlinkert
asn1	MIT	Copyright (c) 2011 Mark Cavage
asn1.js	МІТ	Copyright (c) 2017 Fedor Indutny
assert	МІТ	Copyright Joyent, Inc. and other Node contributors
assert-plus	МІТ	The copyright for this library is unknown
assign-symbols	МІТ	Copyright (c) 2015, Jon Schlinkert
async	МІТ	Copyright (c) 2010-2018 Caolan McMahon
async-each	МІТ	The copyright for this library is unknown
async-limiter	МІТ	Copyright (c) 2017 Samuel Reed
at-least-node	ISC	Copyright (c) 2020 Ryan Zimmerman
atob	MIT AND Apache-2.0	Copyright 2015 AJ ONeal
autoprefixer	MIT	Copyright 2013 Andrey Sitnik
aws-sign2	Apache-2.0	The copyright for this library is unknown
aws4	МІТ	Copyright 2013 Michael Hart (michael.hart.au@gmail.com)
babel-code-frame	МІТ	The copyright for this library is unknown
babel-core	МІТ	The copyright for this library is unknown
babel-extract-comments	МІТ	Copyright (c) 2015, 2018, Jon Schlinkert
babel-generator	МІТ	The copyright for this library is unknown
babel-helpers	МІТ	The copyright for this library is unknown
babel-messages	МІТ	The copyright for this library is unknown
babel-plugin-dynamic-import- node	МІТ	Copyright (c) 2016 Airbnb
babel-plugin-macros	MIT	Copyright (c) 2017 Kent C. Dodds
babel-plugin-syntax-object-rest- spread	МІТ	The copyright for this library is unknown
babel-plugin-transform-object- rest-spread	МІТ	The copyright for this library is unknown
babel-plugin-transform-react- remove-prop-types	МІТ	Copyright (c) 2015 Nikita Gusakov
babel-preset-react-app	МІТ	Copyright (c) 2013-present, Facebook, Inc.

Component	License	Copyright
babel-register	МІТ	The copyright for this library is unknown
babel-runtime	МІТ	The copyright for this library is unknown
babel-template	МІТ	The copyright for this library is unknown
babel-traverse	МІТ	The copyright for this library is unknown
babel-types	МІТ	The copyright for this library is unknown
babylon	МІТ	Copyright (c) 2012-2014 by various contributors
base	МІТ	Copyright (c) 2015-2017, Jon Schlinkert
base64-js	MIT	Copyright (c) 2014 Jameson Little
batch	MIT	Copyright (c) 2013 TJ Holowaychuk
bcrypt-pbkdf	BSD-3-Clause AND ISC	Copyright 2016, Joyent Inc
big.js	MIT	The copyright for this library is unknown
bluebird	MIT	Copyright (c) 2013-2018 Petka Antonov
bn.js	MIT	The copyright for this library is unknown
body-parser	МІТ	Copyright (c) 2014-2015 Douglas Christopher Wilson
bonjour	MIT	Copyright (c) 2015-2016 Thomas Watson Steen
boolbase	ISC	The copyright for this library is unknown
brorand	MIT	The copyright for this library is unknown
browser-process-hrtime	BSD-2-Clause	Copyright 2014 kumavis
browser-resolve	МІТ	Copyright (c) 2013-2015 Roman Shtylman
browserify-aes	MIT	Copyright (c) 2014-2017 browserify-aes contributors
browserify-cipher	MIT	Copyright (c) 2014-2017 Calvin Metcalf & contributors
browserify-des	MIT	Copyright (c) 2014-2017 Calvin Metcalf, Fedor Indutny & contributors
browserify-rsa	МІТ	Copyright (c) 2014-2015 Calvin Metcalf & contributors
browserify-sign	ISC	Copyright (c) 2014-2015 Calvin Metcalf and browserify-sign contributors
browserify-zlib	MIT	Copyright Joyent, Inc. and other Node contributors
buffer	MIT	Copyright (c) Feross Aboukhadijeh, and other

Component	License	Copyright
		contributors
buffer-indexof	MIT	Copyright (c) 2013 Ryan Day
buffer-xor	МІТ	Copyright (c) 2015 Daniel Cousens
builtin-status-codes	MIT	Copyright (c) Ben Drucker
bytes	MIT	Copyright (c) 2015 Jed Watson
cacache	ISC	The copyright for this library is unknown
cache-base	МІТ	Copyright (c) 2014-2017, Jon Schlinkert
caller-callsite	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
caller-path	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
camel-case	МІТ	Copyright (c) 2014 Blake Embrey (hello@blakeembrey.com)
caniuse-api	МІТ	Copyright (c) 2014 Sebastien Balayn
capture-exit	ISC	The copyright for this library is unknown
case-sensitive-paths-webpack- plugin	міт	Copyright (c) 2018 Michael Pratt
caseless	Apache-2.0	The copyright for this library is unknown
chardet	МІТ	Copyright (c) 2018 Dmitry Shirokov
chownr	ISC	Copyright (c) Isaac Z. Schlueter and Contributors
chrome-trace-event	МІТ	The copyright for this library is unknown
cipher-base	МІТ	Copyright (c) 2017 crypto- browserify contributors
class-utils	МІТ	Copyright (c) 2015, 2017-2018, Jon Schlinkert
clean-css	МІТ	Copyright (c) 2017 JakubPawlowicz.com
clean-stack	міт	Copyright (c) Sindre Sorhus (sindresorhus.com)
cli-cursor	міт	Copyright (c) Sindre Sorhus (sindresorhus.com)
cli-width	ISC	Copyright (c) 2015, Ilya Radchenko
clone-deep	МІТ	Copyright (c) 2014-2015, Jon Schlinkert
соа	МІТ	Copyright (c) 2015-present Sergey Berezhnoy
collection-visit	міт	Copyright (c) 2015, 2017, Jon Schlinkert
color	міт	Copyright (c) 2012 Heather Arthur
color-string	міт	Copyright (c) 2011 Heather Arthur

Component	License	Copyright
colorette	МІТ	The copyright for this library is unknown
colors	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
common-tags	МІТ	The copyright for this library is unknown
commondir	МІТ	Copyright (c) 2013 James Halliday (mail@substack.net)
component-emitter	МІТ	Copyright (c) 2014 Component
compose-function	МІТ	The copyright for this library is unknown
compressible	міт	Copyright (c) 2015 Douglas Christopher Wilson
compression	МІТ	Copyright (c) 2014-2015 Douglas Christopher Wilson
concat-stream	MIT	Copyright (c) 2013 Max Ogden
configstore	BSD-3-Clause	The copyright for this library is unknown
connect-history-api-fallback	міт	Copyright (c) 2012 Ben Ripkens http://bripkens.de
console-browserify	МІТ	The copyright for this library is unknown
constants-browserify	МІТ	The copyright for this library is unknown
contains-path	МІТ	Copyright (c) 2015, Jon Schlinkert
content-disposition	МІТ	Copyright (c) 2014-2017 Douglas Christopher Wilson
content-type	МІТ	Copyright (c) 2015 Douglas Christopher Wilson
cookie	МІТ	Copyright (c) 2015 Douglas Christopher Wilson
cookie-signature	МІТ	The copyright for this library is unknown
copy-concurrently	ISC	Copyright (c) 2017, Rebecca Turner
copy-descriptor	МІТ	Copyright (c) 2015-2016, Jon Schlinkert
core-js-pure	МІТ	Copyright (c) 2014-2020 Denis Pushkarev
create-ecdh	МІТ	Copyright (c) 2014-2017 createECDH contributors
create-hash	МІТ	Copyright (c) 2017 crypto- browserify contributors
create-hmac	міт	Copyright (c) 2017 crypto- browserify contributors
crypto-browserify	MIT	Copyright (c) 2013 Dominic Tarr
css	МІТ	Copyright (c) 2012 TJ Holowaychuk
css-blank-pseudo	CC0-1.0	The copyright for this library is unknown
css-color-names	МІТ	The copyright for this library is

Component	License	Copyright
		unknown
css-declaration-sorter	МІТ	The copyright for this library is unknown
css-has-pseudo	CC0-1.0	The copyright for this library is unknown
css-loader	міт	Copyright JS Foundation and other contributors
css-prefers-color-scheme	CC0-1.0	The copyright for this library is unknown
css-select	BSD-2-Clause	Copyright (c) Felix Bohm
css-select-base-adapter	MIT	Copyright (c) 2018 Nik Coughlin
css-tree	міт	Copyright (c) 2016-2019 by Roman Dvornov
css-what	BSD-2-Clause	Copyright (c) Felix Bohm
cssdb	CC0-1.0	The copyright for this library is unknown
cssnano	міт	The copyright for this library is unknown
cssnano-preset-default	міт	The copyright for this library is unknown
cssnano-util-get-arguments	МІТ	The copyright for this library is unknown
cssnano-util-get-match	міт	The copyright for this library is unknown
cssnano-util-raw-cache	МІТ	The copyright for this library is unknown
cssnano-util-same-parent	МІТ	The copyright for this library is unknown
csso	міт	Copyright (c) 2011-2015 by Sergey Kryzhanovsky
cubus-typedoc-dark-theme	Apache-2.0	The copyright for this library is unknown
cyclist	МІТ	Copyright (c) 2015 Mathias Buus
d	ISC	Copyright (c) 2013-2019, Mariusz Nowak, medikoo, medikoo.com
dashdash	МІТ	The copyright for this library is unknown
dashify	МІТ	Copyright (c) 2015-present, Jon Schlinkert
decode-uri-component	MIT	Copyright (c) Sam Verschueren
deep-extend	МІТ	Copyright (c) 2013-2018, Viacheslav Lotsmanov
default-gateway	BSD-2-Clause	Copyright (c) silverwind
define-property	МІТ	Copyright (c) 2015, Jon Schlinkert
del	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
depd	МІТ	Copyright (c) 2014-2017 Douglas Christopher Wilson
des.js	MIT	The copyright for this library is

Component	License	Copyright
		unknown
destroy	МІТ	Copyright (c) 2014 Jonathan Ong me@jongleberry.com
detect-file	МІТ	Copyright (c) 2016-2017, Brian Woodward
detect-hover	МІТ	Copyright (c) 2016 Rafael Pedicini
detect-indent	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
detect-node	MIT	Copyright (c) 2017 Ilya Kantor
detect-passive-events	МІТ	Copyright (c) 2016 Rafael Pedicini
detect-pointer	МІТ	Copyright (c) 2016 Rafael Pedicini
detect-port-alt	MIT	Copyright (c) 2015 xdf
detect-touch-events	МІТ	Copyright (c) 2016 Rafael Pedicini
diffie-hellman	МІТ	Copyright (c) 2017 Calvin Metcalf
direflow-component	МІТ	The copyright for this library is unknown
direflow-scripts	МІТ	The copyright for this library is unknown
dns-equal	МІТ	Copyright (c) 2016 Thomas Watson Steen
dns-packet	МІТ	Copyright (c) 2016 Mathias Buus
dns-txt	МІТ	Copyright (c) 2015 Thomas Watson Steen
dom-converter	MIT	Copyright (c) 2013 Aria Minaei
dom-serializer	МІТ	Copyright (c) 2014 The cheeriojs contributors
domain-browser	МІТ	The copyright for this library is unknown
domelementtype	BSD-2-Clause	Copyright (c) Felix Bohm
domhandler	BSD-2-Clause	Copyright (c) Felix Bohm
domutils	BSD-2-Clause	Copyright (c) Felix Bohm
dot-case	МІТ	Copyright (c) 2014 Blake Embrey (hello@blakeembrey.com)
dot-prop	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
dotenv	BSD-2-Clause	Copyright (c) 2015, Scott Motte
dotenv-expand	BSD-2-Clause	Copyright (c) 2016, Scott Motte
duplexer	МІТ	The copyright for this library is unknown
duplexify	МІТ	Copyright (c) 2014 Mathias Buus
ecc-jsbn	МІТ	Copyright (c) 2014 Jeremie Miller
ee-first	МІТ	Copyright (c) 2014 Jonathan Ong me@jongleberry.com

Component	License	Copyright
elliptic	МІТ	The copyright for this library is unknown
emojis-list	МІТ	The copyright for this library is unknown
encodeurl	МІТ	Copyright (c) 2016 Douglas Christopher Wilson
end-of-stream	МІТ	Copyright (c) 2014 Mathias Buus
es5-ext	ISC	Copyright (c) 2011-2019, Mariusz Nowak, medikoo, medikoo.com
es6-iterator	MIT	Copyright (c) 2013-2017 Mariusz Nowak (www.medikoo.com)
es 6-s ymbol	ISC	Copyright (c) 2013-2019, Mariusz Nowak, medikoo, medikoo.com
escape-html	МІТ	Copyright (c) 2015 Tiancheng Timothy Gu
eslint-config-react	МІТ	Copyright (c) 2015 Patric Nordmark
esm	МІТ	copyright Ben Newman
etag	МІТ	Copyright (c) 2014-2016 Douglas Christopher Wilson
event-hooks-webpack-plugin	МІТ	The copyright for this library is unknown
eventemitter3	МІТ	Copyright (c) 2014 Arnout Kazemier
events	МІТ	Copyright Joyent, Inc. and other Node contributors
eventsource	МІТ	Copyright (c) EventSource GitHub
evp_bytestokey	МІТ	Copyright (c) 2017 crypto- browserify contributors
exec-sh	МІТ	Copyright (c) 2014 Aleksandr Tsertkov
expand-brackets	МІТ	Copyright (c) 2015-2016, Jon Schlinkert
expand-range	МІТ	Copyright (c) 2014-2016, Jon Schlinkert
expand-tilde	МІТ	Copyright (c) 2015-2016, Jon Schlinkert
express	MIT	Copyright (c) 2014-2015 Douglas Christopher Wilson
ext	ISC	Copyright (c) 2011-2019, Mariusz Nowak, medikoo, medikoo.com
extend	МІТ	Copyright (c) 2014 Stefan Thomas
extend-shallow	МІТ	Copyright (c) 2014-2015, Jon Schlinkert
external-editor	MIT	Copyright (c) 2016 Kevin Gravier

Component	License	Copyright
extglob	МІТ	Copyright (c) 2015-2017, Jon Schlinkert
extsprintf	MIT	Copyright (c) 2012, Joyent, Inc.
faye-websocket	міт	The copyright for this library is unknown
figgy-pudding	ISC	The copyright for this library is unknown
figures	МІТ	Copyright (c) Sindre Sorhus (https://sindresorhus.com)
file-loader	МІТ	Copyright JS Foundation and other contributors
filename-regex	МІТ	Copyright (c) 2014-2015, 2017, Jon Schlinkert
filesize	BSD-3-Clause	Copyright (c) 2019, Jason Mulligan
finalhandler	МІТ	Copyright (c) 2014-2017 Douglas Christopher Wilson
find-cache-dir	MIT	Copyright (c) James Talmage
findup-sync	МІТ	Copyright (c) 2013-2018 Ben Alman , Blaine Bublitz , and Eric Schoffstall
flatten	МІТ	Copyright (c) 2016 Joshua Holbrook
flush-write-stream	МІТ	Copyright (c) 2015 Mathias Buus
follow-redirects	МІТ	Copyright 2014-present Olivier Lalonde , James Talmage , Ruben Verborgh
for-in	МІТ	Copyright (c) 2014-2017, Jon Schlinkert
for-own	МІТ	Copyright (c) 2014-2015, 2017, Jon Schlinkert
forever-agent	Apache-2.0	The copyright for this library is unknown
fork-ts-checker-webpack-plugin	MIT	Copyright (c) 2019 TypeStrong
forwarded	міт	Copyright (c) 2014-2017 Douglas Christopher Wilson
fragment-cache	МІТ	Copyright (c) 2016-2017, Jon Schlinkert
fresh	МІТ	Copyright (c) 2016-2017 Douglas Christopher Wilson
from2	МІТ	The copyright for this library is unknown
fs-minipass	ISC	Copyright (c) Isaac Z. Schlueter and Contributors
fs-write-stream-atomic	ISC	Copyright (c) Isaac Z. Schlueter and Contributors
functional-red-black-tree	МІТ	Copyright (c) 2013 Mikola Lysenko
get-own-enumerable-property- symbols	ISC	Copyright (c) 2019, Shahar Or
get-value	МІТ	Copyright (c) 2014-2016, Jon

Component	License	Copyright
		Schlinkert
getpass	МІТ	Copyright Joyent, Inc.
glob-base	МІТ	Copyright (c) 2015, Jon Schlinkert
got	МІТ	The copyright for this library is unknown
growly	МІТ	The copyright for this library is unknown
gzip-size	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
hammerjs	МІТ	The copyright for this library is unknown
handle-thing	МІТ	The copyright for this library is unknown
handlebars	МІТ	Copyright (c) 2011-2019 by Yehuda Katz
har-schema	ISC	Copyright (c) 2015, Ahmad Nassri
har-validator	МІТ	Copyright (c) 2018 Ahmad Nassri
harmony-reflect	Apache-2.0	The copyright for this library is unknown
has-ansi	МІТ	The copyright for this library is unknown
has-value	МІТ	Copyright (c) 2014-2017, Jon Schlinkert
has-values	МІТ	Copyright (c) 2014-2017, Jon Schlinkert
hash-base	МІТ	Copyright (c) 2016 Kirill Fomichev
hash.js	МІТ	The copyright for this library is unknown
he	МІТ	The copyright for this library is unknown
hex-color-regex	МІТ	The copyright for this library is unknown
hmac-drbg	МІТ	The copyright for this library is unknown
home-or-tmp	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
homedir-polyfill	МІТ	Copyright (c) 2016 Brian Woodward
hpack.js	МІТ	The copyright for this library is unknown
hsl-regex	МІТ	The copyright for this library is unknown
hsla-regex	МІТ	The copyright for this library is unknown
html-comment-regex	MIT	Copyright 2018 Steve Mao
html-entities	MIT	Copyright (c) 2013 Dulin Marat
html-minifier-terser	МІТ	Copyright (c) 2010-2019 Juriy kangax Zaytsev

Component	License	Copyright
html-webpack-plugin	MIT	Copyright JS Foundation and other contributors
htmlparser2	MIT	Copyright 2010, 2011, Chris Winberry
http-deceiver	MIT	The copyright for this library is unknown
http-errors	МІТ	Copyright (c) 2016 Douglas Christopher Wilson doug@somethingdoug.com
http-parser-js	МІТ	The copyright for this library is unknown
http-proxy	МІТ	Copyright (c) 2010-2016 Charlie Robbins, Jarrett Cruger & the Contributors
http-proxy-middleware	MIT	Copyright (c) 2015 Steven Chim
http-signature	МІТ	Copyright Joyent, Inc.
https-browserify	МІТ	Copyright (c) James Halliday
icss-utils	ISC	The copyright for this library is unknown
identity-obj-proxy	MIT	Copyright (c) 2015 Keyan Zhang
ieee754	BSD-3-Clause	Copyright 2008 Fair Oaks Labs, Inc.
iferr	MIT	Copyright (c) 2014 Nadav Ivgi
import-cwd	MIT	Copyright (c) Sindre Sorhus (sindresorhus.com)
import-from	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
indefinite-observable	Apache-2.0	The copyright for this library is unknown
indexes-of	MIT	Copyright (c) 2013 Dominic Tarr
infer-owner	ISC	Copyright (c) npm, Inc. and Contributors
infinity-agent	MIT	The copyright for this library is unknown
inquirer	МІТ	Copyright (c) 2012 Simon Boudrias
internal-ip	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
interpret	МІТ	Copyright (c) 2014-2018 Tyler Kellen , Blaine Bublitz , and Eric Schoffstall
invariant	MIT	Copyright (c) 2013-present, Facebook, Inc.
ip	MIT	The copyright for this library is unknown
ip-regex	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
ipaddr.js	МІТ	Copyright (c) 2011-2017 whitequark
is-absolute-url	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
is-accessor-descriptor	МІТ	Copyright (c) 2015-2017, Jon

Component	License	Copyright
		Schlinkert
is-buffer	МІТ	Copyright (c) Feross Aboukhadijeh
is-ci	МІТ	Copyright (c) 2016-2018 Thomas Watson Steen
is-color-stop	MIT	Copyright (c) 2017 pigcan
is-data-descriptor	МІТ	Copyright (c) 2015-2017, Jon Schlinkert
is-descriptor	МІТ	Copyright (c) 2015-2017, Jon Schlinkert
is-directory	МІТ	Copyright (c) 2014-2016, Jon Schlinkert
is-docker	МІТ	Copyright (c) Sindre Sorhus (https://sindresorhus.com)
is-dotfile	МІТ	Copyright (c) 2015-2017, Jon Schlinkert
is-equal-shallow	МІТ	Copyright (c) 2015, Jon Schlinkert
is-extendable	МІТ	Copyright (c) 2015, Jon Schlinkert
is-finite	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
is-npm	МІТ	The copyright for this library is unknown
is-obj	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
is-path-cwd	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
is-path-in-cwd	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
is-posix-bracket	МІТ	Copyright (c) 2015-2016, Jon Schlinkert
is-primitive	МІТ	Copyright (c) 2014-2015, Jon Schlinkert
is-redirect	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
is-regexp	МІТ	The copyright for this library is unknown
is-resolvable	ISC	Copyright 2018 Shinnosuke Watanabe
is-root	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
is-svg	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
is-typedarray	МІТ	The copyright for this library is unknown
is-wsl	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
isobject	МІТ	Copyright (c) 2014-2017, Jon Schlinkert
isstream	МІТ	The copyright for this library is unknown

Component	License	Copyright
jest-environment-jsdom- fourteen	МІТ	Copyright (c) 2019 Ian Schmitz
jest-environment-jsdom-sixteen	МІТ	Copyright (c) 2020 Simen Bekkhus
jest-jasmine2	МІТ	The copyright for this library is unknown
jest-serializer	МІТ	Copyright (c) Facebook, Inc. and its affiliates
jest-watch-typeahead	МІТ	Copyright (c) 2018 Rogelio Guzman
jsbn	МІТ	Copyright (c) 2003-2005 Tom Wu
json-parse-better-errors	МІТ	The copyright for this library is unknown
json-schema	AFL-2.1	The copyright for this library is unknown
json-stable-stringify	МІТ	The copyright for this library is unknown
json-stringify-safe	ISC	Copyright (c) Isaac Z. Schlueter and Contributors
json3	MIT	Copyright (c) 2013-2015 Benjamin Tan. https:// d10.github.io
jsprim	МІТ	Copyright (c) 2012, Joyent, Inc.
killable	ISC	Copyright 2014 Marten de Vries
last-call-webpack-plugin	МІТ	Copyright (c) 2016 Nuno Rodrigues
latest-version	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
lazy-cache	МІТ	Copyright (c) 2015-2016, Jon Schlinkert
left-pad	WTFPL	The copyright for this library is unknown
levenary	МІТ	Copyright (c) 2019 Tan Li Hau
load-json-file	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
loader-fs-cache	МІТ	Copyright (c) 2014-2016 Ade Viankakrisna Fadlil
loader-runner	МІТ	Copyright (c) Tobias Koppers
loader-utils	МІТ	Copyright JS Foundation and other contributors
lodashreinterpolate	МІТ	The copyright for this library is unknown
lodash.pick	MIT AND CC0-1.0	copyright Jeremy Ashkenas, DocumentCloud and Investigative Reporters & Editors
lodash.sortby	MIT AND CC0-1.0	copyright Jeremy Ashkenas, DocumentCloud and Investigative Reporters & Editors
lodash.template	MIT AND CC0-1.0	copyright Jeremy Ashkenas,

Component	License	Copyright
		DocumentCloud and Investigative Reporters & Editors
lodash.templatesettings	MIT AND CC0-1.0	copyright Jeremy Ashkenas, DocumentCloud and Investigative Reporters & Editors
loglevel	МІТ	The copyright for this library is unknown
lolex	BSD-3-Clause	Copyright (c) 2010-2014, Christian Johansen, christian@cjohansen.no
lower-case	МІТ	Copyright (c) 2014 Blake Embrey (hello@blakeembrey.com)
lowercase-keys	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
lunr	МІТ	Copyright (c) 2013 by Oliver Nightingale
mamacro	МІТ	The copyright for this library is unknown
map-cache	МІТ	Copyright (c) 2015-2016, Jon Schlinkert
map-visit	МІТ	Copyright (c) 2015-2017, Jon Schlinkert
marked	МІТ	The copyright for this library is unknown
math-random	МІТ	The copyright for this library is unknown
md5.js	МІТ	Copyright (c) 2016 Kirill Fomichev
mdn-data	CC0-1.0	The copyright for this library is unknown
media-typer	МІТ	Copyright (c) 2014 Douglas Christopher Wilson
memorystream	МІТ	Copyright (c) 2011 Dmitry Nizovtsev
merge-deep	МІТ	Copyright (c) 2014-present, Jon Schlinkert
merge-descriptors	МІТ	Copyright (c) 2015 Douglas Christopher Wilson
methods	МІТ	Copyright (c) 2015-2016 Douglas Christopher Wilson
microevent.ts	МІТ	Copyright (c) 2016 Christian Speckner
miller-rabin	МІТ	The copyright for this library is unknown
mime	МІТ	Copyright (c) 2010 Benjamin Thomas, Robert Kieffer
mini-css-extract-plugin	MIT	Copyright JS Foundation and other contributors
minimalistic-assert	ISC	Copyright 2015 Calvin Metcalf
minimalistic-crypto-utils	МІТ	The copyright for this library is unknown

Component	License	Copyright
minipass	ISC	Copyright (c) npm, Inc. and Contributors
minipass-collect	ISC	Copyright (c) Isaac Z. Schlueter and Contributors
minipass-flush	ISC	Copyright (c) Isaac Z. Schlueter and Contributors
minipass-pipeline	ISC	Copyright (c) Isaac Z. Schlueter and Contributors
mississippi	BSD-2-Clause	The copyright for this library is unknown
mixin-deep	МІТ	Copyright (c) 2014-2015, 2017, Jon Schlinkert
mixin-object	MIT	Copyright (c) 2014-2015, Jon Schlinkert
mkdirp	MIT	Copyright 2010 James Halliday (mail@substack.net)
move-concurrently	ISC	Copyright (c) 2017, Rebecca Turner
multicast-dns	МІТ	Copyright (c) 2015 Mathias Buus
multicast-dns-service-types	MIT	Copyright (c) 2015 Mathias Buus
mute-stream	ISC	Copyright (c) Isaac Z. Schlueter and Contributors
nanomatch	МІТ	Copyright (c) 2016-2018, Jon Schlinkert
negotiator	MIT	Copyright (c) 2014-2015 Douglas Christopher Wilson
neo-async	MIT	Copyright Caolan McMahon
nested-error-stacks	MIT	Copyright (c) 2014 Matt Lavin
next-tick	МІТ	Copyright (c) 2012-2016 Mariusz Nowak
nice-try	MIT	Copyright (c) 2018 Tobias Reich
no-case	MIT	Copyright (c) 2014 Blake Embrey (hello@blakeembrey.com)
node-forge	BSD-3-Clause	copyrighted by the Free Software Foundation
node-forge/flash	BSD-3-Clause	The copyright for this library is unknown
node-libs-browser	МІТ	Copyright (c) 2012 Tobias Koppers
node-modules-regexp	MIT	Copyright (c) James Talmage
node-notifier	MIT	Copyright (c) 2017 Mikael Brevik
normalize-range	MIT	Copyright (c) James Talmage
normalize-url	MIT	Copyright (c) Sindre Sorhus (sindresorhus.com)
npm-run-all	MIT	Copyright (c) 2015 Toru Nagashima
nth-check	BSD-2-Clause	Copyright (c) Felix Bohm
num2fraction	MIT	Copyright (c) 2014 PostCSS
oauth-sign	Apache-2.0	The copyright for this library is

Component	License	Copyright
		unknown
object-copy	МІТ	Copyright (c) 2016, Jon Schlinkert
object-hash	МІТ	Copyright (c) 2014 object-hash contributors
object-path	МІТ	Copyright (c) 2015 Mario Casciaro
object-visit	МІТ	Copyright (c) 2015, 2017, Jon Schlinkert
object.getownpropertydescripto rs	МІТ	Copyright (c) 2015 Jordan Harband
object.omit	МІТ	Copyright (c) 2014-2016, Jon Schlinkert
object.pick	МІТ	Copyright (c) 2014-2016, Jon Schlinkert
obuf	МІТ	Copyright Fedor Indutny, 2015
on-finished	МІТ	Copyright (c) 2014 Douglas Christopher Wilson
on-headers	міт	Copyright (c) 2014 Douglas Christopher Wilson
onigasm	МІТ	Copyright (c) 2018 Neek Sandhu
open	МІТ	Copyright (c) Sindre Sorhus (https://sindresorhus.com)
opn	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
optimist	МІТ	Copyright 2010 James Halliday (mail@substack.net)
optimize-css-assets-webpack- plugin	МІТ	Copyright (c) 2016 Nuno Rodrigues
original	МІТ	Copyright (c) 2015 Unshift.io, Arnout Kazemier
os-browserify	MIT	Copyright (c) 2017 CoderPuppy
os-homedir	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
os-tmpdir	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
osenv	ISC	Copyright (c) Isaac Z. Schlueter and Contributors
p-each-series	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
p-finally	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
p-map	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
p-reduce	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
p-retry	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
package-json	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
pako	МІТ	Copyright (c) 2014-2017 by Vitaly Puzrin and Andrei

Component	License	Copyright
		Tuputcyn
parallel-transform	МІТ	Copyright 2013 Mathias Buus
param-case	MIT	Copyright (c) 2014 Blake Embrey (hello@blakeembrey.com)
parse-asn1	ISC	Copyright (c) 2017, crypto- browserify contributors
parse-glob	МІТ	Copyright (c) 2015, Jon Schlinkert
parse-passwd	MIT	Copyright (c) 2016 Brian Woodward
parseurl	МІТ	Copyright (c) 2014-2017 Douglas Christopher Wilson
pascal-case	MIT	Copyright (c) 2014 Blake Embrey (hello@blakeembrey.com)
pascalcase	МІТ	Copyright (c) 2015, Jon Schlinkert
path-browserify	MIT	The copyright for this library is unknown
path-dirname	MIT	Copyright (c) Elan Shanker and Node.js contributors
path-is-inside	WTFPL	The copyright for this library is unknown
path-to-regexp	МІТ	Copyright (c) 2014 Blake Embrey (hello@blakeembrey.com)
pbkdf2	МІТ	Copyright (c) 2014 Daniel Cousens
performance-now	МІТ	The copyright for this library is unknown
pidtree	МІТ	Copyright (c) 2018 Simone Primarosa
pify	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
pinkie	МІТ	Copyright (c) Vsevolod Strukchinsky
pinkie-promise	МІТ	Copyright (c) Vsevolod Strukchinsky
pkg-up	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
pn	МІТ	The copyright for this library is unknown
pnp-webpack-plugin	МІТ	The copyright for this library is unknown
portfinder	MIT	Copyright (c) 2012 Charlie Robbins
posix-character-classes	MIT	Copyright (c) 2016-2017, Jon Schlinkert
postcss-attribute-case- insensitive	MIT	Copyright 2016 Dmitry Semigradsky
postcss-browser-comments	CC0-1.0	The copyright for this library is unknown
postcss-calc	міт	Copyright (c) 2014 Maxime Thirouin

Component	License	Copyright
postcss-color-functional- notation	CC0-1.0	The copyright for this library is unknown
postcss-color-gray	ISC	The copyright for this library is unknown
postcss-color-hex-alpha	МІТ	The copyright for this library is unknown
postcss-color-mod-function	CC0-1.0	The copyright for this library is unknown
postcss-color-rebeccapurple	МІТ	Copyright (c) 2014 Maxime Thirouin
postcss-colormin	міт	The copyright for this library is unknown
postcss-convert-values	міт	The copyright for this library is unknown
postcss-custom-media	МІТ	The copyright for this library is unknown
postcss-custom-properties	МІТ	The copyright for this library is unknown
postcss-custom-selectors	МІТ	The copyright for this library is unknown
postcss-dir-pseudo-class	CC0-1.0	The copyright for this library is unknown
postcss-discard-comments	МІТ	The copyright for this library is unknown
postcss-discard-duplicates	МІТ	The copyright for this library is unknown
postcss-discard-empty	МІТ	The copyright for this library is unknown
postcss-discard-overridden	MIT	Copyright 2016 Justineo
postcss-double-position- gradients	CC0-1.0	The copyright for this library is unknown
postcss-env-function	CC0-1.0	The copyright for this library is unknown
postcss-flexbugs-fixes	MIT	Copyright 2015 Luis Rudge
postcss-focus-visible	CC0-1.0	The copyright for this library is unknown
postcss-focus-within	CC0-1.0	The copyright for this library is unknown
postcss-font-variant	МІТ	Copyright (c) 2014 Maxime Thirouin & Ian Storm Taylor
postcss-gap-properties	CC0-1.0	The copyright for this library is unknown
postcss-image-set-function	CC0-1.0	The copyright for this library is unknown
postcss-initial	міт	Copyright 2015 Maksim Koretskiy
postcss-lab-function	CC0-1.0	The copyright for this library is unknown
postcss-load-config	MIT	Copyright (c) Michael Ciniawsky
postcss-loader	MIT	Copyright 2017 Andrey Sitnik
postcss-logical	CC0-1.0	The copyright for this library is unknown

Component	License	Copyright
postcss-media-minmax	МІТ	Copyright (c) 2014 PostCSS
postcss-merge-longhand	міт	The copyright for this library is unknown
postcss-merge-rules	міт	The copyright for this library is unknown
postcss-minify-font-values	МІТ	Copyright (c) Bogdan Chadkin
postcss-minify-gradients	міт	The copyright for this library is unknown
postcss-minify-params	МІТ	Copyright 2015 Bogdan Chadkin
postcss-minify-selectors	міт	The copyright for this library is unknown
postcss-modules-extract- imports	ISC	Copyright 2015 Glen Maddern
postcss-modules-local-by- default	міт	Copyright 2015 Mark Dalgleish
postcss-modules-scope	ISC	Copyright (c) 2015, Glen Maddern
postcss-modules-values	ISC	Copyright (c) 2015, Glen Maddern
postcss-nesting	CC0-1.0	The copyright for this library is unknown
postcss-normalize	CC0-1.0	The copyright for this library is unknown
postcss-normalize-charset	МІТ	Copyright 2015 Bogdan Chadkin
postcss-normalize-display- values	міт	The copyright for this library is unknown
postcss-normalize-positions	міт	The copyright for this library is unknown
postcss-normalize-repeat-style	міт	The copyright for this library is unknown
postcss-normalize-string	міт	The copyright for this library is unknown
postcss-normalize-timing- functions	міт	The copyright for this library is unknown
postcss-normalize-unicode	міт	The copyright for this library is unknown
postcss-normalize-url	міт	The copyright for this library is unknown
postcss-normalize-whitespace	міт	The copyright for this library is unknown
postcss-ordered-values	міт	The copyright for this library is unknown
postcss-overflow-shorthand	CC0-1.0	The copyright for this library is unknown
postcss-page-break	МІТ	Copyright 2017
postcss-place	CC0-1.0	The copyright for this library is unknown
postcss-preset-env	CC0-1.0	The copyright for this library is unknown
postcss-pseudo-class-any-link	CC0-1.0	The copyright for this library is unknown
postcss-reduce-initial	МІТ	The copyright for this library is

Component	License	Copyright
		unknown
postcss-reduce-transforms	МІТ	The copyright for this library is unknown
postcss-replace-overflow-wrap	MIT	Copyright 2016 Matthias Muller
postcss-selector-matches	міт	Copyright (c) 2017 Maxime Thirouin
postcss-selector-not	міт	Copyright (c) 2017 Maxime Thirouin
postcss-svgo	міт	The copyright for this library is unknown
postcss-unique-selectors	МІТ	The copyright for this library is unknown
postcss-values-parser	MIT	Copyright (c) Andrew Powell
prepend-http	міт	Copyright (c) Sindre Sorhus (sindresorhus.com)
preserve	міт	Copyright (c) 2014-2015, Jon Schlinkert
pretty-bytes	міт	Copyright (c) Sindre Sorhus (https://sindresorhus.com)
pretty-error	MIT	Copyright (c) 2013 Aria Minaei
private	MIT	Copyright (c) 2014 Ben Newman
process	міт	Copyright (c) 2013 Roman Shtylman
progress	міт	Copyright (c) 2017 TJ Holowaychuk
promise-inflight	ISC	Copyright (c) 2017, Rebecca Turner
proxy-addr	МІТ	Copyright (c) 2014-2016 Douglas Christopher Wilson
public-encrypt	МІТ	Copyright (c) 2017 Calvin Metcalf
pump	МІТ	Copyright (c) 2014 Mathias Buus
pumpify	MIT	Copyright (c) 2014 Mathias Buus
q	МІТ	Copyright 2009-2017 Kristopher Michael Kowal
qs	BSD-3-Clause	Copyright (c) 2014 Nathan LaFreniere and other contributors
query-string	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
querystring	МІТ	The copyright for this library is unknown
querystring-es3	МІТ	The copyright for this library is unknown
raf	MIT	Copyright 2013 Chris Dickinson
randomatic	МІТ	Copyright (c) 2013-2017, Jon Schlinkert
randombytes	МІТ	Copyright (c) 2017 crypto- browserify
randomfill	MIT	Copyright (c) 2017 crypto-

Component	License	Copyright
		browserify
range-parser	МІТ	Copyright (c) 2015-2016 Douglas Christopher Wilson doug@somethingdoug.com
raw-body	МІТ	Copyright (c) 2014-2015 Douglas Christopher Wilson
rc	MIT	Copyright (c) 2011 Dominic Tarr
react-app-polyfill	МІТ	Copyright (c) 2013-present, Facebook, Inc.
react-app-rewired	МІТ	Copyright (c) 2016 Tim Arney
react-dev-utils	МІТ	Copyright (c) 2013-present, Facebook, Inc.
react-docgen-typescript	МІТ	The copyright for this library is unknown
react-docgen-typescript- webpack-plugin	МІТ	The copyright for this library is unknown
react-error-overlay	МІТ	Copyright (c) 2013-present, Facebook, Inc.
react-hammerjs	MIT	Copyright (c) 2017 Jed Watson
react-lib-adler32	МІТ	Copyright (c) Facebook, Inc. and its affiliates
react-scripts	МІТ	Copyright (c) 2013-present, Facebook, Inc.
react-virtualized	МІТ	Copyright (c) 2015 Brian Vaughn
read-all-stream	МІТ	Copyright (c) Vsevolod Strukchinsky
realpath-native	МІТ	Copyright (c) 2017 Simen Bekkhus
rechoir	MIT	Copyright (c) 2015 Tyler Kellen
recursive-readdir	МІТ	The copyright for this library is unknown
regex-cache	МІТ	Copyright (c) 2015-2017, Jon Schlinkert
regex-not	МІТ	Copyright (c) 2016, 2018, Jon Schlinkert
regex-parser	МІТ	Copyright (c) 2014-19 Ionica Bizau (https://ionicabizau.net)
registry-url	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
relateurl	МІТ	Copyright (c) Steven Vachon (svachon.com)
remove-trailing-separator	ISC	The copyright for this library is unknown
renderkid	MIT	Copyright (c) 2015 Aria Minaei
repeat-element	МІТ	Copyright (c) 2015-present, Jon Schlinkert
repeat-string	МІТ	Copyright (c) 2014-2016, Jon Schlinkert
repeating	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
request	Apache-2.0	The copyright for this library is unknown

Component	License	Copyright
request-promise-core	ISC	Copyright (c) 2020, Nicolai Kamenzky and contributors
request-promise-native	ISC	Copyright (c) 2020, Nicolai Kamenzky and contributors
require-main-filename	ISC	The copyright for this library is unknown
resolve-dir	МІТ	Copyright (c) 2015-2016, Jon Schlinkert
resolve-url	МІТ	Copyright (c) 2013 Simon Lydell
resolve-url-loader	МІТ	The copyright for this library is unknown
restore-cursor	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
ret	МІТ	Copyright (c) 2011 by Roly Fentanes
retry	МІТ	Copyright (c) 2011 Tim Koschutzki (tim@debuggable.com) Felix Geisendorfer (felix@debuggable.com)
rework		The copyright for this library is unknown
rework-visit	МІТ	The copyright for this library is unknown
rgb-regex	МІТ	The copyright for this library is unknown
rgba-regex	МІТ	The copyright for this library is unknown
ripemd160	МІТ	Copyright (c) 2016 crypto- browserify
rsvp	МІТ	Copyright (c) 2014 Yehuda Katz, Tom Dale, Stefan Penner and contributors
run-async	МІТ	Copyright (c) 2014 Simon Boudrias
run-queue	ISC	The copyright for this library is unknown
rxjs	Apache-2.0	The copyright for this library is unknown
safe-regex	МІТ	The copyright for this library is unknown
sane	МІТ	The copyright for this library is unknown
sanitize.css	CC0-1.0	The copyright for this library is unknown
sass	MIT	Copyright (c) 2016, Google Inc.
sass-loader	МІТ	Copyright JS Foundation and other contributors
sax	ISC	Copyright (c) Isaac Z. Schlueter and Contributors
schema-utils	МІТ	Copyright JS Foundation and other contributors

Component	License	Copyright
select-hose	MIT	The copyright for this library is unknown
selfsigned	МІТ	Copyright (c) 2013 Jose F. Romaniello
semver-diff	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
send	MIT	Copyright (c) 2014-2016 Douglas Christopher Wilson
serialize-javascript	BSD-3-Clause	Copyright 2014 Yahoo! Inc.
serve-index	МІТ	Copyright (c) 2014-2015 Douglas Christopher Wilson
serve-static	МІТ	Copyright (c) 2014-2016 Douglas Christopher Wilson
set-blocking	ISC	The copyright for this library is unknown
set-value	МІТ	Copyright (c) 2014-2017, Jon Schlinkert
setprototypeof	ISC	Copyright (c) 2015, Wes Todd
sha.js	MIT AND BSD-3-Clause	Copyright (c) 1998 - 2009, Paul Johnston & Contributors Copyright (c) 2013-2018 sha.js contributors
shallow-clone	MIT	Copyright (c) 2015, Jon Schlinkert
shell-quote	MIT	Copyright (c) 2013 James Halliday (mail@substack.net)
shelljs	BSD-3-Clause	Copyright (c) 2012, Artur Adib
shellwords	МІТ	Copyright (c) 2011 by Jimmy Cuadra
shiki	МІТ	The copyright for this library is unknown
simple-swizzle	МІТ	Copyright (c) 2015 Josh Junon
snapdragon	МІТ	Copyright (c) 2015-2016, Jon Schlinkert
snapdragon-node	МІТ	Copyright (c) 2017, Jon Schlinkert
snapdragon-util	МІТ	Copyright (c) 2017, Jon Schlinkert
sockjs	МІТ	Copyright (c) 2011 VMware, Inc.
sockjs-client	МІТ	Copyright (c) 2011-2018 The sockjs-client
sort-keys	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
source-list-map	МІТ	Copyright 2017 JS Foundation
source-map-resolve	МІТ	Copyright (c) 2019 ZHAO Jinxiang
source-map-url	MIT	Copyright (c) 2014 Simon Lydell
spdy	МІТ	The copyright for this library is unknown
spdy-transport	МІТ	The copyright for this library is unknown
split-string	МІТ	Copyright (c) 2015-2017, Jon

Component	License	Copyright
		Schlinkert
sshpk	MIT	Copyright Joyent, Inc.
ssri	ISC	The copyright for this library is unknown
stable	МІТ	The copyright for this library is unknown
static-extend	МІТ	Copyright (c) 2016, Jon Schlinkert
statuses	МІТ	Copyright (c) 2016 Douglas Christopher Wilson
stealthy-require	ISC	Copyright (c) 2017, Nicolai Kamenzky and contributors
stream-browserify	MIT	Copyright (c) James Halliday
stream-each	МІТ	Copyright (c) 2015 Mathias Buus
stream-http	MIT	Copyright (c) 2015 John Hiesey
stream-shift	МІТ	Copyright (c) 2016 Mathias Buus
strict-uri-encode	MIT	Copyright (c) Kevin Martensson
string.prototype.padend	МІТ	Copyright (c) 2015 EcmaScript Shims
stringify-object	BSD-2-Clause	Copyright (c) 2015, Yeoman team
strip-comments	міт	Copyright (c) 2015-2018, Jon Schlinkert
strip-eof	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
style-loader	МІТ	Copyright JS Foundation and other contributors
stylehacks	МІТ	The copyright for this library is unknown
svg-parser	МІТ	The copyright for this library is unknown
svgo	МІТ	Copyright (c) 2012-2016 Kir Belevich
symbol-observable	MIT	Copyright (c) Ben Lesh
sync-files	MIT	Copyright (c) 2015 LMTM
sync-files/prout/chalk	МІТ	The copyright for this library is unknown
sync-files/prout/chokidar	МІТ	The copyright for this library is unknown
sync-files/prout/fs-extra	МІТ	Copyright (c) 2011-2014 JP Richardson
sync-files/prout/lodash	МІТ	The copyright for this library is unknown
sync-files/prout/minimist	МІТ	The copyright for this library is unknown
sync-files/prout/update-notifier	BSD-3-Clause	The copyright for this library is unknown
terser	BSD-2-Clause	Copyright 2012-2018 (c) Mihai Bazon

Component	License	Copyright
terser-webpack-plugin	МІТ	Copyright JS Foundation and other contributors
throat	МІТ	Copyright (c) 2013 Forbes Lindesay
through	МІТ	The copyright for this library is unknown
through2	МІТ	The copyright for this library is unknown
thunky	МІТ	Copyright (c) 2018 Mathias Buus
timed-out	МІТ	The copyright for this library is unknown
timers-browserify	МІТ	The copyright for this library is unknown
timsort	МІТ	The copyright for this library is unknown
tmp	MIT	Copyright (c) 2014 KARASZI Istvan
to-arraybuffer	MIT	Copyright (c) 2016 John Hiesey
to-object-path	MIT	Copyright (c) 2015-2016, Jon Schlinkert
to-regex	MIT	Copyright (c) 2016-2018, Jon Schlinkert
to-string-loader	BSD-3-Clause	The copyright for this library is unknown
toidentifier	MIT	Copyright (c) 2016 Douglas Christopher Wilson
trim-right	MIT	Copyright (c) Sindre Sorhus (sindresorhus.com)
ts-loader	МІТ	Copyright (c) 2015 TypeStrong
ts-pnp	MIT	The copyright for this library is unknown
tty-browserify	MIT	The copyright for this library is unknown
tunnel-agent	Apache-2.0	The copyright for this library is unknown
tweetnacl	Unlicense	The copyright for this library is unknown
type	ISC	Copyright (c) 2019, Mariusz Nowak, medikoo, medikoo.com
type-is	MIT	Copyright (c) 2014-2015 Douglas Christopher Wilson
typedarray	MIT	Copyright (c) 2012, Joshua Bell
typedoc	Apache-2.0	The copyright for this library is unknown
typedoc-default-themes	Apache-2.0	The copyright for this library is unknown
uglify-js	BSD-2-Clause	Copyright 2012-2019 (c) Mihai Bazon
union-value	МІТ	Copyright (c) 2015-2017, Jon Schlinkert
uniq	MIT	Copyright (c) 2013 Mikola

Component	License	Copyright
		Lysenko
uniqs	MIT	The copyright for this library is unknown
unique-filename	ISC	Copyright npm, Inc
unique-slug	ISC	Copyright npm, Inc
unpipe	МІТ	Copyright (c) 2015 Douglas Christopher Wilson
unquote	МІТ	Copyright (c) 2017 Cameron Lakenen
unset-value	МІТ	Copyright (c) 2015, 2017, Jon Schlinkert
upath	МІТ	Copyright (c) 2014-2019 Angelos Pikoulas (agelos.pikoulas@gmail.com)
update-notifier	BSD-3-Clause	The copyright for this library is unknown
urix	MIT	Copyright (c) 2013 Simon Lydell
url	МІТ	Copyright Joyent, Inc. and other Node contributors
url-loader	МІТ	Copyright JS Foundation and other contributors
use	МІТ	Copyright (c) 2015-present, Jon Schlinkert
user-home	МІТ	Copyright (c) Sindre Sorhus (sindresorhus.com)
util	МІТ	Copyright Joyent, Inc. and other Node contributors
util.promisify	МІТ	Copyright (c) 2017 Jordan Harband
utila	MIT	Copyright (c) 2014 Aria Minaei
utils-merge	МІТ	Copyright (c) 2013-2017 Jared Hanson
vary	МІТ	Copyright (c) 2014-2017 Douglas Christopher Wilson
vendors	MIT	Copyright (c) 2016 Titus Wormer
verror	MIT	Copyright (c) 2016, Joyent, Inc.
vm-browserify	МІТ	The copyright for this library is unknown
vscode-textmate	міт	The copyright for this library is unknown
w3c-hr-time	МІТ	The copyright for this library is unknown
watchpack	МІТ	Copyright JS Foundation and other contributors
watchpack-chokidar2	МІТ	The copyright for this library is unknown
wbuf	MIT	The copyright for this library is unknown
webfontloader	Apache-2.0	The copyright for this library is unknown
webpack	МІТ	Copyright JS Foundation and other contributors

Component	License	Copyright
webpack-cli	МІТ	Copyright JS Foundation and
		other contributors
webpack-dev-middleware	МІТ	Copyright JS Foundation and other contributors
webpack-dev-server	МІТ	Copyright JS Foundation and other contributors
webpack-filter-warnings-plugin	MIT	Copyright (c) 2017 Matt Lewis
webpack-log	МІТ	Copyright (c) 2017 webpack- contrib
webpack-manifest-plugin	MIT	Copyright (c) Dane Thurber
webpack-sources	MIT	Copyright (c) 2017 JS Foundation and other contributors
websocket-driver	Apache-2.0	The copyright for this library is unknown
websocket-extensions	Apache-2.0	The copyright for this library is unknown
whatwg-fetch	МІТ	Copyright (c) 2014-2016 GitHub, Inc.
which-module	ISC	Copyright (c) 2016, Contributors
wordwrap	МІТ	The copyright for this library is unknown
workbox-background-sync	MIT	Copyright 2018 Google LLC
workbox-broadcast-update	MIT	Copyright 2018 Google LLC
workbox-build	MIT	Copyright 2018 Google LLC
workbox-cacheable-response	МІТ	Copyright 2018 Google LLC
workbox-core	МІТ	Copyright 2018 Google LLC
workbox-expiration	МІТ	Copyright 2018 Google LLC
workbox-google-analytics	MIT	Copyright 2018 Google LLC
workbox-navigation-preload	МІТ	Copyright 2018 Google LLC
workbox-precaching	МІТ	Copyright 2018 Google LLC
workbox-range-requests	міт	Copyright 2018 Google LLC
workbox-routing	MIT	Copyright 2018 Google LLC
workbox-strategies	MIT	Copyright 2018 Google LLC
workbox-streams	MIT	Copyright 2018 Google LLC
workbox-sw	MIT	Copyright 2018 Google LLC
workbox-webpack-plugin	MIT	Copyright 2018 Google LLC
workbox-webpack-program	MIT	Copyright 2018 Google LLC
worker-farm	міт	The copyright for this library is unknown
worker-rpc	MIT	Copyright (c) 2016 Christian Speckner
write	MIT	Copyright (c) 2014-2017, Jon Schlinkert
xdg-basedir	міт	Copyright (c) Sindre Sorhus (sindresorhus.com)
xregexp	МІТ	Copyright (c) 2007-present Steven Levithan
xtend	MIT	Copyright (c) 2012-2014 Raynos

The default license texts are as follows:

ΜΙΤ

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

ISC

Permission to use, copy, modify, and/or distribute this software for any purpose with or without fee is hereby granted, provided that the above copyright notice and this permission notice appear in all copies.

THE SOFTWARE IS PROVIDED "AS IS" AND THE AUTHOR DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS. IN NO EVENT SHALL THE AUTHOR BE LIABLE FOR ANY SPECIAL, DIRECT, INDIRECT, OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

Zero-Clause BSD

Permission to use, copy, modify, and/or distribute this software for any purpose with or without fee is hereby granted.

THE SOFTWARE IS PROVIDED "AS IS" AND THE AUTHOR DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS. IN NO EVENT SHALL THE AUTHOR BE LIABLE FOR ANY SPECIAL, DIRECT, INDIRECT, OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

BSD 3

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- 3. Neither the name of the copyright holder nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

BSD 2

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Apache 2.0

Definitions

"License" shall mean the terms and conditions for use, reproduction, and distribution as defined by Sections 1 through 9 of this document.

"Licensor" shall mean the copyright owner or entity authorized by the copyright owner that is granting the License.

"Legal Entity" shall mean the union of the acting entity and all other entities that control, are controlled by, or are under common control with that entity. For the purposes of this definition, "control" means (i) the power, direct or indirect, to cause the direction or management of such entity, whether by contract or otherwise, or (ii) ownership of fifty percent (50%) or more of the outstanding shares, or (iii) beneficial ownership of such entity.

"You" (or "Your") shall mean an individual or Legal Entity exercising permissions granted by this License.

"Source" form shall mean the preferred form for making modifications, including but not limited to software source code, documentation source, and configuration files.

"Object" form shall mean any form resulting from mechanical transformation or translation of a Source form, including but not limited to compiled object code, generated documentation, and conversions to other media types.

"Work" shall mean the work of authorship, whether in Source or Object form, made available under the License, as indicated by a copyright notice that is included in or attached to the work (an example is provided in the Appendix below).

"Derivative Works" shall mean any work, whether in Source or Object form, that is based on (or derived from) the Work and for which the editorial revisions, annotations, elaborations, or other modifications represent, as a whole, an original work of authorship. For the purposes of this License, Derivative Works shall not include works that remain separable from, or merely link (or bind by name) to the interfaces of, the Work and Derivative Works thereof.

"Contribution" shall mean any work of authorship, including the original version of the Work and any modifications or additions to that Work or Derivative Works thereof, that is intentionally submitted to Licensor for inclusion in the Work by the copyright owner or by an individual or Legal Entity authorized to submit on behalf of the copyright owner. For the purposes of this definition, "submitted" means any form of electronic, verbal, or written communication sent to the Licensor or its representatives, including but not limited to communication on electronic mailing lists, source code control systems, and issue tracking systems that are managed by, or on behalf of, the Licensor for the purpose of discussing and improving the Work, but excluding communication that is conspicuously marked or otherwise designated in writing by the copyright owner as "Not a Contribution."

"Contributor" shall mean Licensor and any individual or Legal Entity on behalf of whom a

Contribution has been received by Licensor and subsequently incorporated within the Work.

Grant of Copyright License

Subject to the terms and conditions of this License, each Contributor hereby grants to You a perpetual, worldwide, non-exclusive, no-charge, royalty-free, irrevocable copyright license to reproduce, prepare Derivative Works of, publicly display, publicly perform, sublicense, and distribute the Work and such Derivative Works in Source or Object form.

Grant of Patent License

Subject to the terms and conditions of this License, each Contributor hereby grants to You a perpetual, worldwide, non-exclusive, no-charge, royalty-free, irrevocable (except as stated in this section) patent license to make, have made, use, offer to sell, sell, import, and otherwise transfer the Work, where such license applies only to those patent claims licensable by such Contributor that are necessarily infringed by their Contribution(s) alone or by combination of their Contribution(s) with the Work to which such Contribution(s) was submitted. If You institute patent litigation against any entity (including a cross-claim or counterclaim in a lawsuit) alleging that the Work or a Contribution incorporated within the Work constitutes direct or contributory patent infringement, then any patent licenses granted to You under this License for that Work shall terminate as of the date such litigation is filed.

Redistribution

You may reproduce and distribute copies of the Work or Derivative Works thereof in any medium, with or without modifications, and in Source or Object form, provided that You meet the following conditions:

You must give any other recipients of the Work or Derivative Works a copy of this License; and

You must cause any modified files to carry prominent notices stating that You changed the files; and

You must retain, in the Source form of any Derivative Works that You distribute, all copyright, patent, trademark, and attribution notices from the Source form of the Work, excluding those notices that do not pertain to any part of the Derivative Works; and If the Work includes a "NOTICE" text file as part of its distribution, then any Derivative Works that You distribute must include a readable copy of the attribution notices contained within such NOTICE file, excluding those notices that do not pertain to any part of the Derivative Works, in at least one of the following places: within a NOTICE text file distributed as part of the Derivative Works; within the Source form or documentation, if provided along with the Derivative Works; or, within a display generated by the Derivative Works, if and wherever such third-party notices normally appear. The contents of the NOTICE file are for informational purposes only and do not modify the License. You may add Your own attribution notices within Derivative Works that You distribute, alongside or as an addendum to the NOTICE text from the Work, provided that such additional attribution notices cannot be construed as modifying the License. You may add Your own copyright statement to Your modifications and may provide additional or different license terms and conditions for use, reproduction, or distribution of Your modifications, or for any such Derivative Works as a whole, provided Your use,

reproduction, and distribution of the Work otherwise complies with the conditions stated in this License.

Submission of Contributions

Unless You explicitly state otherwise, any Contribution intentionally submitted for inclusion in the Work by You to the Licensor shall be under the terms and conditions of this License, without any additional terms or conditions. Notwithstanding the above, nothing herein shall supersede or modify the terms of any separate license agreement you may have executed with Licensor regarding such Contributions.

Trademarks

This License does not grant permission to use the trade names, trademarks, service marks, or product names of the Licensor, except as required for reasonable and customary use in describing the origin of the Work and reproducing the content of the NOTICE file.

Disclaimer of Warranty

Unless required by applicable law or agreed to in writing, Licensor provides the Work (and each Contributor provides its Contributions) on an "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied, including, without limitation, any warranties or conditions of TITLE, NON-INFRINGEMENT, MERCHANTABILITY, or FITNESS FOR A PARTICULAR PURPOSE. You are solely responsible for determining the appropriateness of using or redistributing the Work and assume any risks associated with Your exercise of permissions under this License.

Limitation of Liability

In no event and under no legal theory, whether in tort (including negligence), contract, or otherwise, unless required by applicable law (such as deliberate and grossly negligent acts) or agreed to in writing, shall any Contributor be liable to You for damages, including any direct, indirect, special, incidental, or consequential damages of any character arising as a result of this License or out of the use or inability to use the Work (including but not limited to damages for loss of goodwill, work stoppage, computer failure or malfunction, or any and all other commercial damages or losses), even if such Contributor has been advised of the possibility of such damages.

Accepting Warranty or Additional Liability

While redistributing the Work or Derivative Works thereof, You may choose to offer, and charge a fee for, acceptance of support, warranty, indemnity, or other liability obligations and/or rights consistent with this License. However, in accepting such obligations, You may act only on Your own behalf and on Your sole responsibility, not on behalf of any other Contributor, and only if You agree to indemnify, defend, and hold each Contributor harmless for any liability incurred by, or claims asserted against, such Contributor by reason of your accepting any such warranty or additional liability.

X11 License

Copyright (C) 1996 X Consortium

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE X CONSORTIUM BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Except as contained in this notice, the name of the X Consortium shall not be used in advertising or otherwise to promote the sale, use or other dealings in this Software without prior written authorization from the X Consortium.

X Window System is a trademark of X Consortium, Inc.

WTFPL

Version 2, December 2004

Everyone is permitted to copy and distribute verbatim or modified copies of this license document, and changing it is allowed as long as the name is changed.

DO WHAT THE FUCK YOU WANT TO PUBLIC LICENSE TERMS AND CONDITIONS FOR COPYING, DISTRIBUTION AND MODIFICATION

0. You just DO WHAT THE FUCK YOU WANT TO.

CC BY 4.0

Creative Commons Corporation ("Creative Commons") is not a law firm and does not provide legal services or legal advice. Distribution of Creative Commons public licenses does not create a lawyer-client or other relationship. Creative Commons makes its licenses and related information available on an "as-is" basis. Creative Commons gives no warranties regarding its licenses, any material licensed under their terms and conditions, or any related information. Creative Commons disclaims all liability for damages resulting from their use to the fullest extent possible.

Using Creative Commons Public Licenses

Creative Commons public licenses provide a standard set of terms and conditions that creators and other rights holders may use to share original works of authorship and other

material subject to copyright and certain other rights specified in the public license below. The following considerations are for informational purposes only, are not exhaustive, and do not form part of our licenses.

Considerations for licensors: Our public licenses are intended for use by those authorized to give the public permission to use material in ways otherwise restricted by copyright and certain other rights. Our licenses are irrevocable. Licensors should read and understand the terms and conditions of the license they choose before applying it. Licensors should also secure all rights necessary before applying our licenses so that the public can reuse the material as expected. Licensors should clearly mark any material not subject to the license. This includes other CC-licensed material, or material used under an exception or limitation to copyright. More considerations for licensors : wiki.creativecommons.org/Considerations_for_licensors

Considerations for the public: By using one of our public licenses, a licensor grants the public permission to use the licensed material under specified terms and conditions. If the licensor's permission is not necessary for any reason—for example, because of any applicable exception or limitation to copyright—then that use is not regulated by the license. Our licenses grant only permissions under copyright and certain other rights that a licensor has authority to grant. Use of the licensed material may still be restricted for other reasons, including because others have copyright or other rights in the material. A licensor may make special requests, such as asking that all changes be marked or described. Although not required by our licenses, you are encouraged to respect those requests where reasonable. More considerations for the public : wiki.creativecommons.org/Considerations_for_licenses

Creative Commons Attribution 4.0 International Public License

By exercising the Licensed Rights (defined below), You accept and agree to be bound by the terms and conditions of this Creative Commons Attribution 4.0 International Public License ("Public License"). To the extent this Public License may be interpreted as a contract, You are granted the Licensed Rights in consideration of Your acceptance of these terms and conditions, and the Licensor grants You such rights in consideration of benefits the Licensor receives from making the Licensed Material available under these terms and conditions.

Section 1 – Definitions

- a) Adapted Material means material subject to Copyright and Similar Rights that is derived from or based upon the Licensed Material and in which the Licensed Material is translated, altered, arranged, transformed, or otherwise modified in a manner requiring permission under the Copyright and Similar Rights held by the Licensor. For purposes of this Public License, where the Licensed Material is a musical work, performance, or sound recording, Adapted Material is always produced where the Licensed Material is synched in timed relation with a moving image.
- b) Adapter's License means the license You apply to Your Copyright and Similar Rights in Your contributions to Adapted Material in accordance with the terms and conditions of this Public License.
- c) Copyright and Similar Rights means copyright and/or similar rights closely related to copyright including, without limitation, performance, broadcast, sound recording, and Sui Generis Database Rights, without regard to how the rights are labeled or

categorized. For purposes of this Public License, the rights specified in Section 2(b)(1)-(2) are not Copyright and Similar Rights.

- d) Effective Technological Measures means those measures that, in the absence of proper authority, may not be circumvented under laws fulfilling obligations under Article 11 of the WIPO Copyright Treaty adopted on December 20, 1996, and/or similar international agreements.
- e) Exceptions and Limitations means fair use, fair dealing, and/or any other exception or limitation to Copyright and Similar Rights that applies to Your use of the Licensed Material.
- f) Licensed Material means the artistic or literary work, database, or other material to which the Licensor applied this Public License.
- g) Licensed Rights means the rights granted to You subject to the terms and conditions of this Public License, which are limited to all Copyright and Similar Rights that apply to Your use of the Licensed Material and that the Licensor has authority to license.
- h) Licensor means the individual(s) or entity(ies) granting rights under this Public License.
- i) Share means to provide material to the public by any means or process that requires permission under the Licensed Rights, such as reproduction, public display, public performance, distribution, dissemination, communication, or importation, and to make material available to the public including in ways that members of the public may access the material from a place and at a time individually chosen by them.
- j) Sui Generis Database Rights means rights other than copyright resulting from Directive 96/9/EC of the European Parliament and of the Council of 11 March 1996 on the legal protection of databases, as amended and/or succeeded, as well as other essentially equivalent rights anywhere in the world.
- k) You means the individual or entity exercising the Licensed Rights under this Public License. Your has a corresponding meaning.

Section 2 – Scope.

a) License grant.

- Subject to the terms and conditions of this Public License, the Licensor hereby grants You a worldwide, royalty-free, non-sublicensable, non-exclusive, irrevocable license to exercise the Licensed Rights in the Licensed Material to: A. reproduce and Share the Licensed Material, in whole or in part; and B. produce, reproduce, and Share Adapted Material.
- 2. <u>Exceptions and Limitations</u>. For the avoidance of doubt, where Exceptions and Limitations apply to Your use, this Public License does not apply, and You do not need to comply with its terms and conditions.
- 3. Term. The term of this Public License is specified in Section 6(a).
- 4. <u>Media and formats; technical modifications allowed.</u> The Licensor authorizes You to exercise the Licensed Rights in all media and formats whether now known or hereafter created, and to make technical modifications necessary to do so. The Licensor waives and/or agrees not to assert any right or authority to forbid You from making technical modifications necessary to exercise the Licensed Rights, including technical modifications necessary to circumvent Effective Technological Measures. For purposes of this Public License, simply making modifications authorized by this Section 2(a)(4) never produces Adapted Material.
- 5. <u>Downstream recipients.</u>
 - A. <u>Offer from the Licensor Licensed Material</u>. Every recipient of the Licensed Material automatically receives an offer from the Licensor to exercise the Licensed Rights under the terms and conditions of this Public License.

- B. <u>No downstream restrictions</u>. You may not offer or impose any additional or different terms or conditions on, or apply any Effective Technological Measures to, the Licensed Material if doing so restricts exercise of the Licensed Rights by any recipient of the Licensed Material.
- <u>No endorsement</u>. Nothing in this Public License constitutes or may be construed as permission to assert or imply that You are, or that Your use of the Licensed Material is, connected with, or sponsored, endorsed, or granted official status by, the Licensor or others designated to receive attribution as provided in Section 3(a)(1)(A) (i).

b) Other rights.

- 1. Moral rights, such as the right of integrity, are not licensed under this Public License, nor are publicity, privacy, and/or other similar personality rights; however, to the extent possible, the Licensor waives and/or agrees not to assert any such rights held by the Licensor to the limited extent necessary to allow You to exercise the Licensed Rights, but not otherwise.
- 2. Patent and trademark rights are not licensed under this Public License.
- 3. To the extent possible, the Licensor waives any right to collect royalties from You for the exercise of the Licensed Rights, whether directly or through a collecting society under any voluntary or waivable statutory or compulsory licensing scheme. In all other cases the Licensor expressly reserves any right to collect such royalties.

Section 3 – License Conditions.

Your exercise of the Licensed Rights is expressly made subject to the following conditions.

a) Attribution.

- 1. If You Share the Licensed Material (including in modified form), You must:
 - A. retain the following if it is supplied by the Licensor with the Licensed Material:
 - i. identification of the creator(s) of the Licensed Material and any others designated to receive attribution, in any reasonable manner requested by the Licensor (including by pseudonym if designated);
 - ii. a copyright notice;
 - iii.a notice that refers to this Public License;
 - iv.a notice that refers to the disclaimer of warranties;
 - v. a URI or hyperlink to the Licensed Material to the extent reasonably practicable;
 - B. indicate if You modified the Licensed Material and retain an indication of any previous modifications; and
 - C. indicate the Licensed Material is licensed under this Public License, and include the text of, or the URI or hyperlink to, this Public License.
- 2. You may satisfy the conditions in Section 3(a)(1) in any reas<ronable manner based on the medium, means, and context in which You Share the Licensed Material. For example, it may be reasonable to satisfy the conditions by providing a URI or hyperlink to a resource that includes the required information.
- 3. If requested by the Licensor, You must remove any of the information required by Section 3(a)(1)(A) to the extent reasonably practicable.
- 4. If You Share Adapted Material You produce, the Adapter's License You apply must not prevent recipients of the Adapted Material from complying with this Public License.

Section 4 – Sui Generis Database Rights.

Where the Licensed Rights include Sui Generis Database Rights that apply to Your use of the Licensed Material:

- a) for the avoidance of doubt, Section 2(a)(1) grants You the right to extract, reuse, reproduce, and Share all or a substantial portion of the contents of the database;
- b) if You include all or a substantial portion of the database contents in a database in which You have Sui Generis Database Rights, then the database in which You have Sui Generis Database Rights (but not its individual contents) is Adapted Material; and
- c) You must comply with the conditions in Section 3(a) if You Share all or a substantial portion of the contents of the database.

For the avoidance of doubt, this Section 4 supplements and does not replace Your obligations under this Public License where the Licensed Rights include other Copyright and Similar Rights.

Section 5 – Disclaimer of Warranties and Limitation of Liability.

- a) Unless otherwise separately undertaken by the Licensor, to the extent possible, the Licensor offers the Licensed Material as-is and as-available, and makes no representations or warranties of any kind concerning the Licensed Material, whether express, implied, statutory, or other. This includes, without limitation, warranties of title, merchantability, fitness for a particular purpose, non-infringement, absence of latent or other defects, accuracy, or the presence or absence of errors, whether or not known or discoverable. Where disclaimers of warranties are not allowed in full or in part, this disclaimer may not apply to You.
- b) To the extent possible, in no event will the Licensor be liable to You on any legal theory (including, without limitation, negligence) or otherwise for any direct, special, indirect, incidental, consequential, punitive, exemplary, or other losses, costs, expenses, or damages arising out of this Public License or use of the Licensed Material, even if the Licensor has been advised of the possibility of such losses, costs, expenses, or damages. Where a limitation of liability is not allowed in full or in part, this limitation may not apply to You.
- c) The disclaimer of warranties and limitation of liability provided above shall be interpreted in a manner that, to the extent possible, most closely approximates an absolute disclaimer and waiver of all liability.

Section 6 – Term and Termination.

- a) This Public License applies for the term of the Copyright and Similar Rights licensed here. However, if You fail to comply with this Public License, then Your rights under this Public License terminate automatically.
- b) Where Your right to use the Licensed Material has terminated under Section 6(a), it reinstates:
 - 1. automatically as of the date the violation is cured, provided it is cured within 30 days of Your discovery of the violation; or
 - 2. upon express reinstatement by the Licensor.
- c) For the avoidance of doubt, this Section 6(b) does not affect any right the Licensor may have to seek remedies for Your violations of this Public License.
- d) For the avoidance of doubt, the Licensor may also offer the Licensed Material under separate terms or conditions or stop distributing the Licensed Material at any time;

however, doing so will not terminate this Public License. e) Sections 1, 5, 6, 7, and 8 survive termination of this Public License.

Section 7 – Other Terms and Conditions.

- a) The Licensor shall not be bound by any additional or different terms or conditions communicated by You unless expressly agreed.
- b) Any arrangements, understandings, or agreements regarding the Licensed Material not stated herein are separate from and independent of the terms and conditions of this Public License.

Section 8 – Interpretation.

- a) For the avoidance of doubt, this Public License does not, and shall not be interpreted to, reduce, limit, restrict, or impose conditions on any use of the Licensed Material that could lawfully be made without permission under this Public License.
- b) To the extent possible, if any provision of this Public License is deemed unenforceable, it shall be automatically reformed to the minimum extent necessary to make it enforceable. If the provision cannot be reformed, it shall be severed from this Public License without affecting the enforceability of the remaining terms and conditions.
- c) No term or condition of this Public License will be waived and no failure to comply consented to unless expressly agreed to by the Licensor.
- d) Nothing in this Public License constitutes or may be interpreted as a limitation upon, or waiver of, any privileges and immunities that apply to the Licensor or You, including from the legal processes of any jurisdiction or authority.

Unlicense

This is free and unencumbered software released into the public domain.

Anyone is free to copy, modify, publish, use, compile, sell, or distribute this software, either in source code form or as a compiled binary, for any purpose, commercial or non-commercial, and by any means.

In jurisdictions that recognize copyright laws, the author or authors of this software dedicate any and all copyright interest in the software to the public domain. We make this dedication for the benefit of the public at large and to the detriment of our heirs and successors. We intend this dedication to be an overt act of relinquishment in perpetuity of all present and future rights to this software under copyright law.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

For more information, please refer to <http://unlicense.org/>

CC0 1.0 Universal

The laws of most jurisdictions throughout the world automatically confer exclusive Copyright and Related Rights (defined below) upon the creator and subsequent owner(s) (each and all, an "owner") of an original work of authorship and/or a database (each, a "Work").

Certain owners wish to permanently relinquish those rights to a Work for the purpose of contributing to a commons of creative, cultural and scientific works ("Commons") that the public can reliably and without fear of later claims of infringement build upon, modify, incorporate in other works, reuse and redistribute as freely as possible in any form whatsoever and for any purposes, including without limitation commercial purposes. These owners may contribute to the Commons to promote the ideal of a free culture and the further production of creative, cultural and scientific works, or to gain reputation or greater distribution for their Work in part through the use and efforts of others.

For these and/or other purposes and motivations, and without any expectation of additional consideration or compensation, the person associating CCO with a Work (the "Affirmer"), to the extent that he or she is an owner of Copyright and Related Rights in the Work, voluntarily elects to apply CCO to the Work and publicly distribute the Work under its terms, with knowledge of his or her Copyright and Related Rights in the Work and the meaning and intended legal effect of CCO on those rights.

- 1. **Copyright and Related Rights.** A Work made available under CCO may be protected by copyright and related or neighboring rights ("Copyright and Related Rights"). Copyright and Related Rights include, but are not limited to, the following:
 - a. the right to reproduce, adapt, distribute, perform, display, communicate, and translate a Work;
 - b. moral rights retained by the original author(s) and/or performer(s);
 - c. publicity and privacy rights pertaining to a person's image or likeness depicted in a Work;
 - d. rights protecting against unfair competition in regards to a Work, subject to the limitations in paragraph 4(a), below;
 - e. rights protecting the extraction, dissemination, use and reuse of data in a Work;
 - f. database rights (such as those arising under Directive 96/9/EC of the European Parliament and of the Council of 11 March 1996 on the legal protection of databases, and under any national implementation thereof, including any amended or successor version of such directive); and
 - g. other similar, equivalent or corresponding rights throughout the world based on applicable law or treaty, and any national implementations thereof.
- 2. Waiver. To the greatest extent permitted by, but not in contravention of, applicable

law, Affirmer hereby overtly, fully, permanently, irrevocably and unconditionally waives, abandons, and surrenders all of Affirmer's Copyright and Related Rights and associated claims and causes of action, whether now known or unknown (including existing as well as future claims and causes of action), in the Work (i) in all territories worldwide, (ii) for the maximum duration provided by applicable law or treaty (including future time extensions), (iii) in any current or future medium and for any number of copies, and (iv) for any purpose whatsoever, including without limitation commercial, advertising or promotional purposes (the "Waiver"). Affirmer makes the Waiver for the benefit of each member of the public at large and to the detriment of Affirmer's heirs and successors, fully intending that such Waiver shall not be subject to revocation, rescission, cancellation, termination, or any other legal or equitable action to disrupt the quiet enjoyment of the Work by the public as contemplated by Affirmer's express Statement of Purpose.

3. Public License Fallback. Should any part of the Waiver for any reason be judged legally invalid or ineffective under applicable law, then the Waiver shall be preserved to the maximum extent permitted taking into account Affirmer's express Statement of Purpose. In addition, to the extent the Waiver is so judged Affirmer hereby grants to each affected person a royalty-free, non transferable, non sublicensable, non exclusive, irrevocable and unconditional license to exercise Affirmer's Copyright and Related Rights in the Work (i) in all territories worldwide, (ii) for the maximum duration provided by applicable law or treaty (including future time extensions), (iii) in any current or future medium and for any number of copies, and (iv) for any purpose whatsoever, including without limitation commercial, advertising or promotional purposes (the "License"). The License shall be deemed effective as of the date CCO was applied by Affirmer to the Work. Should any part of the License for any reason be judged legally invalid or ineffective under applicable law, such partial invalidity or ineffectiveness shall not invalidate the remainder of the License, and in such case Affirmer hereby affirms that he or she will not (i) exercise any of his or her remaining Copyright and Related Rights in the Work or (ii) assert any associated claims and causes of action with respect to the Work, in either case contrary to Affirmer's express Statement of Purpose.

4. Limitations and Disclaimers.

- a. No trademark or patent rights held by Affirmer are waived, abandoned, surrendered, licensed or otherwise affected by this document.
- b. Affirmer offers the Work as-is and makes no representations or warranties of any kind concerning the Work, express, implied, statutory or otherwise, including without limitation warranties of title, merchantability, fitness for a particular purpose, non infringement, or the absence of latent or other defects, accuracy, or the present or absence of errors, whether or not discoverable, all to the greatest extent permissible under applicable law.
- c. Affirmer disclaims responsibility for clearing rights of other persons that may apply to the Work or any use thereof, including without limitation any person's Copyright and Related Rights in the Work. Further, Affirmer disclaims responsibility for obtaining any necessary consents, permissions or other rights required for any use of the Work.
- d. Affirmer understands and acknowledges that Creative Commons is not a party to this document and has no duty or obligation with respect to this CC0 or use of the Work.

CC BY 3.0

THE WORK (AS DEFINED BELOW) IS PROVIDED UNDER THE TERMS OF THIS CREATIVE COMMONS PUBLIC LICENSE ("CCPL" OR "LICENSE"). THE WORK IS PROTECTED BY COPYRIGHT AND/OR OTHER APPLICABLE LAW. ANY USE OF THE WORK OTHER THAN AS AUTHORIZED UNDER THIS LICENSE OR COPYRIGHT LAW IS PROHIBITED.

BY EXERCISING ANY RIGHTS TO THE WORK PROVIDED HERE, YOU ACCEPT AND AGREE TO BE BOUND BY THE TERMS OF THIS LICENSE. TO THE EXTENT THIS LICENSE MAY BE CONSIDERED TO BE A CONTRACT, THE LICENSOR GRANTS YOU THE RIGHTS CONTAINED HERE IN CONSIDERATION OF YOUR ACCEPTANCE OF SUCH TERMS AND CONDITIONS.

1. Definitions

- a. "Adaptation" means a work based upon the Work, or upon the Work and other preexisting works, such as a translation, adaptation, derivative work, arrangement of music or other alterations of a literary or artistic work, or phonogram or performance and includes cinematographic adaptations or any other form in which the Work may be recast, transformed, or adapted including in any form recognizably derived from the original, except that a work that constitutes a Collection will not be considered an Adaptation for the purpose of this License. For the avoidance of doubt, where the Work is a musical work, performance or phonogram, the synchronization of the Work in timed-relation with a moving image ("synching") will be considered an Adaptation for the purpose of this License.
- b. "Collection" means a collection of literary or artistic works, such as encyclopedias and anthologies, or performances, phonograms or broadcasts, or other works or subject matter other than works listed in Section 1(f) below, which, by reason of the selection and arrangement of their contents, constitute intellectual creations, in which the Work is included in its entirety in unmodified form along with one or more other contributions, each constituting separate and independent works in themselves, which together are assembled into a collective whole. A work that constitutes a Collection will not be considered an Adaptation (as defined above) for the purposes of this License.
- **c.** "**Distribute**" means to make available to the public the original and copies of the Work or Adaptation, as appropriate, through sale or other transfer of ownership.
- **d. "Licensor"** means the individual, individuals, entity or entities that offer(s) the Work under the terms of this License.
- e. "Original Author" means, in the case of a literary or artistic work, the individual, individuals, entity or entities who created the Work or if no individual or entity can be identified, the publisher; and in addition (i) in the case of a performance the actors, singers, musicians, dancers, and other persons who act, sing, deliver, declaim, play in, interpret or otherwise perform literary or artistic works or expressions of folklore; (ii) in the case of a performance or other sounds; and, (iii) in the case of broadcasts, the organization that transmits the broadcast.
- **f. "Work"** means the literary and/or artistic work offered under the terms of this License including without limitation any production in the literary, scientific and artistic domain, whatever may be the mode or form of its expression including digital form, such as a book, pamphlet and other writing; a lecture, address, sermon or other work of the same nature; a dramatic or dramatico-musical work; a

choreographic work or entertainment in dumb show; a musical composition with or without words; a cinematographic work to which are assimilated works expressed by a process analogous to cinematography; a work of drawing, painting, architecture, sculpture, engraving or lithography; a photographic work to which are assimilated works expressed by a process analogous to photography; a work of applied art; an illustration, map, plan, sketch or three-dimensional work relative to geography, topography, architecture or science; a performance; a broadcast; a phonogram; a compilation of data to the extent it is protected as a copyrightable work; or a work performed by a variety or circus performer to the extent it is not otherwise considered a literary or artistic work.

- **g. "You"** means an individual or entity exercising rights under this License who has not previously violated the terms of this License with respect to the Work, or who has received express permission from the Licensor to exercise rights under this License despite a previous violation.
- h. "Publicly Perform" means to perform public recitations of the Work and to communicate to the public those public recitations, by any means or process, including by wire or wireless means or public digital performances; to make available to the public Works in such a way that members of the public may access these Works from a place and at a place individually chosen by them; to perform the Work to the public by any means or process and the communication to the public of the performances of the Work, including by public digital performance; to broadcast and rebroadcast the Work by any means including signs, sounds or images.
- i. "Reproduce" means to make copies of the Work by any means including without limitation by sound or visual recordings and the right of fixation and reproducing fixations of the Work, including storage of a protected performance or phonogram in digital form or other electronic medium.
- **2. Fair Dealing Rights.** Nothing in this License is intended to reduce, limit, or restrict any uses free from copyright or rights arising from limitations or exceptions that are provided for in connection with the copyright protection under copyright law or other applicable laws.
- **3. License Grant.** Subject to the terms and conditions of this License, Licensor hereby grants You a worldwide, royalty-free, non-exclusive, perpetual (for the duration of the applicable copyright) license to exercise the rights in the Work as stated below:
 - **a.** to Reproduce the Work, to incorporate the Work into one or more Collections, and to Reproduce the Work as incorporated in the Collections;
 - b. to create and Reproduce Adaptations provided that any such Adaptation, including any translation in any medium, takes reasonable steps to clearly label, demarcate or otherwise identify that changes were made to the original Work. For example, a translation could be marked "The original work was translated from English to Spanish," or a modification could indicate "The original work has been modified.";
 - **c.** to Distribute and Publicly Perform the Work including as incorporated in Collections; and,
 - d. to Distribute and Publicly Perform Adaptations.
 - e. For the avoidance of doubt:
 - i. Non-waivable Compulsory License Schemes. In those jurisdictions in which the right to collect royalties through any statutory or compulsory licensing scheme cannot be waived, the Licensor reserves the exclusive right to collect such royalties for any exercise by You of the rights granted under this License;

- ii. Waivable Compulsory License Schemes. In those jurisdictions in which the right to collect royalties through any statutory or compulsory licensing scheme can be waived, the Licensor waives the exclusive right to collect such royalties for any exercise by You of the rights granted under this License; and,
- **iii.**Voluntary License Schemes. The Licensor waives the right to collect royalties, whether individually or, in the event that the Licensor is a member of a collecting society that administers voluntary licensing schemes, via that society, from any exercise by You of the rights granted under this License.

The above rights may be exercised in all media and formats whether now known or hereafter devised. The above rights include the right to make such modifications as are technically necessary to exercise the rights in other media and formats. Subject to Section 8(f), all rights not expressly granted by Licensor are hereby reserved.

- 4. **Restrictions.** The license granted in Section 3 above is expressly made subject to and limited by the following restrictions:
 - a. You may Distribute or Publicly Perform the Work only under the terms of this License. You must include a copy of, or the Uniform Resource Identifier (URI) for, this License with every copy of the Work You Distribute or Publicly Perform. You may not offer or impose any terms on the Work that restrict the terms of this License or the ability of the recipient of the Work to exercise the rights granted to that recipient under the terms of the License. You may not sublicense the Work. You must keep intact all notices that refer to this License and to the disclaimer of warranties with every copy of the Work You Distribute or Publicly Perform. When You Distribute or Publicly Perform the Work, You may not impose any effective technological measures on the Work that restrict the ability of a recipient of the Work from You to exercise the rights granted to that recipient under the terms of the License. This Section 4(a) applies to the Work as incorporated in a Collection, but this does not require the Collection apart from the Work itself to be made subject to the terms of this License. If You create a Collection, upon notice from any Licensor You must, to the extent practicable, remove from the Collection any credit as required by Section 4(b), as requested. If You create an Adaptation, upon notice from any Licensor You must, to the extent practicable, remove from the Adaptation any credit as required by Section 4(b), as requested.
 - b. If You Distribute, or Publicly Perform the Work or any Adaptations or Collections, You must, unless a request has been made pursuant to Section 4(a), keep intact all copyright notices for the Work and provide, reasonable to the medium or means You are utilizing: (i) the name of the Original Author (or pseudonym, if applicable) if supplied, and/or if the Original Author and/or Licensor designate another party or parties (e.g., a sponsor institute, publishing entity, journal) for attribution ("Attribution Parties") in Licensor's copyright notice, terms of service or by other reasonable means, the name of such party or parties; (ii) the title of the Work if supplied; (iii) to the extent reasonably practicable, the URI, if any, that Licensor specifies to be associated with the Work, unless such URI does not refer to the copyright notice or licensing information for the Work; and (iv), consistent with Section 3(b), in the case of an Adaptation, a credit identifying the use of the Work in the Adaptation (e.g., "French translation of the Work by Original Author," or "Screenplay based on original Work by Original Author"). The credit required by this Section 4 (b) may be implemented in any reasonable manner; provided, however, that in the case of a Adaptation or Collection, at a minimum such credit will appear, if a credit for all contributing authors of the Adaptation or Collection appears, then

as part of these credits and in a manner at least as prominent as the credits for the other contributing authors. For the avoidance of doubt, You may only use the credit required by this Section for the purpose of attribution in the manner set out above and, by exercising Your rights under this License, You may not implicitly or explicitly assert or imply any connection with, sponsorship or endorsement by the Original Author, Licensor and/or Attribution Parties, as appropriate, of You or Your use of the Work, without the separate, express prior written permission of the Original Author, Licensor and/or Attribution Parties.

c. Except as otherwise agreed in writing by the Licensor or as may be otherwise permitted by applicable law, if You Reproduce, Distribute or Publicly Perform the Work either by itself or as part of any Adaptations or Collections, You must not distort, mutilate, modify or take other derogatory action in relation to the Work which would be prejudicial to the Original Author's honor or reputation. Licensor agrees that in those jurisdictions (e.g. Japan), in which any exercise of the right granted in Section 3(b) of this License (the right to make Adaptations) would be deemed to be a distortion, mutilation, modification or other derogatory action prejudicial to the Original Author's honor and reputation, the Licensor will waive or not assert, as appropriate, this Section, to the fullest extent permitted by the applicable national law, to enable You to reasonably exercise Your right under Section 3(b) of this License (right to make Adaptations) but not otherwise.

5. Representations, Warranties and Disclaimer

UNLESS OTHERWISE MUTUALLY AGREED TO BY THE PARTIES IN WRITING, LICENSOR OFFERS THE WORK AS-IS AND MAKES NO REPRESENTATIONS OR WARRANTIES OF ANY KIND CONCERNING THE WORK, EXPRESS, IMPLIED, STATUTORY OR OTHERWISE, INCLUDING, WITHOUT LIMITATION, WARRANTIES OF TITLE, MERCHANTIBILITY, FITNESS FOR A PARTICULAR PURPOSE, NONINFRINGEMENT, OR THE ABSENCE OF LATENT OR OTHER DEFECTS, ACCURACY, OR THE PRESENCE OF ABSENCE OF ERRORS, WHETHER OR NOT DISCOVERABLE. SOME JURISDICTIONS DO NOT ALLOW THE EXCLUSION OF IMPLIED WARRANTIES, SO SUCH EXCLUSION MAY NOT APPLY TO YOU.

6. Limitation on Liability. EXCEPT TO THE EXTENT REQUIRED BY APPLICABLE LAW, IN NO EVENT WILL LICENSOR BE LIABLE TO YOU ON ANY LEGAL THEORY FOR ANY SPECIAL, INCIDENTAL, CONSEQUENTIAL, PUNITIVE OR EXEMPLARY DAMAGES ARISING OUT OF THIS LICENSE OR THE USE OF THE WORK, EVEN IF LICENSOR HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

7. Termination

- a. This License and the rights granted hereunder will terminate automatically upon any breach by You of the terms of this License. Individuals or entities who have received Adaptations or Collections from You under this License, however, will not have their licenses terminated provided such individuals or entities remain in full compliance with those licenses. Sections 1, 2, 5, 6, 7, and 8 will survive any termination of this License.
- b. Subject to the above terms and conditions, the license granted here is perpetual (for the duration of the applicable copyright in the Work). Notwithstanding the above, Licensor reserves the right to release the Work under different license terms or to stop distributing the Work at any time; provided, however that any such election will not serve to withdraw this License (or any other license that has been, or is required to be, granted under the terms of this License), and this License will continue in full force and effect unless terminated as stated above.

8. Miscellaneous

- a. Each time You Distribute or Publicly Perform the Work or a Collection, the Licensor offers to the recipient a license to the Work on the same terms and conditions as the license granted to You under this License.
- b. Each time You Distribute or Publicly Perform an Adaptation, Licensor offers to the recipient a license to the original Work on the same terms and conditions as the license granted to You under this License.
- c. If any provision of this License is invalid or unenforceable under applicable law, it shall not affect the validity or enforceability of the remainder of the terms of this License, and without further action by the parties to this agreement, such provision shall be reformed to the minimum extent necessary to make such provision valid and enforceable.
- d. No term or provision of this License shall be deemed waived and no breach consented to unless such waiver or consent shall be in writing and signed by the party to be charged with such waiver or consent.
- e. This License constitutes the entire agreement between the parties with respect to the Work licensed here. There are no understandings, agreements or representations with respect to the Work not specified here. Licensor shall not be bound by any additional provisions that may appear in any communication from You. This License may not be modified without the mutual written agreement of the Licensor and You.
- f. The rights granted under, and the subject matter referenced, in this License were drafted utilizing the terminology of the Berne Convention for the Protection of Literary and Artistic Works (as amended on September 28, 1979), the Rome Convention of 1961, the WIPO Copyright Treaty of 1996, the WIPO Performances and Phonograms Treaty of 1996 and the Universal Copyright Convention (as revised on July 24, 1971). These rights and subject matter take effect in the relevant jurisdiction in which the License terms are sought to be enforced according to the corresponding provisions of the implementation of those treaty provisions in the applicable national law. If the standard suite of rights granted under applicable copyright law includes additional rights not granted under this License, such additional rights are deemed to be included in the License; this License is not intended to restrict the license of any rights under applicable law.

Academic Free License 2.1

This Academic Free License (the "License") applies to any original work of authorship (the "Original Work") whose owner (the "Licensor") has placed the following notice immediately following the copyright notice for the Original Work:

- 1. Grant of Copyright License. Licensor hereby grants You a world-wide, royalty-free, nonexclusive, perpetual, sublicenseable license to do the following:
 - a. to reproduce the Original Work in copies;
 - b. to prepare derivative works ("Derivative Works") based upon the Original Work;
 - c. to distribute copies of the Original Work and Derivative Works to the public;
 - d. to perform the Original Work publicly; and
 - e. to display the Original Work publicly.
- 2. Grant of Patent License. Licensor hereby grants You a world-wide, royalty-free, nonexclusive, perpetual, sublicenseable license, under patent claims owned or controlled by the Licensor that are embodied in the Original Work as furnished by the Licensor, to

make, use, sell and offer for sale the Original Work and Derivative Works.

- 3. Grant of Source Code License. The term "Source Code" means the preferred form of the Original Work for making modifications to it and all available documentation describing how to modify the Original Work. Licensor hereby agrees to provide a machine-readable copy of the Source Code of the Original Work along with each copy of the Original Work that Licensor distributes. Licensor reserves the right to satisfy this obligation by placing a machine-readable copy of the Source Code in an information repository reasonably calculated to permit inexpensive and convenient access by You for as long as Licensor continues to distribute the Original Work, and by publishing the address of that information repository in a notice immediately following the copyright notice that applies to the Original Work.
- 4. Exclusions From License Grant. Neither the names of Licensor, nor the names of any contributors to the Original Work, nor any of their trademarks or service marks, may be used to endorse or promote products derived from this Original Work without express prior written permission of the Licensor. Nothing in this License shall be deemed to grant any rights to trademarks, copyrights, patents, trade secrets or any other intellectual property of Licensor except as expressly stated herein. No patent license is granted to make, use, sell or offer to sell embodiments of any patent claims other than the licensed claims defined in Section 2. No right is granted to the trademarks of Licensor even if such marks are included in the Original Work. Nothing in this License shall be interpreted to prohibit Licensor otherwise would have a right to license.
- 5. This section intentionally omitted.
- 6. Attribution Rights. You must retain, in the Source Code of any Derivative Works that You create, all copyright, patent or trademark notices from the Source Code of the Original Work, as well as any notices of licensing and any descriptive text identified therein as an "Attribution Notice." You must cause the Source Code for any Derivative Works that You create to carry a prominent Attribution Notice reasonably calculated to inform recipients that You have modified the Original Work.
- 7. Warranty of Provenance and Disclaimer of Warranty. Licensor warrants that the copyright in and to the Original Work and the patent rights granted herein by Licensor are owned by the Licensor or are sublicensed to You under the terms of this License with the permission of the contributor(s) of those copyrights and patent rights. Except as expressly stated in the immediately proceeding sentence, the Original Work is provided under this License on an "AS IS" BASIS and WITHOUT WARRANTY, either express or implied, including, without limitation, the warranties of NON-INFRINGEMENT, MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. THE ENTIRE RISK AS TO THE QUALITY OF THE ORIGINAL WORK IS WITH YOU. This DISCLAIMER OF WARRANTY constitutes an essential part of this License. No license to Original Work is granted hereunder except under this disclaimer.
- 8. Limitation of Liability. Under no circumstances and under no legal theory, whether in tort (including negligence), contract, or otherwise, shall the Licensor be liable to any person for any direct, indirect, special, incidental, or consequential damages of any character arising as a result of this License or the use of the Original Work including, without limitation, damages for loss of goodwill, work stoppage, computer failure or malfunction, or any and all other commercial damages or losses. This limitation of liability shall not apply to liability for death or personal injury resulting from Licensor's negligence to the extent applicable law prohibits such limitation. Some jurisdictions do not allow the exclusion or limitation of incidental or consequential damages, so this

exclusion and limitation may not apply to You.

- 9. Acceptance and Termination. If You distribute copies of the Original Work or a Derivative Work, You must make a reasonable effort under the circumstances to obtain the express assent of recipients to the terms of this License. Nothing else but this License (or another written agreement between Licensor and You) grants You permission to create Derivative Works based upon the Original Work or to exercise any of the rights granted in Section 1 herein, and any attempt to do so except under the terms of this License (or another written agreement between Licensor and You) is expressly prohibited by U.S. copyright law, the equivalent laws of other countries, and by international treaty. Therefore, by exercising any of the rights granted to You in Section 1 herein, You indicate Your acceptance of this License and all of its terms and conditions.
- 10. Termination for Patent Action. This License shall terminate automatically and You may no longer exercise any of the rights granted to You by this License as of the date You commence an action, including a cross-claim or counterclaim, against Licensor or any licensee alleging that the Original Work infringes a patent. This termination provision shall not apply for an action alleging patent infringement by combinations of the Original Work with other software or hardware.
- 11.Jurisdiction, Venue and Governing Law. Any action or suit relating to this License may be brought only in the courts of a jurisdiction wherein the Licensor resides or in which Licensor conducts its primary business, and under the laws of that jurisdiction excluding its conflict-of-law provisions. The application of the United Nations Convention on Contracts for the International Sale of Goods is expressly excluded. Any use of the Original Work outside the scope of this License or after its termination shall be subject to the requirements and penalties of the U.S. Copyright Act, 17 U.S.C. § 101 et seq., the equivalent laws of other countries, and international treaty. This section shall survive the termination of this License.
- 12.Attorneys Fees. In any action to enforce the terms of this License or seeking damages relating thereto, the prevailing party shall be entitled to recover its costs and expenses, including, without limitation, reasonable attorneys' fees and costs incurred in connection with such action, including any appeal of such action. This section shall survive the termination of this License.
- 13. Miscellaneous. This License represents the complete agreement concerning the subject matter hereof. If any provision of this License is held to be unenforceable, such provision shall be reformed only to the extent necessary to make it enforceable.
- 14. Definition of "You" in This License. "You" throughout this License, whether in upper or lower case, means an individual or a legal entity exercising rights under, and complying with all of the terms of, this License. For legal entities, "You" includes any entity that controls, is controlled by, or is under common control with you. For purposes of this definition, "control" means (i) the power, direct or indirect, to cause the direction or management of such entity, whether by contract or otherwise, or (ii) ownership of fifty percent (50%) or more of the outstanding shares, or (iii) beneficial ownership of such entity.
- 15.Right to Use. You may use the Original Work in all ways not otherwise restricted or conditioned by this License or by law, and Licensor promises not to interfere with or be responsible for such uses by You.

This license is Copyright (C) 2003-2004 Lawrence E. Rosen. All rights reserved.

Permission is hereby granted to copy and distribute this license without modification. This license may not be modified without the express written permission of its copyright owner.

Zlib License

This software is provided 'as-is', without any express or implied warranty. In no event will the authors be held liable for any damages arising from the use of this software.

Permission is granted to anyone to use this software for any purpose, including commercial applications, and to alter it and redistribute it freely, subject to the following restrictions:

- 1. The origin of this software must not be misrepresented; you must not claim that you wrote the original software. If you use this software in a product, an acknowledgment in the product documentation would be appreciated but is not required.
- 2. Altered source versions must be plainly marked as such, and must not be misrepresented as being the original software.
- 3. This notice may not be removed or altered from any source distribution.

MPL-2.0

Mozilla Public License, version 2.0

- 1. Definitions
- 1.1. "Contributor"

means each individual or legal entity that creates, contributes to the creation of, or owns Covered Software.

1.2. "Contributor Version"

means the combination of the Contributions of others (if any) used by a Contributor and that particular Contributor's Contribution.

1.3. "Contribution"

means Covered Software of a particular Contributor.

1.4. "Covered Software"

means Source Code Form to which the initial Contributor has attached the notice in Exhibit A, the Executable Form of such Source Code Form, and Modifications of such Source Code Form, in each case including portions thereof.

- 1.5. "Incompatible With Secondary Licenses" means
 - a. that the initial Contributor has attached the notice described in Exhibit B to the Covered Software; or

- b. that the Covered Software was made available under the terms of version 1.1 or earlier of the License, but not also under the terms of a Secondary License.
- 1.6. "Executable Form"

means any form of the work other than Source Code Form.

1.7. "Larger Work"

means a work that combines Covered Software with other material, in a separate file or files, that is not Covered Software.

1.8. "License"

means this document.

1.9. "Licensable"

means having the right to grant, to the maximum extent possible, whether at the time of the initial grant or subsequently, any and all of the rights conveyed by this License.

1.10. "Modifications"

means any of the following:

- a. any file in Source Code Form that results from an addition to, deletion from, or modification of the contents of Covered Software; or
- b. any new file in Source Code Form that contains any Covered Software.
- 1.11. "Patent Claims" of a Contributor

means any patent claim(s), including without limitation, method, process, and apparatus claims, in any patent Licensable by such Contributor that would be infringed, but for the grant of the License, by the making, using, selling, offering for sale, having made, import, or transfer of either its Contributions or its Contributor Version.

1.12. "Secondary License"

means either the GNU General Public License, Version 2.0, the GNU Lesser General Public License, Version 2.1, the GNU Affero General Public License, Version 3.0, or any later versions of those licenses.

1.13. "Source Code Form"

means the form of the work preferred for making modifications.

1.14. "You" (or "Your")

means an individual or a legal entity exercising rights under this License. For legal entities, "You" includes any entity that controls, is controlled by, or is under common control with You. For purposes of this definition, "control" means (a) the power, direct or indirect, to cause the direction or management of such entity, whether by contract or otherwise, or (b) ownership of more than fifty percent (50%) of the outstanding shares or beneficial ownership of such entity.

2. License Grants and Conditions

2.1. Grants

Each Contributor hereby grants You a world-wide, royalty-free, non-exclusive license:

- a. under intellectual property rights (other than patent or trademark) Licensable by such Contributor to use, reproduce, make available, modify, display, perform, distribute, and otherwise exploit its Contributions, either on an unmodified basis, with Modifications, or as part of a Larger Work; and
- b. under Patent Claims of such Contributor to make, use, sell, offer for sale, have made, import, and otherwise transfer either its Contributions or its Contributor Version.

2.2. Effective Date

The licenses granted in Section 2.1 with respect to any Contribution become effective for each Contribution on the date the Contributor first distributes such Contribution.

2.3. Limitations on Grant Scope

The licenses granted in this Section 2 are the only rights granted under this License. No additional rights or licenses will be implied from the distribution or licensing of Covered Software under this License. Notwithstanding Section 2.1(b) above, no patent license is granted by a Contributor:

- a. for any code that a Contributor has removed from Covered Software; or
- b. for infringements caused by: (i) Your and any other third party's modifications of Covered Software, or (ii) the combination of its Contributions with other software (except as part of its Contributor Version); or
- c. under Patent Claims infringed by Covered Software in the absence of its Contributions.

This License does not grant any rights in the trademarks, service marks, or logos of any Contributor (except as may be necessary to comply with the notice requirements in Section 3.4).

2.4. Subsequent Licenses

No Contributor makes additional grants as a result of Your choice to distribute the Covered Software under a subsequent version of this License (see Section 10.2) or under the terms of a Secondary License (if permitted under the terms of Section 3.3).

2.5. Representation

Each Contributor represents that the Contributor believes its Contributions are its original creation(s) or it has sufficient rights to grant the rights to its Contributions conveyed by this License.

2.6. Fair Use

This License is not intended to limit any rights You have under applicable copyright doctrines of fair use, fair dealing, or other equivalents.

2.7. Conditions

Sections 3.1, 3.2, 3.3, and 3.4 are conditions of the licenses granted in Section 2.1.

3. Responsibilities

3.1. Distribution of Source Form

All distribution of Covered Software in Source Code Form, including any Modifications that You create or to which You contribute, must be under the terms of this License. You must inform recipients that the Source Code Form of the Covered Software is governed by the terms of this License, and how they can obtain a copy of this License. You may not attempt to alter or restrict the recipients' rights in the Source Code Form.

3.2. Distribution of Executable Form

If You distribute Covered Software in Executable Form then:

a. such Covered Software must also be made available in Source Code Form, as described in Section 3.1, and You must inform recipients of the Executable Form how they can obtain a copy of such Source Code Form by reasonable means in a timely manner, at a charge no more than the cost of distribution to the recipient; and b. You may distribute such Executable Form under the terms of this License, or sublicense it under different terms, provided that the license for the Executable Form does not attempt to limit or alter the recipients' rights in the Source Code Form under this License.

3.3. Distribution of a Larger Work

You may create and distribute a Larger Work under terms of Your choice, provided that You also comply with the requirements of this License for the Covered Software. If the Larger Work is a combination of Covered Software with a work governed by one or more Secondary Licenses, and the Covered Software is not Incompatible With Secondary Licenses, this License permits You to additionally distribute such Covered Software under the terms of such Secondary License(s), so that the recipient of the Larger Work may, at their option, further distribute the Covered Software under the terms of either this License or such Secondary License(s).

3.4. Notices

You may not remove or alter the substance of any license notices (including copyright notices, patent notices, disclaimers of warranty, or limitations of liability) contained within the Source Code Form of the Covered Software, except that You may alter any license notices to the extent required to remedy known factual inaccuracies.

3.5. Application of Additional Terms

You may choose to offer, and to charge a fee for, warranty, support, indemnity or liability obligations to one or more recipients of Covered Software. However, You may do so only on Your own behalf, and not on behalf of any Contributor. You must make it absolutely clear that any such warranty, support, indemnity, or liability obligation is offered by You alone, and You hereby agree to indemnify every Contributor for any liability incurred by such Contributor as a result of warranty, support, indemnity or liability terms You offer. You may include additional disclaimers of warranty and limitations of liability specific to any jurisdiction.

4. Inability to Comply Due to Statute or Regulation

If it is impossible for You to comply with any of the terms of this License with respect to some or all of the Covered Software due to statute, judicial order, or regulation then You must: (a) comply with the terms of this License to the maximum extent possible; and (b) describe the limitations and the code they affect. Such description must be placed in a text file included with all distributions of the Covered Software under this License. Except to the extent prohibited by statute or regulation, such description must be sufficiently detailed for a recipient of ordinary skill to be able to understand it.

5. Termination

- 5.1. The rights granted under this License will terminate automatically if You fail to comply with any of its terms. However, if You become compliant, then the rights granted under this License from a particular Contributor are reinstated (a) provisionally, unless and until such Contributor explicitly and finally terminates Your grants, and (b) on an ongoing basis, if such Contributor fails to notify You of the non-compliance by some reasonable means prior to 60 days after You have come back into compliance. Moreover, Your grants from a particular Contributor are reinstated on an ongoing basis if such Contributor notifies You of the non-compliance by some reasonable means, this is the first time You have received notice of non-compliance with this License from such Contributor, and You become compliant prior to 30 days after Your receipt of the notice.
- 5.2. If You initiate litigation against any entity by asserting a patent infringement claim (excluding declaratory judgment actions, counter-claims, and cross-claims) alleging that a Contributor Version directly or indirectly infringes any patent, then the rights granted to You by any and all Contributors for the Covered Software under Section 2.1 of this License shall terminate.
- 5.3. In the event of termination under Sections 5.1 or 5.2 above, all end user license agreements (excluding distributors and resellers) which have been validly granted by You or Your distributors under this License prior to termination shall survive termination.
- 6. Disclaimer of Warranty

Covered Software is provided under this License on an "as is" basis, without warranty of any kind, either expressed, implied, or statutory, including, without limitation, warranties that the Covered Software is free of defects, merchantable, fit for a particular purpose or non-infringing. The entire risk as to the quality and performance of the Covered Software is with You. Should any Covered Software prove defective in any respect, You (not any Contributor) assume the cost of any necessary servicing, repair, or correction. This disclaimer of warranty constitutes an essential part of this License. No use of any Covered Software is authorized under this License except under this disclaimer.

7. Limitation of Liability

Under no circumstances and under no legal theory, whether tort (including negligence), contract, or otherwise, shall any Contributor, or anyone who distributes Covered Software as permitted above, be liable to You for any direct, indirect, special, incidental, or consequential damages of any character including, without limitation, damages for lost profits, loss of goodwill, work stoppage, computer failure or malfunction, or any and all other commercial damages or losses, even if such party shall have been

informed of the possibility of such damages. This limitation of liability shall not apply to liability for death or personal injury resulting from such party's negligence to the extent applicable law prohibits such limitation. Some jurisdictions do not allow the exclusion or limitation of incidental or consequential damages, so this exclusion and limitation may not apply to You.

8. Litigation

Any litigation relating to this License may be brought only in the courts of a jurisdiction where the defendant maintains its principal place of business and such litigation shall be governed by laws of that jurisdiction, without reference to its conflict-of-law provisions. Nothing in this Section shall prevent a party's ability to bring cross-claims or counter-claims.

9. Miscellaneous

This License represents the complete agreement concerning the subject matter hereof. If any provision of this License is held to be unenforceable, such provision shall be reformed only to the extent necessary to make it enforceable. Any law or regulation which provides that the language of a contract shall be construed against the drafter shall not be used to construe this License against a Contributor.

10. Versions of the License

10.1. New Versions

Mozilla Foundation is the license steward. Except as provided in Section 10.3, no one other than the license steward has the right to modify or publish new versions of this License. Each version will be given a distinguishing version number.

10.2. Effect of New Versions

You may distribute the Covered Software under the terms of the version of the License under which You originally received the Covered Software, or under the terms of any subsequent version published by the license steward.

10.3. Modified Versions

If you create software not governed by this License, and you want to create a new license for such software, you may create and use a modified version of this License if you rename the license and remove any references to the name of the license steward (except to note that such modified license differs from this License).

10.4. Distributing Source Code Form that is Incompatible With Secondary

Licenses If You choose to distribute Source Code Form that is Incompatible With Secondary Licenses under the terms of this version of the License, the notice described in Exhibit B of this License must be attached.

Exhibit A - Source Code Form License Notice

This Source Code Form is subject to the terms of the Mozilla Public License, v. 2.0. If a copy of the MPL was not distributed with this file, You can obtain one at http://mozilla.org/MPL/2.0/.

If it is not possible or desirable to put the notice in a particular file, then You may include the notice in a location (such as a LICENSE file in a relevant directory) where a recipient would be likely to look for such a notice.

You may add additional accurate notices of copyright ownership.

Exhibit B - "Incompatible With Secondary Licenses" Notice

This Source Code Form is "Incompatible With Secondary Licenses", as defined by the Mozilla Public License, v. 2.0.